

**Section 12. Crowns: Measurements and Sampling**

12.1 OVERVIEW ..... 2  
12.2 CROWN DEFINITIONS..... 2  
12.3 CROWN DENSITY-FOLIAGE TRANSPARENCY CARD ..... 5  
12.4 CROWN RATING PRECAUTIONS ..... 6  
12.5 UNCOMPACTED LIVE CROWN RATIO..... 7  
12.6 CROWN LIGHT EXPOSURE..... 10  
12.7 CROWN POSITION ..... 12  
12.8 CROWN VIGOR CLASS..... 14  
12.9 CROWN DENSITY ..... 15  
12.10 CROWN DIEBACK ..... 17  
12.11 FOLIAGE TRANSPARENCY..... 20  
12.12 CONTACTS..... 22

## 12.1 OVERVIEW

Crown indicators are designed to be used together. Each indicator comprises a piece of information that can be used individually or as a factor in combination with other indicators. Each variable, alone or in combination with others, adds to the overall rating given each tree. It is important to realize that models are designed to rate trees on how they look, from thriving to almost dead and to help predict future conditions of trees and forest ecosystems.

VIGOR CLASS, UNCOMPACTED LIVE CROWN RATIO, CROWN LIGHT EXPOSURE and CROWN POSITION are determined for each sapling. Foliage below the point used for UNCOMPACTED LIVE CROWN RATIO is not considered in VIGOR CLASS determination. All sapling measurements are done during plot establishment and whenever plot remeasurement occurs.

Crown evaluations, including UNCOMPACTED LIVE CROWN RATIO, LIGHT EXPOSURE, POSITION, DENSITY, DIEBACK, and TRANSPARENCY are made on all trees with DBH/DRC (DRC in the West) 5.0 inches or larger. Trees with high scores for UNCOMPACTED LIVE CROWN RATIO and DENSITY, and low scores for DIEBACK and FOLIAGE TRANSPARENCY have increased potential for carbon fixation, nutrient storage and increased potential for survival and reproduction. Crown evaluations allow for the quantitative assessment of current tree conditions and provide an integrated measure of site conditions, stand density and influence of external stresses. All crown measurements are taken during plot establishment and whenever plot remeasurement occurs.

Note: This indicator is CORE OPTIONAL for all phase 2 plots.

Two persons make all crown measurements. Individuals should be ½ to 1 tree length from the base of the tree to obtain a good view of the crown. Move away from each other at least 10 feet to take these measurements. A position of 90 degrees to each other from the tree base is ideal (Figure 12.3). When estimates made by two individuals disagree, they should discuss the reasons for their ratings until an agreement is reached, or use the methods below to resolve the situation.

If the numbers for a crown measurement estimated by two crew members do not match, arrive at the final value by: (1) taking an average, if the numbers differ by 10 percent (2 classes) or less; (2) changing positions, if the numbers differ by 15 percent or more and attempting to narrow the range to 10 percent or less if crew members cannot agree; or (3) averaging the two estimates for those trees that actually have different ratings from the two viewing areas (ratings of 30 and 70 would be recorded as 50).

## 12.2 CROWN DEFINITIONS

### Crown Shape

Crown shape is the silhouette of a tree, drawn from branch tip to branch tip, which contains all of a tree's foliage as it grows in a stand. Exclude abnormally long branches beyond the edge of the crown for this silhouette. Normally, silhouettes are derived from vigorous, open grown trees and tend to be species-specific. For Phase 3 purposes, silhouettes vary with age and spacing. Tree crowns tend to flatten out with age and be more slender when growing in crowded conditions. Crown shape is important when measuring CROWN DENSITY and is used to estimate crown biomass. Crown shape is used as an outline for the sides of the tree.

### Crown Top

The crown top is the highest point of a standing tree. Young trees usually have more conical-shaped crowns and the main terminal is the top. Older trees and many hardwoods have globose and flat-topped crowns, where a lateral branch is the highest point. For some measurements the highest live foliage is considered the live crown top. Other measurements include a dead top. Some crown measurements assess how much of the expected crown is present and include broken or missing tops.

**Dieback**

This is recent mortality of branches with fine twigs, which begins at the terminal portion of a branch and proceeds toward the trunk. Dieback is only considered when it occurs in the upper and outer portions of the tree. When whole branches are dead in the upper crown, without obvious signs of damage such as breaks or animal injury, assume that the branches died from the terminal portion of the branch. Dead branches in the lower portion of the live crown are assumed to have died from competition and shading. Dead branches in the lower live crown are not considered as part of crown dieback, unless there is continuous dieback from the upper and outer crown down to those branches.

**Epicormic**

Shoot growth, from latent or suppressed buds, that arises from old branches, from the trunk or near large branch wounds or breaks. Epicormics remain epicormics until they regain the size of previous branches for trees with no branches 1.0 inch or larger in diameter at the base above the swelling. For trees that had 1.0 inch or larger branches when the epicormics formed, epicormics become branches once they reach 1.0 inch in diameter.

**Live Branch**

A live branch is any woody lateral growth supporting foliage, and is 1.0 inch or larger in diameter at the base above the swelling where it joins a main stem or larger branch. Small trees or certain tree species greater than 5.0 inches DBH/DRC may have only live twigs which have not yet reached 1.0 inch or larger at the point of attachment. If the death of larger branches is not the cause of these twigs, the twigs are considered branches for these smaller branched trees until the tree matures to a point where twigs have attained 1.0 inch or larger in diameter at the base above the swelling where it joins a main stem or larger branch.

**Live Crown Base**

The live crown base is an imaginary horizontal line drawn across the trunk from the bottom of the lowest live foliage of the "obvious live crown" for trees and from the lowest live foliage of the lowest twig for saplings. The "obvious live crown" is described as the point on the tree where most live branches/twigs above that point are continuous and typical for a tree species (and/or tree size) on a particular site. Include most crown branches/twigs, but exclude epicormic twigs/sprigs and straggler branches that usually do not contribute much to the tree's growth. The base of the live branch/twig bearing the lowest foliage may be above or below this line.

For trees 5.0 inches DBH/DRC or greater, if any live branch is within 5 feet below this "obvious live crown" line, a new horizontal line is established. Create the new line at the base of live foliage on that branch. Continue this evaluation process until no live branches are found within 5 feet of the foliage of the lowest qualifying branch (Figure 12-1).

Occasionally, all original major crown branches/twigs are dead or broken and many new twigs/sprigs develop. These situations are likely to occur in areas of heavy thinning, commercial clearcuts and severe weather damage:

- Trees that had an "obvious live crown" with live branches now have no crown to measure until the new live twigs become live branches. When these new live branches appear, draw the new live crown base to the live foliage of the lowest live branch that now meets the 5-foot rule.
- Saplings and small trees that had only live twigs should establish the crown base at the base of the live foliage on the new lowest live twig. If no live twigs are present, there is no crown to measure.

DETERMINING CROWN BASE & USE OF 5' RULE




Figure 12-1. Determining the base of the live crown.

**Overstory Canopy Zone**

The area delineated by the average live crown height determined from the UNCOMPACTED LIVE CROWN RATIO of overstory trees. The bottom of the overstory canopy zone is the average height of the live crown bases. The top of the zone is the average height for the live crown tops.

**Snag Branch**

A dead upper crown branch without twigs or sprigs attached to it. A lower branch on woodland trees such as juniper is not considered a snag branch unless the branch reaches into the upper crown, or reached into the upper crown when the branch was alive. A branch that died due to shading in any crown is not a snag branch.

**Sprig**


Any woody or non-woody lateral growth, without secondary branching, less than 1.0 inch in diameter at the base above the swelling at the point of attachment to a branch or crown stem.

**Twig**

Any woody lateral growth, with secondary branching, less than 1.0 inch in diameter at the base above the swelling at the point of attachment to a branch or crown stem.

12.3 CROWN DENSITY-FOLIAGE TRANSPARENCY CARD

Front



Back




Figure 12-2. Density-Transparency card

The crown density - foliage transparency card (Figure 12-2) should be used as a training aid until crew personnel are comfortable with all ratings. White areas of the card represent skylight visible through the crown area and black areas represent a portion of the tree that is blocking skylight. After training, use the card to calibrate your eyes at the start of each day and rate those trees that do not fit into an obvious class. For CROWN DENSITY, hold the card so that "Crown Density" is right-side up ("Foliage Transparency" should be upside down). Use the numbers that are right-side up. Conversely, for FOLIAGE TRANSPARENCY, make sure that "Foliage Transparency" is right-side up. Crews should refer to specific CROWN DENSITY or FOLIAGE TRANSPARENCY sections for a definition of aspects that are included in the crown rating.

The back of the crown density - foliage transparency card has two uses: for CROWN DENSITY when a portion of the crown is missing and a general scale for estimating UNCOMPACTED LIVE CROWN RATIO. Crews should refer to the CROWN DENSITY and UNCOMPACTED LIVE CROWN RATIO sections for the use of this side of the card.

## 12.4 CROWN RATING PRECAUTIONS

Crews must be especially careful when making evaluations, and pay special attention to certain factors that may affect measurements in the field. These factors include:

- Distance and slope from the tree
- View of the crown
- Climatic conditions
- Heavy defoliation
- Leaning trees
- Trees with no "crown" by definition

### Distance and slope from the tree -

Crews must attempt to stay at least 1/2 to 1 tree length from the tree being evaluated. Some ratings change with proximity to the tree. In some situations, it is impossible to satisfy this step, but the crew should do the best it can in each case. All evaluations are made at grade (same elevation as base of the tree) or up slope from the tree. This may not be possible in all cases but evaluating trees from the down slope side should be avoided.

### View of the crown -

Crew members should evaluate trees when standing at an angle to each other, striving to obtain the best view of the crown. The ideal positions are at 90 degrees to each other on flat terrain (Figure 12-3). If possible, never evaluate the tree from the same position or at 180 degrees. In a thick canopy forest, getting a good perspective of the crown becomes difficult. Overlapping branches, background trees and lack of a good viewing area can cause problems when rating some trees. Crews need to move laterally to search for a good view. Take special care when rating such trees.




Figure 12-3. Crew positions for viewing crowns.

**Climatic conditions -**

Cloudy or overcast skies, fog, rain and poor sun angles may affect the accuracy of crown estimates. Crews need to be especially careful during poor lighting conditions to obtain the best possible view of the crown for the given climate conditions.

**Heavy defoliation -**

During heavy defoliation, CROWN DIEBACK may be overestimated and FOLIAGE TRANSPARENCY may be underestimated due to the difficulty in differentiating dead twigs from defoliated twigs. The use of binoculars may help in separating dead twigs from defoliated twigs.

**Leaning trees -**

So that crown dimensions are measured consistently on both leaning and upright trees, UNCOMPACTED LIVE CROWN RATIO and CROWN DENSITY for leaning and down trees must be rated in relation to the actual length of the tree bole (as opposed to height above the ground). CROWN POSITION and CROWN LIGHT EXPOSURE should still be estimated relative to the tree's actual location in the canopy. FOLIAGE TRANSPARENCY will rarely be affected by lean angle. Place a note in the PDR TREE NOTES field that the tree is leaning if it is leaning more than 45 degrees from vertical.

**Trees with no "crown" by definition (epicormics or sprigs only) -**

After a sudden release or damage, a tree may have very dense foliage, but no crown. The following combination of codes is a flag for trees with no crowns:

- UNCOMPACTED LIVE CROWN RATIO = 00
- CROWN LIGHT EXPOSURE = 0
- CROWN POSITION = 3
- CROWN DENSITY = 00
- CROWN DIEBACK = 99
- FOLIAGE TRANSPARENCY = 99

After a sudden release or damage, a sapling may have very dense foliage, but no crown as it only has sprigs. The following combination of codes is a flag for saplings with no crowns:

- UNCOMPACTED LIVE CROWN RATIO = 00
- CROWN LIGHT EXPOSURE = 0
- CROWN POSITION = 3
- VIGOR = 3

**12.5 UNCOMPACTED LIVE CROWN RATIO**

UNCOMPACTED LIVE CROWN RATIO is a percentage determined by dividing the live crown length by the actual tree length (Figure 12-5). UNCOMPACTED LIVE CROWN RATIO for leaning and down trees must be rated in relation to the actual length of the tree bole (as opposed to height above the ground.) Record the UNCOMPACTED LIVE CROWN RATIO to the nearest 1%.

**Saplings**

Determine sapling UNCOMPACTED LIVE CROWN RATIO by dividing the live crown length by actual tree length, then enter the appropriate code into the PDR. Live crown length is the distance between the top live foliage (dieback and dead branches are not included) and the lowest live foliage on the lowest live twig for saplings. Be sure to eliminate vine foliage as best you can when determining the live crown. The live crown base for saplings is different from trees 5.0 inches DBH/DRC and larger. The 5-foot/1-inch rule does not apply in this case. Do not include sprigs or leaves on the main stem below the lowest live twig (Figure 12-4).

When the two estimates do not agree, follow the guidelines listed at the end of section 12.1 *Overview*.




Figure12-4. Sapling UNCOMPACTED LIVE CROWN RATIO determination examples.






Figure 12-5. UNCOMPACTED LIVE CROWN RATIO examples.

### Trees

Live crown length is the distance from the live crown top (dieback in the upper portion of the crown is not part of the live crown) to the "obvious live crown" base (Figure 12-6). Many times there are additional live branches below the "obvious live crown". These branches are only included if they have a basal diameter greater than 1.0 inch and are within 5.0 feet of the base of the obvious live crown (Figure 12-1). The live crown base becomes that point on the main bole perpendicular to the lowest live foliage on the last branch that is included in the live crown. The live crown base is determined by the live foliage and not by the point where a branch intersects with the main bole. Occasionally, small trees or certain species may not have 1.0-inch diameter branches. If this occurs, use the 5.0-foot rule, and apply it to branches that you feel contribute significantly to tree growth.

An individual can use the UNCOMPACTED LIVE CROWN RATIO scale on the back of the crown density - foliage transparency card to help estimate ratios (Figure 12-2). Hold the card in one hand, parallel to the trunk of the tree being evaluated and move the card closer or farther from your eye until the 0 is at the live crown top and the 99 is at the base of the tree where it meets the ground. Then place your finger at the live crown base. A clinometer can also be used to verify the UNCOMPACTED LIVE CROWN RATIO by determining the values of both lengths and determining the ratio of the two values.

When estimates between crew members do not agree, follow the guidelines listed at the end of section 12.1 *Overview*.




Figure 12-6. UNCOMPACTED LIVE CROWN RATIO outline and rating examples

When collected: All live trees  $\geq 1.0$  in DBH/DRC  
Field width: 2 digits  
Tolerance: +/- 10%  
MQO: At least 90% of the time  
Values: 00 to 99 percent

## 12.6 CROWN LIGHT EXPOSURE

As illustrated in Figure 12-7, visually divide the crown vertically into four equal quarters (25 percent of the crown circumference.) Rate the UNCOMPACTED LIVE CROWN RATIO for each quarter separately using the criteria for estimating total UNCOMPACTED LIVE CROWN RATIO. In order for an individual quarter to be tallied, that quarter must have an uncompacted live crown ratio of at least 35 percent. Additionally for a quarter to be counted as receiving full light, a continuous portion of live crown (at least 35 percent of the actual tree length) would be completely exposed to direct light if the sun were directly above the tree. Try to divide the crown in such a way that as many quarters as possible receive full light. Count the number of quarters that qualify as receiving full light. Add one if the tree receives direct light from the top.

For this measurement, crown shape cannot result in a tree shading itself (e.g., umbrella-shaped trees.) For down trees or trees with severe lean, do not count any quarters that face the ground.




Figure 12-7. Dividing the crown.

Note: A sliver of a quarter receiving light does not qualify (Figure 12-8). Trees with all quarters having less than a 35 percent UNCOMPACTED LIVE CROWN RATIO can have a maximum crown exposure of one. Individual quarters with less than 35 percent UNCOMPACTED LIVE CROWN RATIO should not be counted (Figure 12-8).




Figure 12-8. CROWN LIGHT EXPOSURE.

When collected: All live trees  $\geq 1.0$  in DBH/DRC  
 Field width: 1 digit  
 Tolerance: within 1 if  $> 0$   
 MQO: At least 85% of the time

Values:

<u>Code</u>	<u>Definition</u>
0	The tree receives no full light because it is shaded by trees, vines, or other vegetation; the tree has no crown by definition.
1	The tree receives full light from the top or 1 quarter.
2	The tree receives full light from the top and 1 quarter (or 2 quarters without the top).
3	The tree receives full light from the top and 2 quarters (or 3 quarters without the top).
4	The tree receives full light from the top and 3 quarters.
5	The tree receives full light from the top and 4 quarters.

### **12.7 CROWN POSITION**

Determine the relative position of each tree in relation to the overstory canopy zone (Figure 12-9). Codes 1-3 should be used in stands where the tree crown cover is closed (>50 percent cover). If the tree crowns are not closed (<50 percent cover) and the area is greater than 1 acre in size, then assign code 4. When code 4 is used, it is assigned to all trees in the stand except trees with no crown by definition (see 'Trees with no crown by definition...' in section 12.4). Code 4 is typically used in the following cases:

- Trees and saplings in stands, over 1 acre in size, where crown cover is less than 50 percent.
- Trees and saplings in clumps less than 1 acre in size (i.e., not a condition class) when the overall forest (the condition class), over 1 acre in size, is a patchwork of open areas and clumps of trees.

Code 1 is not used for saplings. For a leaning tree, CROWN POSITION should be estimated relative to the tree's actual location in the canopy.




Figure 12-9. CROWN LIGHT EXPOSURE and CROWN POSITION.

When collected: All live trees  $\geq 1.0$  in DBH/DRC

Field width: 1 digit

Tolerance: No errors

MQO: At least 85% of the time

Values:

Code	Definition
1	Superstory. The live crown top must be two times the height of the top of the overstory canopy zone. The tree is open grown because most of the crown is above the overstory canopy zone (pioneers, seed trees, whips, remnants from previous stands, etc.). NOT USED FOR SAPLINGS.
2	Overstory. The live crown top is above the middle of the overstory canopy zone.
3	Understory. The live crown top is at or below the middle of the overstory canopy zone, or tree has no crown by definition.
4	Open Canopy. An overstory canopy zone is not evident because the tree crowns in this condition are not fully closed (<50% cover). Most of the trees in this stand are not competing with each other for light.

## 12.8 CROWN VIGOR CLASS

See Figure 12-10 for a visual description of the sapling CROWN VIGOR classes.




Figure 12-10. Sapling CROWN VIGOR classes.

When collected: All live trees  $\geq 1.0$  in DBH/DRC and  $< 5.0$  in DBH/DRC

Field width: 1 digit

Tolerance: No errors

MQO: At least 90% of the time

Values:

Class/Code	Definition
1	Saplings <u>must have an UNCOMPACTED LIVE CROWN RATIO of 35 or higher</u> , have less than 5 percent DIEBACK (deer/rabbit browse is not considered as dieback but is considered missing foliage) and 80 percent or more of the foliage present is normal or at least 50 percent of each leaf is not damaged or missing. Twigs and branches that are dead because of normal shading are not included.
2	Saplings do not meet Class 1 or 3 criteria. They may have any UNCOMPACTED LIVE CROWN RATIO, may or may not have DIEBACK and may have between 21 and 100 percent of the foliage classified as normal.
3	Saplings may have any UNCOMPACTED LIVE CROWN RATIO and have 1 to 20 percent normal foliage or the percent of foliage missing combined with the percent of leaves that are over 50 percent damaged or missing should equal 80 percent or more of the live crown. Twigs and branches that are dead because of normal shading are not included. Code is also used for saplings that have no crown by definition.

## 12.9 CROWN DENSITY

CROWN DENSITY estimates crown condition in relation to a typical tree for the site where it is found. CROWN DENSITY also serves as an indicator of expected growth in the near future. CROWN DENSITY is the amount of crown branches, foliage and reproductive structures that blocks light visibility through the crown. Each tree species has a normal crown that varies with the site, genetics, tree damage, etc.

To determine the crown shape, select the crown base on the stem used for UNCOMPACTED LIVE CROWN RATIO. Project a full "mirror image" around the central axis of the main crown stem based on that tree's shape. Include missing or dead tops. Project half-sided trees as full crowns by using the "mirror image" of the existing half of the crown. Foliage below the crown base is not included (Figure 12-1). Include CROWN DIEBACK and open areas in this outline (Figures 12-11 and 12-12). The central axis of the crown usually runs along the length of the tree bole for leaning trees. This axis may be bowed for trees with severe sweep.

After determining the crown shape, each person should use the crown density - foliage transparency card (Figure 12-2). Along the line of sight, estimate what percentage of the outlined area is blocking sunlight. In cases where portions of the tree may be missing, i.e., half-sided trees, it may be easier to determine the percent of the crown shape missing and the actual density of the tree's remaining portion. Then use the table on the back of the crown density - foliage transparency card to arrive at the final CROWN DENSITY. When two individuals disagree with their estimates, follow the guidelines listed at the end of section 12.1 *Overview*. The estimate is placed into one of 21 percentage classes.




Figure 12-11. CROWN DENSITY rating outline examples.






Figure 12-12. Crown density outline and rating examples

When collected: All live trees  $\geq 5.0$  in DBH/DRC  
 Field width: 2 digits  
 Tolerance: +/- 10% (2 classes)  
 MQO: At least 90% of the time  
 Values:

Code	Definition	Code	Definition	Code	Definition
00	No crown	35	31-35%	70	66-70%
05	1-5%	40	36-40%	75	71-75%
10	6-10%	45	41-45%	80	76-80%
15	11-15%	50	46-50%	85	81-85%
20	16-20%	55	51-55%	90	86-90%
25	21-25%	60	56-60%	95	91-95%
30	26-30%	65	61-65%	99	96-100%

Note: Class code is the percentage of the upper limits of the class, i.e., Code 10 is 6% to 10%, etc

### 12.10 CROWN DIEBACK

CROWN DIEBACK estimates reflect the severity of recent stresses on a tree. Estimate CROWN DIEBACK as a percentage of the live crown area, including the dieback area. The crown base should be the same as that used for the UNCOMPACTED LIVE CROWN RATIO estimate. Assume the perimeter of the crown is a two-dimensional outline from branch-tip to branch-tip, excluding snag branches and large holes or gaps in the crown (Figures 12-13 and 12-14).

Project a two-dimensional crown outline, block in the dieback and estimate the dieback area. When two individuals disagree with their estimates, follow the guidelines listed at the end of section 12.1 *Overview*. The estimate is placed into one of 21 percentage classes.




Figure 12-13. CROWN DIEBACK rating outline examples.




Figure 12-14. Dieback outline and rating examples.

When collected: All live trees  $\geq 5.0$  in DBH/DRC  
 Field width: 2 digits  
 Tolerance: +/- 10% (2 classes)  
 MQO: At least 90% of the time  
 Values:

Code	Definition	Code	Definition	Code	Definition
00	0%	35	31-35%	70	66-70%
05	1-5%	40	36-40%	75	71-75%
10	6-10%	45	41-45%	80	76-80%
15	11-15%	50	46-50%	85	81-85%
20	16-20%	55	51-55%	90	86-90%
25	21-25%	60	56-60%	95	91-95%
30	26-30%	65	61-65%	99	96-100%

Note: Class code is the percentage of the upper limits of the class, i.e., Code 10 is 6% to 10%, etc.

### 12.11 FOLIAGE TRANSPARENCY

Foliage transparency is the amount of skylight visible through the live, normally foliated portion (where you see foliage, normal or damaged, or remnants of its recent presence) of the crown. A recently defoliated tree except for one or two live leaves should have a transparency rating of 99 not 0!! (See coding for 'Trees with no crown by definition...' in section 12.4.) Check with binoculars to assess which branches are alive and should have foliage.

Different tree species have a normal range of foliage transparency, which may be more or less than that of other species. Changes in foliage transparency can also occur because of current defoliation or stresses during the current or preceding years.

Estimate FOLIAGE TRANSPARENCY using the crown density - foliage transparency card (Figure 12-2). Exclude vine foliage from the transparency estimate as best you can. Dead branches in the lower live crown, snag branches, crown dieback and missing branches or areas where foliage is expected to be missing are deleted from the estimate (Figure 12-15).

When defoliation is severe, branches alone will screen the light, but you should exclude the branches from the foliage outline and rate the area as if the light was penetrating those branches. For example, an almost completely defoliated dense spruce may have less than 20 percent skylight coming through the crown, but it will be rated as highly transparent because of the missing foliage. Old trees and some hardwood species, have crowns with densely foliated branches that are widely spaced. These spaces between branches should not be included in the FOLIAGE TRANSPARENCY rating. When FOLIAGE TRANSPARENCY in one part of the crown differs from another part, the average FOLIAGE TRANSPARENCY is estimated.

Project a two-dimensional crown outline. Determine the foliated area within the crown outline and estimate the transparency of the normally foliated area.




Figure 12-15. FOLIAGE TRANSPARENCY rating outline examples.

When collected: All live trees  $\geq 5.0$  in DBH/DRC  
 Field width: 2 digits  
 Tolerance: +/- 10% (2 classes)  
 MQO: At least 90% of the time  
 Values:

Code	Definition	Code	Definition	Code	Definition
00	0%	35	31-35%	70	66-70%
05	1-5%	40	36-40%	75	71-75%
10	6-10%	45	41-45%	80	76-80%
15	11-15%	50	46-50%	85	81-85%
20	16-20%	55	51-55%	90	86-90%
25	21-25%	60	56-60%	95	91-95%
30	26-30%	65	61-65%	99	96-100%

Note: Class code is the percentage of the upper limits of the class, i.e., Code 10 is 6% to 10%, etc.

## 12.12 CONTACTS

National Crown Indicator Advisors:

William A. Bechtold  
USDA Forest Service  
Southern Research Station  
200 Weaver Blvd.  
Asheville, NC 28804  
phone: 828-257-4357  
fax: 828-257-4894  
email: [wabechtold@fs.fed.us](mailto:wabechtold@fs.fed.us)

KaDonna Randolph  
USDA Forest Service  
Southern Research Station, FIA  
4700 Old Kingston Pike  
Knoxville, TN 37919  
phone: 865-862-2024  
fax: 865-862-0262  
email: [krandolph@fs.fed.us](mailto:krandolph@fs.fed.us)