

170-TP-601-001

**HDF-EOS Library Users Guide
for the ECS Project
Volume 2: Function Reference Guide**

Technical Paper

November 2000

Prepared Under Contract NAS5-60000

RESPONSIBLE ENGINEER

<u>Larry Klein /s/</u>	11/20/00
David Wynne, Abe Taaheri, Alex Muslimov Xin-Min Hua, Ray Milburn, and Larry Klein EOSDIS Core System Project	Date

SUBMITTED BY

<u>William Knauss /s/</u>	11/21/00
Will Knauss, Director of Development EOSDIS Core System Project	Date

Raytheon Company
Upper Marlboro, Maryland

This page intentionally left blank.

Preface

This document is a Users Guide for HDF-EOS (Hierarchical Data Format - Earth Observing System) library tools. HDF is the scientific data format standard selected by NASA as the baseline standard for EOS. This Users Guide accompanies Version 2 software, which is available to the user community on the EDHS1 server. These library is aimed at EOS data producers and consumers, who will develop their data into increasingly higher order products. These products range from calibrated Level 1 to Level 4 model data. The primary use of the HDF-EOS library will be to create structures for associating geolocation data with their associated science data. This association is specified by producers through use of the supplied library. Most EOS data products which have been identified, fall into categories of grid, point or swath structures, which are implemented in the current version of the library. Services based on geolocation information will be built on HDF-EOS structures. Producers of products not covered by these structures, e.g. non-geolocated data, can use the standard HDF libraries.

In the ECS (EOS Core System) production system, the HDF-EOS library will be used in conjunction with SDP (Science Data Processing) Toolkit software. The primary tools used in conjunction with HDF-EOS library will be those for metadata handling, process control and status message handling. Metadata tools will be used to write ECS inventory and granule specific metadata into HDF-EOS files, while the process control tools will be used to access physical file handles used by the HDF tools. (*SDP Toolkit Users Guide for the ECS Project, February, 2000, 333-CD-510-001*).

HDF-EOS is an extension of NCSA (National Center for Supercomputing Applications) HDF and uses HDF library calls as an underlying basis. Version 4.1r3 of HDF is used. The library tools are written in the C language and a Fortran interface is provided. The current version contains software for creating, accessing and manipulating Grid, Point and Swath structures. This document includes overviews of the interfaces, and code examples. EOSView, the HDF-EOS viewing tool, has been revised to accommodate the current version of the library.

Technical Points of Contact within EOS are:

Larry Klein, larry@eos.hitc.com

David Wynne, davidw@eos.hitc.com

Abe Taaheri, ataaheri@eos.hitc.com

Alex Muslimov, amuslivo@eos.hitc.com

An email address has been provided for user help:

pgstlk@eos.hitc.com

Any questions should be addressed to:

Data Management Office
The ECS Project Office
Raytheon Systems Company
1616 McCormick Drive
Upper Marlboro, MD 20774-5301

This page intentionally left blank.

Abstract

This document will serve as the user's guide to the HDF-EOS file access library. HDF refers to the scientific data format standard selected by NASA as the baseline standard for EOS, and HDF-EOS refers to EOS conventions for using HDF. This document will provide information on the use of the three interfaces included in HDF-EOS - Point, Swath, and Grid - including overviews of the interfaces, and code examples. This document should be suitable for use by data producers and data users alike.

Keywords: HDF-EOS, Metadata, Standard Data Format, Standard Data Product, Disk Format, Point, Grid, Swath, Projection, Array, Browse

This page intentionally left blank

Change Information Page

List of Effective Pages			
Page Number	Issue		
Title	Submitted as Final		
iii through x	Submitted as Final		
1-1 through 1-12	Submitted as Final		
2-1 through 2-180	Submitted as Final		
AB-1 through AB-4	Submitted as Final		
Document History			
Document Number	Status/Issue	Publication Date	CCR Number
170-TP-601-001	Submitted as Final	November 2000	00-0245

This page intentionally left blank.

Contents

Preface

Abstract

1. Introduction

1.1	Purpose	1-1
1.2	Organization.....	1-1
1.3	Point Data.....	1-1
	1.3.1 PT API Routines.....	1-1
	1.3.2 List of PT API Routines	1-1
1.4	Swath Data	1-3
	1.4.1 The Swath Data Interface	1-3
	1.4.2 List of SW API Routines.....	1-3
1.5	Grid Data	1-5
	1.5.1 The Grid Data Interface.....	1-5
	1.5.2 List of Grid API ROUTINES	1-5
1.6	GCTP Usage.....	1-7
	1.6.1 GCTP Projection Codes	1-7
	1.6.2 UTM Zone Codes.....	1-8
	1.6.3 GCTP Spheroid Codes	1-8
	1.6.4 GCTP Projection Parameters	1-9

2. Function Reference

2.1	Format	2-1
	2.1.1 Point Interface Functions.....	2-1
	2.1.2 Swath Interface Functions	2-42
	2.1.3 Grid Interface Functions.....	2-107
	2.1.4 HDF-EOS Utility Routines	2-172

List of Tables

1-1	Summary of the Point Interface.....	1-2
1-2	Summary of the Swath Interface	1-4
1-3	Summary of the Grid Interface.....	1-6
1-4	Projection Transformation Package Projection Parameters	1-9

Abbreviations and Acronyms

1. Introduction

1.1 Purpose

The *HDF-EOS Software Reference Guide for the ECS Project* was prepared under the Earth Observing System Data and Information System (EOSDIS) Core System (ECS), Contract (NAS5-60000).

This software reference guide is intended for use by anyone who wishes to use the HDF-EOS library to create or read EOS data products. Users of this document will include EOS instrument team science software developers and data product designers, DAAC personnel, and end users of EOS data products such as scientists and researchers.

1.2 Organization

This paper is organized as follows:

- Section 1 Introduction - Presents Scope and Purpose of this document
- Section 2 Function Reference
- Abbreviations and Acronyms

1.3 Point Data

The PT (*Point*) interface consists of routines for storing, retrieving, and manipulating data in point data sets. This interface is designed to support data that has associated geolocation information, but is not organized in any well defined spatial or temporal way. See the Users' Guide, Volume 1 that accompanies this document for more information.

1.3.1 PT API Routines

All C routine names in the point data interface have the prefix "PT" and the equivalent FORTRAN routine names are prefixed by "pt." The PT routines are classified into the following categories:

- **Access routines** initialize and terminate access to the PT interface and point data sets (including opening and closing files).
- **Definition** routines allow the user to set key features of a point data set.
- **Basic I/O** routines read and write data and metadata to a point data set.
- **Index I/O** routines read and write information which links two tables in a point data set.
- **Inquiry** routines return information about data contained in a point data set.
- **Subset** routines allow reading of data from a specified geographic region.

1.3.2 List of PT API Routines

The PT function calls are listed below in Table 1-1 and are described in detail in Section 2 of this

document. The listing in Section 2 is in alphabetical order.

Table 1-1. Summary of the Point Interface

Category	Routine Name		Description	Page Nos.
	C	FORTRAN		
Access	PTopen	ptopen	creates a new file or opens an existing one	2-29
	PTcreate	ptcreate	creates a new point data set and returns a handle	2-6
	PTattach	ptattach	attaches to an existing point data set	2-2
	PTdetach	ptdetach	releases a point data set and frees memory	2-15
	PTclose	ptclose	closes the HDF-EOS file and deactivates the point interface	2-5
Definition	PTdeflevel	ptdeflev	defines a level within the point data set	2-8
	Ptdeflinkage	ptdeflink	defines link field to use between two levels	2-10
	Ptdefvrregion	ptdefvrreg	defines a vertical subset region	2-13
Basic I/O	Ptwritelevel	ptwlev	writes (appends) full records to a level	2-41
	Ptreadlevel	ptrdlev	reads data from the specified fields and records of a level	2-33
	Ptupdatelevel	ptuplev	updates the specified fields and records of a level	2-37
	Ptwriteattr	ptwrattr	creates or updates an attribute of the point data set	2-39
	Ptreadattr	ptrdattr	reads existing attribute of point data set	2-32
Inquiry	Ptnlevels	ptnlevs	returns the number of levels in a point data set	2-27
	Ptnrecs	ptnrecs	returns the number of records in a level	2-28
	Ptnfields	ptnflds	returns number of fields defined in a level	2-26
	Ptlevelinfo	ptlevinfo	returns information about a given level	2-25
	Ptlevelindx	ptlevidx	returns index number for a named level	2-24
	Ptbcklinkinfo	ptblinkinfo	returns link field to previous level	2-4
	Ptfwdlinkinfo	ptfwdlinkinfo	returns link field to following level	2-18
	Ptgetlevelname	ptgetlevname	returns level name given level number	2-19
	Ptsizeof	ptsizeof	returns size in bytes for specified fields in a point	2-36
	Ptattrinfo	ptattrinfo	returns information about point attributes	2-3
Utility	Ptingattr	ptingattr	retrieves number and names of attributes defined	2-22
	Ptingpoint	ptingpoint	retrieves number and names of points in file	2-23
Subset	Ptgetrecnums	ptgetrecnums	returns corresponding record numbers in a related level	2-20
Subset	Ptdefboxregion	ptdefboxreg	define region of interest by latitude/longitude	2-7
	Ptregioninfo	ptreginfo	returns information about defined region	2-34
	Ptregionrecs	ptregrecs	returns # of records and record #'s within region	2-35
	Ptextractregion	ptextreg	read a region of interest from a set of fields in a single level	2-17
	PTdeftimeperiod	ptdeftmep	define time period of interest	2-11
	PTperiodinfo	ptperinfo	returns information about defined time period	2-30
	PTperiodrecs	ptperrecs	returns # of records and record #'s within time period	2-31
	PTexttractperiod	ptextper	read a time period from a set of fields in a single level	2-16

1.4 Swath Data

The SW (*Swath*) interface consists of routines for storing, retrieving, and manipulating data in swath data sets. This interface is tailored to support time-ordered data such as satellite swaths (which consist of a time-ordered series of scanlines), or profilers (which consist of a time-ordered series of profiles). See the Users' Guide, Volume 1 that accompanies this document for more information.

1.4.1 The Swath Data Interface

All C routine names in the swath data interface have the prefix "SW" and the equivalent FORTRAN routine names are prefixed by "sw." The SW routines are classified into the following categories:

- **Access routines** initialize and terminate access to the SW interface and swath data sets (including opening and closing files).
- **Definition** routines allow the user to set key features of a swath data set.
- **Basic I/O** routines read and write data and metadata to a swath data set.
- **Inquiry** routines return information about data contained in a swath data set.
- **Subset** routines allow reading of data from a specified geographic region.

1.4.2 List of SW API Routines

The SW function calls are listed below in Table 1-2 and are described in detail in Section 2 of this document. The listing in Section 2 is in alphabetical order.

Table 1-2. Summary of the Swath Interface (1 of 2)

Category	Routine Name		Description	Page Nos.
	C	FORTRAN		
Access	SWopen	swopen	opens or creates HDF file in order to create, read, or write a swath	2-83
	SWcreate	swcreate	creates a swath within the file	2-46
	SWattach	swattach	attaches to an existing swath within the file	2-42
	SWdetach	swdetach	detaches from swath interface	2-64
	SWclose	swclose	closes file	2-44
Definition	SWdefdim	swdefdim	defines a new dimension within the swath	2-53
	SWdefdimmap	swdefmap	defines the mapping between the geolocation and data dimensions	2-54
	SWdefidxmap	swdefimap	defines a non-regular mapping between the geolocation and data dimension	2-58
	SWdefgeofield	swdefgfd	defines a new geolocation field within the swath	2-56
	SWdefdatafield	swdefdfld	defines a new data field within the swath	2-51
	SWdefcomp	swdefcomp	defines a field compression scheme	2-49
	SWwritegeometa	swwrgmeta	writes field metadata for an existing swath geolocation field	2-102
	SWwritedatameta	swwrdatmeta	writes field metadata for an existing swath data field	2-98
Basic I/O	SWwritefield	swwrfld	writes data to a swath field	2-99
	SWreadfield	swrdfld	reads data from a swath field.	2-87
	SWwriteattr	swrrattr	writes/updates attribute in a swath	2-96
	SWreadattr	swrdattr	reads attribute from a swath	2-86
	SWsetfillvalue	swsetfill	sets fill value for the specified field	2-93
	SWgetfillvalue	swgetfill	retrieves fill value for the specified field	2-71
Inquiry	SWinqdims	swinqdims	retrieves information about dimensions defined in swath	2-76
	SWinqmaps	swinqmaps	retrieves information about the geolocation relations defined	2-79
	SWinqidxmaps	swinqimaps	retrieves information about the indexed geolocation/data mappings defined	2-78
	SWinqgeofields	swinqgfd	retrieves information about the geolocation fields defined	2-77
	SWinqdatafields	swinqdfld	retrieves information about the data fields defined	2-75
	SWinqattrs	swinqattrs	retrieves number and names of attributes defined	2-74
	SWnentries	swnentries	returns number of entries and descriptive string buffer size for a specified entity	2-82
	SWdiminfo	swdiminfo	retrieve size of specified dimension	2-65
	SWmapinfo	swmapinfo	retrieve offset and increment of specified geolocation mapping	2-81
	SWidxmapinfo	swimapinfo	retrieve offset and increment of specified geolocation mapping	2-73
	SWattrinfo	swattrinfo	returns information about swath attributes	2-43
	SWfieldinfo	swfldinfo	retrieve information about a specific geolocation or data field	2-69
	SWcompinfo	swcompinfo	retrieve compression information about a field	2-45
	SWinqswath	swinqswath	retrieves number and names of swaths in file	2-80
	SWregionindex	swregidx	Returns information about the swath region ID	2-89
	SWupdateidxmap	swupimap	update map index for a specified region	2-94

Table 1-2. Summary of the Swath Interface (2 of 2)

Category	Routine Name		Description	Page Nos.
	C	FORTRAN		
Subset	SWgeomapinfo	swgmapinfo	Retrieve type of dimension mapping for a dimension	2-72
	SWdefboxregion	swdefboxreg	define region of interest by latitude/longitude	2-47
	SWregioninfo	swreginfo	returns information about defined region	2-91
	SWextractregion	swextreg	read a region of interest from a field	2-68
	SWdeftimeperiod	swdeftmep	define a time period of interest	2-59
	SWperiodinfo	swperinfo	retuns information about a defined time period	2-84
	SWextractperiod	swextper	extract a defined time period	2-67
	SWdefvrtregion	swdefvrtreg	define a region of interest by vertical field	2-61
	SWdupregion	swdupreg	duplicate a region or time period	2-66

1.5 Grid Data

The GD (*Grid*) interface consists of routines for storing, retrieving, and manipulating data in grid data sets. This interface is designed to support data that has been stored in a rectilinear array based on a well defined and explicitly supported projection. See the Users' Guide, Volume 1 that accompanies this document for more details.

1.5.1 The Grid Data Interface

All C routine names in the grid data interface have the prefix “GD” and the equivalent FORTRAN routine names are prefixed by “gd.” The GD routines are classified into the following categories:

- **Access routines** initialize and terminate access to the GD interface and grid data sets (including opening and closing files).
- **Definition** routines allow the user to set key features of a grid data set.
- **Basic I/O** routines read and write data and metadata to a grid data set.
- **Inquiry** routines return information about data contained in a grid data set.
- **Subset** routines allow reading of data from a specified geographic region.

1.5.2 List of Grid API ROUTINES

The GD function calls are listed below in Table 1-3 and are described in detail in Section 2 of this document. The listing in Section 2 is in alphabetical order.

Table 1-3. Summary of the Grid Interface (1 of 2)

Category	Routine Name		Description	Page Nos.
	C	FORTRAN		
Access	GDopen	gdopen	creates a new file or opens an existing one	2-149
	GDcreate	gdcreate	creates a new grid in the file	2-110
	GDattach	gdattach	attaches to a grid	2-104
	GDdetach	gddetach	detaches from grid interface	2-130
	GDclose	gdclose	closes file	2-108
Definition	GDdeforigin	gddeforigin	defines origin of grid	2-126
	GDdefdim	gddefdim	defines dimensions for a grid	2-122
	GDdefproj	gddefproj	defines projection of grid	2-128
	GDdefpixreg	gddefpixreg	defines pixel registration within grid cell	2-127
	GDdeffield	gddeffld	defines data fields to be stored in a grid	2-124
	GDdefcomp	gddefcomp	defines a field compression scheme	2-121
	GDBlkSOMoffset	none	This is a special function for SOM MISR data. Write block SOM offset values.	2-106
	GDsettilecomp	none	This routine was added as a fix to a bug in HDF-EOS. The current method of implementation didn't allow the user to have a field with fill values and use tiling and compression. This function allows the user to access all of these features.	2-161
Basic I/O	GDwritefieldmeta	gdwrmeta	writes metadata for field already existing in file	2-167
	GDwritefield	gdwrfld	writes data to a grid field.	2-165
	GDreadfield	gdrdfld	reads data from a grid field	2-154
	GDwriteattr	gdwrattr	writes/updates attribute in a grid.	2-163
	GDreadattr	gdrdattr	reads attribute from a grid	2-153
	GDsetfillvalue	gdsetfill	sets fill value for the specified field	2-159
	GDgetfillvalue	gdgetfill	retrieves fill value for the specified field	2-136
Inquiry	GDinqdims	gdinqdims	retrieves information about dimensions defined in grid	2-143
	GDinqfields	gdinqflds	retrieves information about the data fields defined in grid	2-144
	GDinqattrs	gdinqattrs	retrieves number and names of attributes defined	2-142
	GDnentries	gdnentries	returns number of entries and descriptive string buffer size for a specified entity	2-148
	GDgridinfo	gdgridinfo	returns dimensions of grid and X-Y coordinates of corners	2-141
	GDprojinfo	gdprojinfo	returns all GCTP projection information	2-152
	GDdiminfo	gddiminfo	retrieves size of specified dimension.	2-138
	GDcompinfo	gdcompinfo	retrieve compression information about a field	2-109
	GDfieldinfo	gdfldinfo	retrieves information about a specific geolocation or data field in the grid	2-134
	GDinqgrid	gdinqgrid	retrieves number and names of grids in file	2-145
	GDattrinfo	gdattrinfo	returns information about grid attributes	2-105
	GDorigininfo	gdorginfo	return information about grid origin	2-150
	GDpixreginfo	gdprginfo	return pixel registration information for given grid	2-151
	GDdefboxregion	gddefboxreg	define region of interest by latitude/longitude	2-113
	GDregioninfo	gdreginfo	returns information about a defined region	2-157

Table 1-3. Summary of the Grid Interface (2 of 2)

Category	Routine Name		Description	Page Nos.
	C	FORTRAN		
Subset	GDextractregion	gdextrreg	read a region of interest from a field	2-133
	GDdeftimeperiod	gddeftmepер	define a time period of interest	2-125
	GDdefvrregion	gddefvrreg	define a region of interest by vertical field	2-127
	GDgetpixels	gdgetpix	get row/columns for lon/lat pairs	2-137
	GDgetpixvalues	gdgetpixval	get field values for specified pixels	2-139
	GDinterpolate	gdinterpolate	perform bilinear interpolation on a grid field	2-146
	GDdupregion	gddupreg	duplicate a region or time period	2-132
Tiling	GDdeftile	gddeftle	define a tiling scheme	2-123
	GDtileinfo	gdtileinfo	returns information about tiling for a field	2-162
	GDsettilecache	gdsettelleche	set tiling cache parameters	2-160
	GDreadtile	gdrdtile	read data from a single tile	2-156
	GDwritetile	gdwrtile	write data to a single tile	2-168

1.6 GCTP Usage

The HDF-EOS Grid API uses the U.S. Geological Survey General Cartographic Transformation Package (GCTP) to define and subset grid structures. This section described codes used by the package.

1.6.1 GCTP Projection Codes

The following GCTP projection codes are used in the grid API described in Section 7 below:

GCTP_GEO	(0)	Geographic
GCTP_UTM	(1)	Universal Transverse Mercator
GCTP_LAMCC	(4)	Lambert Conformal Conic
GCTP_PS	(6)	Polar Stereographic
GCTP_POLYC	(7)	Polyconic
GCTP_TM	(9)	Transverse Mercator
GCTP_LAMAZ	(11)	Lambert Azimuthal Equal Area
GCTP_HOM	(20)	Hotine Oblique Mercator
GCTP_SOM	(22)	Space Oblique Mercator
GCTP_GOOD (24)		Interrupted Goode Homolosine
GCTP_ISINUS	(99)	Intergerized Sinusoidal Projection*

* The Intergerized Sinusoidal Projection is not part of the original GCTP package. It has been added by ECS. See *Level-3 SeaWiFS Data Products: Spatial and Temporal Binning Algorithms*. Additional references are provided in Section 2.

Note that other projections supported by GCTP will be adapted for HDF-EOS Version 2.7 as new user requirements are surfaced. For further details on the GCTP projection package, please refer to Section 6.3.4 and Appendix G of the SDP Toolkit Users Guide for the ECS Project, Mar, 1998, (333-CD-100-001).

1.6.2 UTM Zone Codes

The Universal Transverse Mercator (UTM) Coordinate System uses zone codes instead of specific projection parameters. The table that follows lists UTM zone codes as used by GCTP Projection Transformation Package. C.M. is Central Meridian

Zone	C.M.	Range	Zone	C.M.	Range
01	177W	180W-174W	31	003E	000E-006E
02	171W	174W-168W	32	009E	006E-012E
03	165W	168W-162W	33	015E	012E-018E
04	159W	162W-156W	34	021E	018E-024E
05	153W	156W-150W	35	027E	024E-030E
06	147W	150W-144W	36	033E	030E-036E
07	141W	144W-138W	37	039E	036E-042E
08	135W	138W-132W	38	045E	042E-048E
09	129W	132W-126W	39	051E	048E-054E
10	123W	126W-120W	40	057E	054E-060E
11	117W	120W-114W	41	063E	060E-066E
12	111W	114W-108W	42	069E	066E-072E
13	105W	108W-102W	43	075E	072E-078E
14	099W	102W-096W	44	081E	078E-084E
15	093W	096W-090W	45	087E	084E-090E
16	087W	090W-084W	46	093E	090E-096E
17	081W	084W-078W	47	099E	096E-102E
18	075W	078W-072W	48	105E	102E-108E
19	069W	072W-066W	49	111E	108E-114E
20	063W	066W-060W	50	117E	114E-120E
21	057W	060W-054W	51	123E	120E-126E
22	051W	054W-048W	52	129E	126E-132E
23	045W	048W-042W	53	135E	132E-138E
24	039W	042W-036W	54	141E	138E-144E
25	033W	036W-030W	55	147E	144E-150E
26	027W	030W-024W	56	153E	150E-156E
27	021W	024W-018W	57	159E	156E-162E
28	015W	018W-012W	58	165E	162E-168E
29	009W	012W-006W	59	171E	168E-174E
30	003W	006W-000E	60	177E	174E-180W

1.6.3 GCTP Spheroid Codes

Clarke 1866 (default)	(0)
Clarke 1880	(1)
Bessel	(2)
International 1967	(3)
International 1909	(4)
WGS 72	(5)
Everest	(6)
WGS 66	(7)
GRS 1980	(8)
Airy	(9)
Modified Airy	(10)

Modified Everest	(11)
WGS 84	(12)
Southeast Asia	(13)
Australian National	(14)
Krassovsky	(15)
Hough	(16)
Mercury 1960	(17)
Modified Mercury 1968	(18)
Sphere of Radius 6370997m	(19)

1.6.4 GCTP Projection Parameters

Table 1-4. Projection Transformation Package Projection Parameters (1 of 2)

Code & Projection Id	Array Element							
	1	2	3	4	5	6	7	8
0 Geographic								
1 UTM	Lon/Z	Lat/Z						
4 Lambert Conformal C	SMajor	SMinor	STDPR1	STDPR2	CentMer	OriginLat	FE	FN
6 Polar Stereographic	SMajor	SMinor			LongPol	TrueScale	FE	FN
7 Polyconic	SMajor	SMinor			CentMer	OriginLat	FE	FN
9 Transverse Mercator	SMajor	SMinor	Factor		CentMer	OriginLat	FE	FN
11 Lambert Azimuthal	Sphere				CentLon	CenterLat	FE	FN
20 Hotin Oblique Merc A	SMajor	SMinor	Factor			OriginLat	FE	FN
20 Hotin Oblique Merc B	SMajor	SMinor	Factor	AziAng	AzmthPt	OriginLat	FE	FN
22 Space Oblique Merc A	SMajor	SMinor		IncAng	AscLong		FE	FN
22 Space Oblique Merc B	SMajor	SMinor	Satnum	Path			FE	FN
24 Interrupted Goode	Sphere							
99 Integerized Sinusoidal	Sphere				CentMer		FE	FN

Table 1-4. Projection Transformation Package Projection Parameters (2 of 2)

Code & Projection Id	Array Element				
	9	10	11	12	13
0 Geographic					
1 UTM					
4 Lambert Conformal C					
6 Polar Stereographic					
7 Polyconic					
9 Transverse Mercator					
11 Lambert Azimuthal					
20 Hotin Oblique Merc A	Long1	Lat1	Long2	Lat2	zero
20 Hotin Oblique Merc B					one
22 Space Oblique Merc A	PSRev	SRat	PFlag	HDF-EOS	zero
22 Space Oblique Merc B				HDF-EOS	one
24 Interrupted Goode					
99 Integerized Sinusoidal	NZone		RFlag		

Where,

- Lon/Z Longitude of any point in the UTM zone or zero. If zero, a zone code must be specified.
- Lat/Z Latitude of any point in the UTM zone or zero. If zero, a zone code must be specified.
- Smajor Semi-major axis of ellipsoid. If zero, Clarke 1866 in meters is assumed.
- Sminor Eccentricity squared of the ellipsoid if less than zero, if zero, a spherical form is assumed, or if greater than zero, the semi-minor axis of ellipsoid.
- Sphere Radius of reference sphere. If zero, 6370997 meters is used.
- STDPR1 Latitude of the first standard parallel
- STDPR2 Latitude of the second standard parallel
- CentMer Longitude of the central meridian

OriginLat	Latitude of the projection origin
FE	False easting in the same units as the semi-major axis
FN	False northing in the same units as the semi-major axis
TrueScale	Latitude of true scale
LongPol	Longitude down below pole of map
Factor	Scale factor at central meridian (Transverse Mercator) or center of projection (Hotine Oblique Mercator)
CentLon	Longitude of center of projection
CenterLat	Latitude of center of projection
Long1	Longitude of first point on center line (Hotine Oblique Mercator, format A)
Long2	Longitude of second point on center line (Hotine Oblique Mercator, frmt A)
Lat1	Latitude of first point on center line (Hotine Oblique Mercator, format A)
Lat2	Latitude of second point on center line (Hotine Oblique Mercator, format A)
AziAng	Azimuth angle east of north of center line (Hotine Oblique Mercator, frmt B)
AzmthPt	Longitude of point on central meridian where azimuth occurs (Hotine Oblique Mercator, format B)
IncAng	Inclination of orbit at ascending node, counter-clockwise from equator (SOM, format A)
AscLong	Longitude of ascending orbit at equator (SOM, format A)
PSRev	Period of satellite revolution in minutes (SOM, format A)
SRat	Satellite ratio to specify the start and end point of x,y values on earth surface (SOM, format A -- for Landsat use 0.5201613)
PFlag	End of path flag for Landsat: 0 = start of path, 1 = end of path (SOM, frmt A)
Satnum	Landsat Satellite Number (SOM, format B)
Path	Landsat Path Number (Use WRS-1 for Landsat 1, 2 and 3 and WRS-2 for Landsat 4 and 5.) (SOM, format B)

Nzone	Number of equally spaced latitudinal zones (rows); must be two or larger and even
Rflag	Right justify columns flag is used to indicate what to do in zones with an odd number of columns. If it has a value of 0 or 1, it indicates the extra column is on the right (zero) or left (one) of the projection Y-axis. If the flag is set to 2 (two), the number of columns are calculated so there are always an even number of columns in each zone.

Notes:

- Array elements 14 and 15 are set to zero.
- All array elements with blank fields are set to zero.

All angles (latitudes, longitudes, azimuths, etc.) are entered in packed degrees/ minutes/ seconds (DDDMMMSSS.SS) format.

The following notes apply to the Space Oblique Mercator A projection:

- A portion of Landsat rows 1 and 2 may also be seen as parts of rows 246 or 247. To place these locations at rows 246 or 247, set the end of path flag (parameter 11) to 1--end of path. This flag defaults to zero.
- When Landsat-1,2,3 orbits are being used, use the following values for the specified parameters:
 - Parameter 4 099005031.2
 - Parameter 5 128.87 degrees - (360/251 * path number) in packed DMS format
 - Parameter 9 103.2669323
 - Parameter 10 0.5201613
- When Landsat-4,5 orbits are being used, use the following values for the specified parameters:
 - Parameter 4 098012000.0
 - Parameter 5 129.30 degrees - (360/233 * path number) in packed DMS format
 - Parameter 9 98.884119
 - Parameter 10 0.5201613

2. Function Reference

2.1 Format

This section contains a function-by-function reference for each interface in the HDF-EOS library. Each function has a separate page describing it (in some cases there are multiple pages). Each page contains the following information (in order):

- Function name as used in C
- Function declaration in ANSI C format
- Description of each argument
- Purpose of routine
- Description of returned value
- Description of the operation of the routine
- A short example of how to use the routine in C
- The FORTRAN declaration of the function and arguments
- An equivalent FORTRAN example

2.1.1 Point Interface Functions

This section contains an alphabetical listing of all the functions in the Point interface. The functions are alphabetized based on their C-language names.

Attach to an Existing Point Structure

PTattach

int PTattach(int *fid*, char **pointname*)

<i>fid</i>	IN: Point file id returned by PTopen
<i>pointname</i>	IN: Name of point to be attached
Purpose	Attaches to an existing point within the file.
Return value	Returns the point handle (pointID) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point file id or point name.
Description	This routine attaches to the point using the <i>pointname</i> parameter as the identifier.
Example	In this example, we attach to the previously created point, "ExamplePoint", within the HDF file, <i>PointFile.hdf</i> , referred to by the handle, <i>fid</i> :

```
pointID = PTattach(fid, "ExamplePoint");
```

The point can then be referenced by subsequent routines using the handle, *pointID*.

FORTRAN integer function ptattach(*fid*,*pointname*)

```
integer fid
```

```
character*(*) pointname
```

The equivalent *FORTRAN* code for the example above is:

```
status = ptattach(fid, "ExamplePoint")
```

Return Information About a Point Attribute

PTattrinfo

```
int PTattrinfo(int pointID, char *attrname, int *numbertype, hsize_t *count)
```

<i>pointID</i>	IN:	Point id returned by PTcreate or PTattach
<i>attrname</i>	IN:	Attribute name
<i>numbertype</i>	OUT:	Number type of attribute
<i>count</i>	OUT:	Number of total bytes in attribute
Purpose		Returns information about a point attribute
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine returns number type and number of elements (count) of a point attribute.
Example		In this example, we return information about the <i>ScalarFloat</i> attribute.

```
status = PTattrinfo(pointID, "ScalarFloat", &nt, &count);
```

The *nt* variable will have the value 5 and *count* will have the value 4.

FORTRAN

```
integer function ptattrinfo(pointid, attrname, ntype, count)
Integer      pointid
character(*) attrname
integer       ntype
integer       count
```

The equivalent *FORTRAN* code for the first example above is:

```
status = ptattrinfo(pointid, "ScalarFloat", nt, count)
```

Return Linkage Field to Previous Level

PTbcklinkinfo

int PTbcklinkinfo(int *pointID*, int *level*, char **linkfield*)

<i>pointID</i>	IN:	Point id returned by PTcreate or PTattach
<i>level</i>	IN:	Point level (0-based)
<i>linkfield</i>	OUT:	Link field
Purpose		Returns the linkfield to the previous level.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine returns the linkfield to the previous level.
Example		In this example, we return the linkfield connecting the <i>Observations</i> level to the previous <i>Desc-Loc</i> level. (These levels are defined in the <i>PTdeflevel</i> routine.)

```
status = PTbcklinkinfo(pointID2, 1, linkfield);
```

The *linkfield* will contain the string: *ID*.

FORTRAN integer ptblinkinfo(*pointid*, *level*, *linkfield*)
 integer *pointid*
 integer *level*
 character*(*) *linkfield*

The equivalent *FORTRAN* code for the example above is:

```
status = ptblinkinfo(pointid2, 0, linkfield)
```

Close an HDF-EOS File

PTclose

intn PTclose(int32 *fid*)

<i>fid</i>	IN: Point file id returned by PTOpen
Purpose	Closes file.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description	This routine closes the HDF point file.
Example	

```
status = PTclose(fid);  
FORTRAN    integer ptclose(fid)  
            integer*4      fid
```

The equivalent *FORTRAN* code for the example above is:

```
status = ptclose(fid)
```

Create a New Point Structure

PTcreate

int32 PTcreate(int32 *fid*, char **pointname*)

<i>fid</i>	IN: Point file id returned by PTopen
<i>pointname</i>	IN: Name of point to be created
Purpose	Creates a point within the file.
Return value	Returns the point handle (<i>pointID</i>) if successful or FAIL (-1) otherwise.
Description	The point is created as a Vgroup within the HDF file with the name <i>pointname</i> and class <i>POINT</i> .
Example	In this example, we create a new point structure, <i>ExamplePoint</i> , in the previously created file, <i>PointFile.hdf</i> .

```
pointID = PTcreate(fid, "ExamplePoint");
```

The point structure is then referenced by subsequent routines using the handle, *pointID*.

FORTRAN integer*4 function ptcreate(*fid*,*pointname*)
 integer*4 *fid*
 character*(*) *pointname*

The equivalent *FORTRAN* code for the example above is:

```
pointid = ptcreate(fid, "ExamplePoint");
```

Define Region of Interest by Latitude/Longitude

PTdefboxregion

int32 PTdefboxregion(int32 *pointID*, float64 *cornerlon[]*, float64 *cornerlat[]*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>cornerlon</i>	IN: Longitude in decimal degrees of box corners
<i>cornerlat</i>	IN: Latitude in decimal degrees of box corners
Purpose	Defines a longitude-latitude box region for a point.
Return value	Returns the point regionID if successful or FAIL (-1) otherwise.
Description	This routine defines an area of interest for a point. It returns a point region ID which is used by the <i>PTextractregion</i> routine to read the fields from a level for those records within the area of interest. The point structure must have a level with both a <i>Longitude</i> and <i>Latitude</i> (or <i>Colatitude</i>) field defined
Example	In this example, we define an area of interest with (opposite) corners at -145 degrees longitude, -15 degrees latitude and -135 degrees longitude, -8 degrees latitude. <pre>cornerlon[0] = -145.; cornerlat[0] = -15.; cornerlon[1] = -135.; cornerlat[1] = -8.; regionID = PTdefboxregion(pointID, cornerlon, cornerlat);</pre>
FORTRAN	<pre>integer*4 function ptdefboxreg(pointid, cornerlon, cornerlat) integer*4 pointid real*8 cornerlon real*8 cornerlat</pre>

The equivalent *FORTRAN* code for the example above is:

```
cornerlon(1) = -145.  
cornerlat(1) = -15.  
cornerlon(2) = -135.  
cornerlat(2) = -8.  
regionid = ptdefboxreg(pointid, cornerlon, cornerlat)
```

Define a New Level Within a Point

PTdeflevel

```
intn PTdeflevel(int32 pointID, char *levelname, char *fieldlist, int32 fieldtype[], int32 fieldorder[])
```

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>levelname</i>	IN: Name of level to be defined
<i>fieldlist</i>	IN: List of fields in level
<i>fieldtype</i>	IN: Array containing field type of each field within level
<i>fieldorder</i>	IN: Array containing order of each field within level
Purpose	Defines a new level within the point.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description	This routine defines a level within the point. A simple point consists of a single level. A point where there is common data for a number of records can be more efficiently stored with multiple levels. The order in which the levels are defined determines the (0-based) level index.
Example	<u>Simple Point</u>

In this example, we define a simple single level point, with levelname, *Sensor*. The levelname should not contain any slashes (“/”). It consists of six fields, *ID*, *Time*, *Longitude*, *Latitude*, *Temperature*, and *Mode* defined in the field list. The *fieldtype* and *fieldorder* parameters are arrays consisting of the HDF number type codes and field orders, respectively. The *Temperature* is an array field of dimension 4 and the *Mode* field a character string of size 4. All other fields are scalars. Note that the order for numerical scalar variables can be either 0 or 1.

```
int32 fieldtype[6] = {DFNT_INT16, DFNT_INT16,
                      DFNT_FLOAT32, DFNT_FLOAT32, DFNT_FLOAT32, DFNT_CHAR8};

int32 fieldorder[6] = {0,0,0,0,4,4};

char8 *fldlist =
    "ID,Time,Longitude,Latitude,Temperature,Mode";

status = PTdeflevel(pointID1, "Sensor", fldlist, fieldtype,
                    fieldorder);
```

Multi-Level Point

In this example, we define a two-level point that describes data from a network of fixed buoys. The first level contains information about each buoy and includes the name (label) of the buoy, its (fixed) longitude and latitude, its deployment date, and an ID that is used to link it to the following level. (The link field is defined in the *PTdeflinkage* routine described later.) The entries within this ID field must be unique. The second level contains the actual measurements from the buoys (rainfall and temperature values) plus the observation time and the ID which relates a given measurement to a particular buoy entry in the previous level. There can be many records in this level with the same ID since there can be multiple measurements from a single buoy. It is advantageous, although not mandatory, to store all records for a particular buoy (ID) contiguously.

Level 0

```
int32 fieldtype0[5] = {DFNT_CHAR8, DFNT_FLOAT64,
                      DFNT_FLOAT64, DFNT_INT32, DFNT_CHAR8};

int32 fieldorder0[5] = {8,0,0,0,1};

char8 *fldlist0 = "Label,Longitude,Latitude,DeployDate,ID";

status = PTdeflevel(pointID2, "Desc-Loc", fldlist0, fieldtype0,
                     fieldorder0);
```

Level 1

```
int32 fieldtype1[4] = {DFNT_FLOAT64, DFNT_FLOAT32,
                      DFNT_FLOAT32, DFNT_CHAR8};

int32 fieldorder1[4] = {0,0,0,1};

char8 *fldlist1 = "Time,Rainfall,Temperature,ID";

status = PTdeflevel(pointID2, "Observations", fldlist1,
                     fieldtype1, fieldorder1);
```

FORTRAN

```
integer function ptdeflev(pointid, levelname, fieldlist, fieldtype, fieldorder)
integer*4      pointid
character*(*)  levelname
character*(*)  fieldlist
integer*4      fieldtype (*)
integer*4      fieldorder (*)
```

The equivalent *FORTRAN* code for the first example above is:

```
status = PTdeflevel(pointID1, "Sensor", fldlist, fieldtype,
                     fieldorder)
```

Define Linkage Field Between Two Levels

PTdeflinkage

intn PTdeflinkage(int32 *pointID*, char **parent*, char **child*, char **linkfield*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>parent</i>	IN: Name of parent level
<i>child</i>	IN: Name of child level
<i>linkfield</i>	IN: Name of (common) linkfield
Purpose	Defines a linkfield between two (adjacent) levels.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description	This routine defines the linkfield between two levels. This field must be defined in both levels.
Example	In this example we define the <i>ID</i> field as the link between the two levels defined previously in the <i>PTdeflevel</i> routine.

```
status = PTdeflinkage(pointID2, "Desc-Loc", "Observations",
                      "ID");
```

FORTRAN

```
integer function ptdeflink(pointid, parent, child,linkfield)
integer*4      pointid
character(*)   parent
character(*)   child
character(*)   linkfield
```

The equivalent *FORTRAN* code for the example above is:

```
status = ptdeflink(pointid2, "Desc-Loc", "Observations", "ID")
```

Define Time Period of Interest

PTdeftimeperiod

int32 PTdeftimeperiod(int32 *pointID*, float64 *starttime*, float64 *endtime*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>starttime</i>	IN: Start time of period
<i>endtime</i>	IN: Stop time of period
Purpose	Defines a time period for a point.
Return value	Returns the point periodID if successful or FAIL (-1) otherwise.
Description	This routine defines time period for a point. It returns a point period ID which is used by the <i>PTextractperiod</i> routine to read the fields from a level for those records within the time period. The point structure must have a level with the <i>Time</i> field defined

Example In this example, we define a time period with a start time of 35208757.6 and a stop time of 35984639.2

```
starttime = 35208757.6;
endtime = 35984639.2;
periodID = PTdeftimeperiod(pointID, starttime, endtime);
```

FORTRAN integer*4 function ptdeftmep(*pointid*, *starttime*,*endtime*)
integer*4 *pointid*
real*8 *starttime*
real*8 *endtime*

The equivalent *FORTRAN* code for the example above is:

```
starttime = 35208757.6
endtime = 35984639.2
periodid = ptdeftmep(pointid, starttime, endtime)
```

Note: This function determines whether a record in the point data is within the specified time interval by doing a simple boolean comparison of the “Time” value and the “starttime” and “endtime”. This simple boolean comparison

does not take into account the precisions of the values being compared. As a result, the first and last records in the subset can be erroneously determined to be outside the interval simply because they are not defined to the maximum precision of a float 64 value. It is the responsibility of the user to subtract a tolerance from the starttime and add it to the stoptime before calling the function.

Define a Vertical Subset Region

PTdefvrtrregion

int32 PTdefvrtrregion(int32 *pointID*, int32 *regionID*, char **fieldname*, float64 *range*[])

<i>pointID</i>	IN:	Point id returned by PTcreate or PTattach
<i>regionID</i>	IN:	Region (or period) id from previous subset call
<i>fieldname</i>	IN:	Dimension or field to subset by
<i>range</i>	IN:	Minimum and maximum range for subset
Purpose		Selects records within a given range for the given field.
Return value		Returns the point region ID if successful or FAIL (-1) otherwise.
Description		This routine allows the user to select those records within a point whose field values are within a given range. (For the current version of this routine, the field must have one of the following number types: INT16, INT32, FLOAT32, FLOAT64.) This routine may be called after <i>PTdefboxregion</i> or <i>PTdeftimeperiod</i> to provide both geographic or time and “vertical” subsetting. In this case the user provides the id from the previous subset call. (This same id is then returned by the function.) This routine may also be called “stand-alone” by setting the input id to HDFE_NOPREVSUB (-1).

This routine may be called as many times as desired for a single region. In this way a region can be subsetted using a number of field ranges. The *PTregioninfo* and *PTextractregion* routines work in the usual manner.

Example Suppose we wish to find those records within a point whose *Rainfall* values fall between 1 and 2. We wish to search all the records within the point so we set the input region ID to HDFE_NOPREVSUB (-1).

```
range[0] = 1. ;
range[1] = 2. ;
regionID = PTdefvrtrregion(pointID, HDFE_NOPREVSUB, "Rainfall",
range);
```

We now wish to subset further using the *Temperature* field.

```
range[0] = 22. ;
range[1] = 24. ;
regionID = PTdefvrtrregion(pointID, regionID, "Temperature",
range);
```

The subsetted region referred to by *regionID* will now contain those records whose *Rainfall* field are between 1 and 2 **and** whose *Temperature* field are between 22 and 24.:

```
FORTRAN    integer*4 function ptdefvrtrg(pointid, regionid, fieldname, range)
            integer*4      pointid
            integer*4      regionid
            character(*)   fieldname
            real*8        range
```

The equivalent *FORTRAN* code for the examples above is:

```
parameter (HDFE_NOPREVSUB=-1)
range(1) = 1.
range(2) = 2.
regionid = ptdefvrtrg(pointid, HDFE_NOPREVSUB, 'Rainfall',
range)
range(1) = 22.          ! Note 1-based element numbers
range(2) = 24.
regionid = ptdefvrtrg(pointid, regionid, 'Temperature', range)
```

Detach from Point Structure

PTdetach

intn PTdetach(int32 *pointID*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
Purpose	Detaches from point data set.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description	This routine should be run before exiting from the point file for every point opened by PTcreate or PTattach.
Example	In this example, we detach the point structure, <i>ExamplePoint</i> :

```
status = PTdetach(pointID);
```

FORTRAN integer ptdetach(*pointid*)
 integer*4 *pointid*

The equivalent *FORTRAN* code for the example above is:

```
status = ptdetach(pointid)
```

Reads Point Records for a Specified Time Period

PTextractperiod

```
intn PTextractperiod(int32 pointID, int32 periodID, int32 level, char *fieldlist,  
VOIDP buffer)
```

<i>pointID</i>	IN:	Point id
<i>periodID</i>	IN:	Period id returned by PTdeftimeperiod
<i>level</i>	IN:	Point level (0-based)
<i>fieldlist</i>	IN:	List of fields to extract
<i>buffer</i>	OUT:	Data buffer
Purpose		Extracts (reads) from subsetted time period.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine reads data from the designated level fields into the data buffer from the subsetted time period.
Example		In this example, we read data within the subsetted time period defined in <i>Ptdeftimeperiod</i> from the <i>Time</i> field.

```
/* Read subsetted data into buffer */  
  
status = PTextractperiod(pointID, periodID, 0, "Time",  
datbuf);
```

FORTRAN integer function ptextper(*pointid,periodid,level,fieldlist,buffer*)
 integer*4 *pointid*
 integer*4 *periodid*
 integer*4 *level*
 character*(*) *fieldlist*
 <valid type> *buffer(*)*

The equivalent *FORTRAN* code for the example above is:

```
status = ptextper(pointid,periodid,0,"Time",datbuf)
```

Reads Point Records for a Specified Geographic Region

PExtractregion

```
intn PExtractregion(int32 pointID, int32 regionID, int32 level, char *fieldlist,  
VOIDP buffer)
```

<i>pointID</i>	IN:	Point id
<i>regionID</i>	IN:	Region id returned by PTdefboxregion
<i>level</i>	IN:	Point level (0-based)
<i>fieldlist</i>	IN:	List of fields to extract
<i>buffer</i>	OUT:	Data buffer
Purpose		Extracts (reads) from subsetted area of interest.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine reads data from the designated level fields into the data buffer from the subsetted area of interest.
Example		In this example, we read data within the subsetted area of interest defined in <i>PTdefboxregion</i> from the <i>Longitude</i> and <i>Latitude</i> fields.

```
/* Read subsetted data into buffer */  
  
status = PExtractregion(pointID, regionID, 0,  
"Longitude, Latitude", datbuf);
```

FORTRAN

```
integer function ptextreg(pointid,regionid,level,fieldlist,buffer)  
  
integer*4          pointid  
integer*4          regionid  
integer*4          level  
character*(* )     fieldlist  
<valid type>      buffer(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status =  
ptextreg(pointid,regionid,0,"Longitude, Latitude",datbuf)
```

Return Linkage Field to Following Level

PTfwdlinkinfo

intn PTfwdlinkinfo(int32 *pointID*, int32 *level*, char **linkfield*)

<i>pointID</i>	IN:	Point id returned by PTcreate or PTattach
<i>level</i>	IN:	Point level (0-based)
<i>linkfield</i>	OUT:	Link field
Purpose		Returns the linkfield to the following level.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine returns the linkfield to the following level.
Example		In this example, we return the linkfield connecting the <i>Desc-Loc</i> level to the following <i>Observations</i> level. (These levels are defined in the <i>PTdeflevel</i> routine.)

```
status = PTfwdlinkinfo(pointID2, 1, linkfield);
```

The *linkfield* will contain the string: *ID*.

FORTRAN integer ptlinkinfo(*pointid*, *level*, *linkfield*)
 integer*4 *pointid*
 integer*4 *level*
 character(*) *linkfield*

The equivalent *FORTRAN* code for the example above is:

```
status = ptlinkinfo(pointid2, 1, linkfield)
```

Return Level Name

PTgetlevelname

intn PTgetlevelname(int32 *pointID*, int32 *level*, char **levelname*, int32 **strbufsize*)

<i>pointID</i>	IN:	Point id returned by PTcreate or PTattach
<i>level</i>	IN:	Point level (0-based)
<i>levelname</i>	OUT:	Level name
<i>strbufsize</i>	OUT:	String length of level name
Purpose		Returns the name of a level given the level number.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine returns the name of a level given the level number (0-based). If the user passes NULL for the <i>levelname</i> , the routine will return just the string length of the level name (not counting the null terminator).

Example In this example, we return the level name of the 0th level of the second point defined in the *PTdeflevel* section:

```
status = PTgetlevelname(pointID2, 0, levelname, &strbufsize);
```

The *levelname* will contain the string: *Desc-Loc* and the *strbufsize* variable will be set to 8.

FORTRAN integer ptgetlevname(*pointid*, *level*, *levelname*,*strbufsize*)
 integer*4 *pointid*
 integer*4 *level*
 character(*) *levelname*
 integer*4 *strbufsize*

The equivalent *FORTRAN* code for the example above is:

```
status = ptgetlevname(pointid2, 0, levelname, strbufsize)
```

Return Record Numbers Related to Level

PTgetrecnums

```
intn PTgetrecnums(int32 pointID, int32 inlevel, int32 outlevel, int32 inNrec, int32  
inRecs[], int32 *outNrec, int32 outRecs[])
```

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>inlevel</i>	IN: Level number of input records(0-based)
<i>outlevel</i>	IN: Level number of output records(0-based)
<i>inNrec</i>	IN: Number of records in the <i>inRecs</i> array
<i>inRecs</i>	IN: Array containing the input record numbers.
<i>outNrec</i>	OUT: Number of records in the <i>outRecs</i> array
<i>outRecs</i>	OUT Array containing the output record numbers.
Purpose	Returns the record numbers in one level corresponding to a group of records in a different level.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description	The records in one level are related to those in another through the link field. These in turn are related to the next. In this way each record in any level is related to others in all the levels of the point structure. The purpose of <i>PTgetrecnums</i> is to return the record numbers in one level that are connected to a given set of records in a different level. Note that the two levels need not be adjacent.
Example	In this example, we get the record number in the second level that are related to the first record in the first level.

```
nrec = 1;  
recs[0] = 0;  
inLevel = 0;  
outLevel = 1;  
  
status = PTgetrecnums(pointID2, inLevel, outLevel, nrec, recs,  
&outNrec, outRecs);
```

```
FORTRAN    integer ptgetrecnum(pointID,inlevel,outlevel,innrec,inrecs,outnrec,outrecs)  
              integer*4      pointid  
              integer*4      inlevel  
              integer*4      outlevel  
              integer*4      innrec  
              integer*4      inrecs  
              integer*4      outnrec  
              integer*4      outnrecs
```

The equivalent *FORTRAN* code for the example above is:

```
status=ptgetrecnums(pointid2,inlevel,outlevel,nrec,recs,outn  
rec,outrecs)
```

Retrieve Information About Point Attributes

PTinqattrs

int32 PTinqattrs(int32 *pointID*, char **attrlist*, int32 **strbufsize*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>attrlist</i>	OUT: Attribute list (entries separated by commas)
<i>strbufsize</i>	OUT: String length of attribute list
Purpose	Retrieve information about attributes defined in point.
Return value	Number of attributes found if successful or FAIL (-1) otherwise.
Description	The attribute list is returned as a string with each attribute name separated by commas. If <i>attrlist</i> is set to NULL, then the routine will return just the string buffer size, <i>strbufsize</i> . This variable does not count the null string terminator.
Example	In this example, we retrieve information about the attributes defined in a point structure. We assume that there are two attributes stored, <i>attrOne</i> and <i>attr_2</i> :

```
nattr = PTinqattrs(pointID, NULL, strbufsize);
```

The parameter, *nattr*, will have the value 2 and *strbufsize* will have value 14.

```
nattr = PTinqattrs(pointID, attrlist, strbufsize);
```

The variable, *attrlist*, will be set to:

"*attrOne,attr_2*".

FORTRAN integer*4 function ptinqattrs(*pointid,attrlist,strbufsize*)
 integer*4 *pointid*
 character(*) *attrlist*
 integer*4 *strbufsize*

The equivalent *FORTRAN* code for the example above is:

```
nattr = ptinqattrs(pointid, attrlist, strbufsize)
```

Retrieve Point Structures Defined in HDF-EOS File

PTinqpoint

int32 PTinqpoint(char *filename, char *pointlist, int32 *strbufsize)

<i>filename</i>	IN: HDF-EOS filename
<i>pointlist</i>	OUT: Point list (entries separated by commas)
<i>strbufsize</i>	OUT: String length of point list
Purpose	Retrieves number and names of points defined in HDF-EOS file.
Return value	Number of points found if successful or FAIL (-1) otherwise.
Description	The point list is returned as a string with each point name separated by commas. If <i>pointlist</i> is set to NULL, then the routine will return just the string buffer size, <i>strbufsize</i> . If <i>strbufsize</i> is also set to NULL, the routine returns just the number of points. Note that <i>strbufsize</i> does not count the null string terminator.
Example	In this example, we retrieve information about the points defined in an HDF-EOS file, <i>HDFEOS.hdf</i> . We assume that there are two points stored, <i>PointOne</i> and <i>Point_2</i> :

```
npoint = PTinqpoint("HDFEOS.hdf", NULL, strbufsize);
```

The parameter, *npoint*, will have the value 2 and *strbufsize* will have value 16.

```
npoint = PTinqpoint("HDFEOS.hdf", pointlist, strbufsize);
```

The variable, *pointlist*, will be set to:

“*PointOne,Point_2*”.

FORTRAN

```
integer*4 function ptinqpoint(filename,pointlist,strbufsize)
character*(*) filename
character*(*) pointlist
integer*4 strbufsize
```

The equivalent *FORTRAN* code for the example above is:

```
npoint = ptinqpoint("HDFEOS.hdf", pointlist, strbufsize)
```

Return Index Number of a Named Level

PTlevelindx

int32 PTlevelindx(int32 *pointID*, char **levelname*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>levelname</i>	IN: Level Name
Purpose	Returns the level index (0-based) for a given (named) level.
Return value	Returns the level index if successful or FAIL (-1) otherwise.
Description	This routine returns the level index for a give level specified by name.
Example	In this example, we return the level index of the <i>Observations</i> level in the multilevel point structure defined in <i>PTdeflevel</i> .

```
levindx = PTlevelindex(pointID2, "Observations");
```

The *levindx* variable will have the value 1.

FORTRAN integer*4 ptlevidx (*pointid*) *levelname*
 integer*4 *pointid*
 character*(*) *levelname*

The equivalent *FORTRAN* code for the example above is:

```
levindx = ptlevidx(pointid2, "Observations")
```

Return Information on Fields in a Given Level

PTlevelinfo

```
int32 PTlevelinfo(int32 pointID, int32 level, char *fieldlist, int32 fldtype[], int32  
                  fldorder[])
```

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>level</i>	IN: Point level (0-based)
<i>fieldlist</i>	OUT: Field names in level
<i>fldtype</i>	OUT: Number type of each field
<i>fldorder</i>	OUT: Order of each field
Purpose	Returns information on fields in a given level.
Return value	Returns number of fields if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point id or level number.
Description	This routine returns information about the fields in a given level.
Example	In this example we return information about the <i>Desc-Loc</i> (1st) level defined previously.

```
nflds = PTlevelinfo(pointID2, 0, fldlist, fldtype, fldorder);
```

The *fldlist* variable will be set to:

"Time,Longitude,Latitude,Channel,Value".

The *nflds*= 5, the *fldtype* array = {22,5,5,22,5}, the *fldorder* array = {0,0,0,0,0}.

FORTRAN

```
integer*4 function ptlevinfo(pointID, level, fieldlist, fldtype, fldorder)  
integer*4      pointid  
integer*4      level  
character(*)   fieldlist  
integer*4      fldtype (*)  
integer*4      fldorder (*)
```

The equivalent *FORTRAN* code for the example above is:

```
nflds = ptlevinfo(pointid2, 0, fldlist, fldtype, fldorder)
```

Unlike the C language example, all output parameters must be supplied in the call.

Return Number of Fields Defined in a Level

PTnfields

int32 PTnfields(int32 *pointID*, int32 *level*, int32 **strbufsize*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>level</i>	IN: Level number (0-based)
<i>strbufsize</i>	OUT: Size in bytes of fieldlist for level
Purpose	Returns number of fields in a level and the size of the fieldlist.
Return value	Returns number of fields if successful or FAIL (-1) otherwise.
Description	This routine returns the number of fields in a level and the size of the comma-separated fieldlist. This value does NOT count the null character at the end of the string.
Example	In this example we retrieve the number of levels in the 2nd point defined previously:

```
nflds = PTnfields(pointID2, 0, strbufsize);
```

The *nflds* variable will be 5 and the *strbufsize* variable equal to 38.

FORTRAN integer*4 function ptnflds(*pointid*, *level*, *strbufsize*
 integer*4 *pointid*
 integer*4 *level*
 integer*4 *strbufsize*

The equivalent *FORTRAN* code for the example above is:

```
nflds = ptnflds(pointid2, 0, strbufsize)
```

Return Number of Levels in a Point Structure

PTnlevels

int32 PTnlevels(int32 *pointID*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
Purpose	Returns number of levels in a point.
Return value	Returns number of levels if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point id.
Description	This routine returns the number of levels in a point.
Example	In this example we retrieve the number of levels in the 2nd point defined previously:

```
nlevels = PTnlevels(pointID2);
```

The *nlevels* variable will be 2.

FORTRAN integer*4 function ptnlevs(*pointid*)
 integer*4 *pointid*

The equivalent *FORTRAN* code for the example above is:

```
nlevels = ptnlevs(pointid2)
```

Return Number of Records in a Given Level

PTnrecs

int32 PTnrecs(int32 *pointID*, int32 *level*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>level</i>	IN: Level number (0-based)
Purpose	Returns number of records in a given level.
Return value	Returns number of records in a given level if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point id or level number.
Description	This routine returns the number of records in a given level.
Example	In this example we retrieve the number of records in the first level of the 2nd point defined previously:

```
nrecs = PTnrecs(pointID2, 0);
```

FORTRAN integer*4 function ptnrecs(*pointid,level*)
 integer*4 *pointid*
 integer*4 *level*

The equivalent *FORTRAN* code for the example above is:

```
nrecs = ptnrecs(pointid2, 0)
```

Open HDF-EOS File

PTopen

int32 PTopen(char *filename, intn access)

filename	IN:	Complete path and filename for the file to be opened
access	IN:	DFACC_READ, DFACC_RDWR or DFACC_CREATE
Purpose		Opens or creates HDF file in order to create, read, or write a point.
Return value		Returns the point file id handle (fid) if successful or FAIL (-1) otherwise.
Description		This routine creates a new file or opens an existing one, depending on the access parameter.

Access codes:

DFACC_READ	Open for read only. If file does not exist, error
DFACC_RDWR	Open for read/write. If file does not exist, create it
DFACC_CREATE	If file exist, delete it, then open a new file for read/write

Example In this example, we create a new point file named, *PointFile.hdf*. It returns the file handle, *fid*.

```
fid = PTopen("PointFile.hdf", DFACC_CREATE);  
FORTRAN integer*4 function ptopen(filename, access)  
character*(*) filename  
integer access
```

The access codes should be defined as parameters:

```
parameter (DFACC_READ=1)  
parameter (DFACC_RDWR=3)  
parameter (DFACC_CREATE=4)
```

The equivalent *FORTRAN* code for the example above is:

```
fid = ptopen("PointFile.hdf", DFACC_CREATE)
```

Note to users of the SDP Toolkit: Please refer to the Version 2.0 *SDP Toolkit User Guide for the ECS Project* (333-CD-100-001), Section 6.2.1.2, for information on how to obtain a file name (referred to as a “physical file handle”) from within a PGE. See also Section 9 of this document for code examples.

Returns Information About a Time Period

PTperiodinfo

```
intn PTperiodinfo(int32 pointID, int32 periodID, int32 level, char *fieldlist,           int32  
*size)
```

<i>pointID</i>	IN:	Point id
<i>periodID</i>	IN:	Period id returned by PTdeftimeperiod
<i>level</i>	IN:	Point level (0-based)
<i>fieldlist</i>	IN:	List of fields to extract
<i>size</i>	OUT:	Size in bytes of subset period
Purpose		Retrieves information about the subsetted period.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine returns information about a subsetted time period for a particular fieldlist. It is useful when allocating space for a data buffer for the subset.
Example		In this example, we get the size of the subsetted time period defined in <i>PTdeftimeperiod</i> for the <i>Time</i> field.

```
status = PTperiodinfo(pointID, periodID, 0, "Time", &size);  
  
FORTRAN integer function ptperinfo(pointid,periodid,level,fieldlist,size)  
    integer*4          pointid  
    integer*4          periodid  
    integer*4          level  
    character*(*)      fieldlist  
    integer*4          size
```

The equivalent *FORTRAN* code for the example above is:

```
status = ptperinfo(pointid,periodid,0,"Time",size)
```

Returns Record Numbers within a Time Period

PTperiodrecs

intn PTperiodrecs(int32 *pointID*, int32 *periodID*, int32 *level*, int32 **nrec*, int32 *recs*[])

<i>pointID</i>	IN:	Point id
<i>periodID</i>	IN:	Period id returned by PTdeftimeperiod
<i>level</i>	IN:	Point level (0-based)
<i>nrec</i>	OUT:	Number of records within time period in level
<i>recs</i>	OUT:	Record numbers of subsetted records in level
Purpose		Retrieves record numbers within time period.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine returns the record numbers within a subsetted time period for a particular level. If the <i>recs</i> array is set to NULL, then the routine simply returns the number of records.
Example		In this example, we get the number of records and record numbers within the subsetted area of interest defined in <i>PTdeftimeperiod</i> for the 0 th level. status = PTperiodrecs(pointID, periodID, 0, &nrec, recs);
FORTRAN		integer function ptperrecs(<i>pointid</i> , <i>periodid</i> , <i>level</i> , <i>nrec</i> , <i>recs</i>) integer*4 <i>pointid</i> integer*4 <i>periodid</i> integer*4 <i>level</i> integer*4 <i>nrec</i> integer*4 <i>recs(*)</i>

The equivalent *FORTRAN* code for the example above is:

```
status = ptperrecs(pointid,periodid,0,nrec,recs)
```

Read Point Attribute

PTreadattr

intn PTreadattr(int32 *pointID*, char **attrname*, VOIDP *datbuf*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>attrname</i>	IN: Attribute name
<i>datbuf</i>	IN: Buffer allocated to hold attribute values
Purpose	Reads attribute from a point.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point id or number type or incorrect attribute name.
Description	The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.
Example	In this example, we read a single precision (32 bit) floating point attribute with the name "ScalarFloat":

```
status = PTreadattr(pointID, "ScalarFloat", &f32);  
FORTRAN integer function ptrdattr(pointid, attrname, datbuf)  
integer*4      pointid  
character*(*)  attrname  
<valid type>   datbuf(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = ptrdattr(pointid, "ScalarFloat", f32)
```

Read Records From a Point Level

PTreadlevel

intn PTreadlevel(int32 *pointID*, int32 *level*, char *fieldlist*, int32 *nrec*, int32 *recs[]*, VOIDP *buffer*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>level</i>	IN: Level to read (0-based)
<i>fieldlist</i>	IN: List of fields to read
<i>nrec</i>	IN: Number of records to read
<i>recs</i>	IN: Record number of records to read (0 - based)
<i>buffer</i>	OUT: Buffer to store data
Purpose	Reads data from a point level.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point id or unknown fieldname.
Description	This routine reads data from the specified fields and records of a single level in a point. Sufficient space in the read buffer must be allocated by the user.
Example	In this example we read records 0, 2, and 3 from the <i>Temperature</i> and <i>Mode</i> fields in the first level in the point referred to by the point id, <i>pointID1</i> .

```
int32 recs[3] = {0,2,3};  
status = PTreadlevel(pointID1, 0, "Temperature,Mode", 3, recs,  
buffer);
```

FORTRAN

```
integer function  
ptrdlev(pointid,level,fieldlist,nrec,recs,buffer)  
integer*4      pointid  
integer*4      level  
character(*)   fieldlist  
integer*4      nrec  
integer*4      recs(*)  
<valid type>  buffer(*)
```

The equivalent *FORTRAN* code for the example above is:

```
integer*4 recs(10)  
recs(1) = 0  
recs(2) = 2  
recs(3) = 3  
status = ptrdlev(pointid1, 1, "Temperature,Mode", 3, recs,  
buffer)
```

Returns Information About a Geographic Region

PTregioninfo

```
intn PTregioninfo(int32 pointID, int32 regionID, int32 level, char *fieldlist,  
                  int32 *size)
```

<i>pointID</i>	IN:	Point id returned by Ptcreate or PTattach
<i>regionID</i>	IN:	Region id returned by PTdefboxregion
<i>level</i>	IN:	Point level (0-based)
<i>fieldlist</i>	IN:	List of fields to extract
<i>size</i>	OUT:	Size in bytes of subset region
Purpose		Retrieves information about the subsetted region.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine returns information about a subsetted area of interest for a particular fieldlist. It is useful when allocating space for a data buffer for the subset.
Example		In this example, we get the size of the subsetted area of interest defined in <i>PTdefboxregion</i> from the <i>Longitude</i> and <i>Latitude</i> fields.

```
status = PTregioninfo(pointID, regionID, 0,  
                      "Longitude, Latitude", &size);
```

FORTRAN integer function ptreginfo(*pointid*,*regionid*,*level*,*fieldlist*,*size*)

 integer*4 *pointid*
 integer*4 *regionid*
 integer*4 *level*
 character(*) *fieldlist*
 integer*4 *size*

The equivalent *FORTRAN* code for the example above is:

```
status =  
ptreginfo(pointid,regionid,0,"Longitude, Latitude",size)
```

Returns Record Numbers within a Geographic Region

PTregionrecs

intn PTregionrecs(int32 *pointID*, int32 *regionID*, int32 *level*, int32 **nrec*, int32 *recls[]*)

<i>pointID</i>	IN:	Point id returned by PTcreate or PTattach
<i>regionID</i>	IN:	Region id returned by PTdefboxregion
<i>level</i>	IN:	Point level (0-based)
<i>nrec</i>	OUT:	Number of records within geographic region in level
<i>recls</i>	OUT:	Record numbers of subsetted records in level
Purpose		Retrieves record numbers within geographic region.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine returns the record numbers within a subsetted geographic region for a particular level. If the <i>recls</i> array is set to NULL, then the routine simply returns the number of records.
Example		In this example, we get the number of records and record numbers within the subsetted area of interest defined in <i>PTdefboxregion</i> for the 0 th level.

```
status = PTregionrecs(pointID, regionID, 0, &nrec, recls);
```

FORTRAN

```
integer function ptregrecs(pointid,regionid,level,nrec,recls)
integer*4          pointid
integer*4          regionid
integer*4          level
integer*4          nrec
integer*4          recls(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = ptregrecs(pointid,regionid,0,nrec,recls)
```

Return Information About Fields in a Point

PTsizeof

int32 PTsizeof(int32 *pointID*, char **fieldlist*, int32 *fldlevel*[])

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>fieldlist</i>	IN: Field names
<i>fldlevel</i>	OUT: Level number of each field
Purpose	Returns information on specified fields in point.
Return value	Returns size in bytes of specified fields if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point id or field names.
Description	This routine returns information about specified fields in a point regardless of level.
Example	In this example we return the size in bytes of the <i>Label</i> and <i>Rainfall</i> fields in the 2nd point defined in the <i>PTdeflevel</i> routine.

size = PTsizeof(pointID2, "Label,Rainfall", fldlevel);

The *size* variable will be 8 and the *fldlevel* = {1,2}.

FORTRAN

```
integer*4 function ptsizeroft(pointID,fieldlist,fldlevel)
integer*4      pointid
character(*)   fieldlist
integer*4      fldlevel (*)
```

The equivalent *FORTRAN* code for the example above is:

```
size = ptsizeroft(pointid2, "Label,Rainfall", fldlevel)
```

Update Records in a Point Structure

PTupdatelevel

intn PTupdatelevel(int32 *pointID*, int32 *level*, char *fieldlist*, int32 *nrec*, int32 *recs[]*,
VOIDP *data*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>level</i>	IN: Level to update (0-based)
<i>fieldlist</i>	IN: List of fields to update
<i>nrec</i>	IN: Number of records to update
<i>recs</i>	IN: Record number of records to update (0 - based)
<i>data</i>	IN: Values to be written to the fields
Purpose	Updates (corrects) data to a point level.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point id or unknown fieldname.
Description	This routine updates the specified fields and records of a single level.
Example	In this example we update records 0, 2, and 3 in the <i>Temperature</i> and <i>Mode</i> fields in the first level in the point referred to by the point id, <i>pointID1</i> .

```
int32 recs[3] = {0,2,3};

/* Fill Data Buffer */

status = PTupdatelevel(pointID1, 0, "Temperature,Mode", 3,
                       recs, datbuf);
```

The user may update a single record or all records in precisely the same manner as that used in the *PTreadlevel* examples.

FORTRAN

```
integer function
pttuplev(pointid,level,fieldlist,nrec,recs,buffer)
integer*4      pointid
integer*4      level
character(*)   fieldlist
integer*4      nrec
integer*4      recs(*)
<valid type>  buffer(*)
```

The equivalent *FORTRAN* code for the example above is:

```
integer*4 recs(10)

recs(1) = 0

recs(2) = 2

recs(3) = 3

status = ptuplev(pointid1, 1, "Temperature,Mode", 3, recs,
                  datbuf)
```

Write/Update Point Attribute

PTwriteattr

intn PTwriteattr(int32 *pointID*, char **attrname*, int32 *ntype*, int32 *count*, VOIDP *dbuf*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>attrname</i>	IN: Attribute name
<i>ntype</i>	IN: Number type of attribute
<i>count</i>	IN: Number of values to store in attribute
<i>dbuf</i>	IN: Attribute values
Purpose	Writes/Updates attribute in a point.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point id or number type.
Description	If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call.
Example	In this example, we write a single precision (32 bit) floating point number with the name "ScalarFloat" and the value 3.14:

```
f32 = 3.14;  
  
status = PTwriteattr(pointid, "ScalarFloat", DFNT_FLOAT32,  
1, &f32);
```

We can update this value by simply calling the routine again with the new value:

```
f32 = 3.14159;  
  
status = PTwriteattr(pointid, "ScalarFloat", DFNT_FLOAT32,  
1, &f32);
```

```
FORTRAN    integer function ptwrattr(pointid, attrname,  
          & ntype, count, dbuf)  
          integer*4    pointid  
          character(*) attrname  
          integer*4    ntype  
          integer*4    count  
          <valid type> dbuf(*)
```

The equivalent *FORTRAN* code for the first example above is:

```
parameter (DFNT_FLOAT32=5)  
  
f32 = 3.14  
  
status = ptwrattr(pointid, "ScalarFloat", DFNT_FLOAT32, 1,  
                  f32)
```

Write New Records to a Point Level

PTwritelevel

intn PTwritelevel(int32 *pointID*, int32 *level*, int32 *nrec*, VOIDP *data*)

<i>pointID</i>	IN: Point id returned by PTcreate or PTattach
<i>level</i>	IN: Level to write (0-based)
<i>nrec</i>	IN: Number of records to write
<i>data</i>	IN: Values to be written to the field
Purpose	Writes (appends) new records to a point level.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper point id or level number.
Description	This routine writes (appends) full records to a level. The data in each record must be <i>packed</i> . Please refer to the section on Vdatas in the HDF documentation. The input data buffer must be sufficient to fill the number of records designated.
Example	In this example we write 5 records to the first level in the point referred to by the point id, <i>pointID1</i> .

FORTRAN

```
/* Fill Data Buffer */

status = PTwritelevel(pointID1, 0, 5, datbuf);
integer function
ptwrlev(pointid,level,nrec,data)
integer*4      pointid
integer*4      level
integer*4      nrec
<valid type>  data(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = ptwrlev(pointid1, 0, 5, datbuf)
```

2.1.2 Swath Interface Functions

This section contains an alphabetical listing of all the functions in the Swath interface. The functions are alphabetized based on their C-language names.

Attach to an Existing Swath Structure

SWattach

int32 SWattach(int32 *fid*, char **swathname*)

<i>fid</i>	IN: Swath file id returned by SWopen
<i>swathname</i>	IN: Name of swath to be attached
Purpose	Attaches to an existing swath within the file.
Return value	Returns the swath handle (<i>swathID</i>) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath file id or swath name.
Description	This routine attaches to the swath using the <i>swathname</i> parameter as the identifier.
Example	In this example, we attach to the previously created swath, "ExampleSwath", within the HDF file, <i>SwathFile.hdf</i> , referred to by the handle, <i>fid</i> :

```
swathID = SWattach(fid, "ExampleSwath");
```

The swath can then be referenced by subsequent routines using the handle, *swathID*.

FORTRAN

```
integer*4 function swattach(fid,swathname)
integer*4      fid
character(*)   swathname
```

The equivalent *FORTRAN* code for the example above is:

```
swathid = swattach(fid, "ExampleSwath")
```

Return Information About a Swath Attribute

SWattrinfo

intn SWattrinfo(int32 *swathID*, char **attrname*, int32 * *numbertype*, int32 **count*)

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>attrname</i>	IN:	Attribute name
<i>numbertype</i>	OUT:	Number type of attribute
<i>count</i>	OUT:	Number of total bytes in attribute
Purpose		Returns information about a swath attribute
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine returns number type and number of elements (count) of a swath attribute.
Example		In this example, we return information about the <i>ScalarFloat</i> attribute.

```
status = SWattrinfo(swathID, "ScalarFloat", &nt, &count);
```

The *nt* variable will have the value 5 and *count* will have the value 4.

FORTRAN

```
integer function swatrinfo(swathid, attrname, ntype, count)
integer*4      swathid
character(*)   attrname
integer*4      ntype
integer*4      count
```

The equivalent *FORTRAN* code for the first example above is:

```
status = swatrinfo(swathid, "ScalarFloat", nt, count)
```

Close an HDF-EOS File

SWclose

intn SWclose(int32 *fid*)

fid IN: Swath file id returned by SWopen

Purpose Closes file.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise.

Description This routine closes the HDF swath file.

Example

```
status = swclose(fid);
```

FORTRAN integer function swclose(fid)
integer*4 fid

The equivalent *FORTRAN* code for the example above is:

```
status = swclose(fid)
```

Retrive Compression Information for Field

SWcompinfo

intn SWcompinfo(int32 *swathID*, char **fieldname*, int32 **compcode*, intn *compparm*[])

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>fieldname</i>	IN:	Fieldname
<i>compcode</i>	OUT:	HDF compression code
<i>compparm</i>	OUT:	Compression parameters
Purpose		Retrieves compression information about a field.
Return value		Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description		This routine returns the compression code and compression parameters for a given field.
Example		To retrieve the compression information about the <i>Opacity</i> field defined in the <i>SWdefcomp</i> section:

```
status = SWcompinfo(swathID, "Opacity", &compcode, compparm);
```

The *compcode* parameter will be set to 4 and *compparm*[0] to 5.

FORTRAN

```
integer function swcompinfo(gridid,fieldname compcode, compparm)
integer*4      swathid
character*(*)  fieldname
integer*4      compcode
integer compparm
```

The equivalent *FORTRAN* code for the example above is:

```
status = swcompinfo(swathid, 'Opacity', compcode, compparm)
```

The *compcode* parameter will be set to 4 and *compparm*(1) to 5.

Create a New Swath Structure

SWcreate

int32 SWcreate(int32 *fid*, char **swathname*)

<i>fid</i>	IN: Swath file id returned by SWopen
<i>swathname</i>	IN: Name of swath to be created
Purpose	Creates a swath within the file.
Return value	Returns the swath handle (<i>swathID</i>) if successful or FAIL (-1) otherwise.
Description	The swath is created as a Vgroup within the HDF file with the name <i>swathname</i> and class <i>SWATH</i> .
Example	In this example, we create a new swath structure, <i>ExampleSwath</i> , in the previously created file, <i>SwathFile.hdf</i> .

```
swathID = SWcreate(fid, "ExampleSwath");
```

The swath structure is referenced by subsequent routines using the handle, *swathID*.

FORTRAN integer*4 function swcreate(*fid*,*swathname*)
 integer*4 *fid*
 character*(*) *swathname*

The equivalent *FORTRAN* code for the example above is:

```
swathid = swcreate(fid, "ExampleSwath")
```

Define a Longitude-Latitude Box Region for a Swath

SWdefboxregion

```
int32 SWdefboxregion(int32 swathID, float64 cornerlon[], float64 cornerlat[], int32 mode)
```

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>cornerlon</i>	IN: Longitude in decimal degrees of box corners
<i>cornerlat</i>	IN: Latitude in decimal degrees of box corners
<i>mode</i>	IN: Cross Track inclusion mode
Purpose	Defines a longitude-latitude box region for a swath.
Return value	Returns the swath region ID if successful or FAIL (-1) otherwise.
Description	This routine defines a longitude-latitude box region for a swath. It returns a swath region ID which is used by the <i>SWextractregion</i> routine to read all the entries of a data field within the region. A cross track is within a region if 1) its midpoint is within the longitude-latitude "box" (HDFE_MIDPOINT), or 2) either of its endpoints is within the longitude-latitude "box" (HDFE_ENDPOINT), or 3) any point of the cross track is within the longitude-latitude "box" (HDFE_ANYPOINT), depending on the inclusion mode designated by the user. All elements within an included cross track are considered to be within the region even though a particular element of the cross track might be outside the region. The swath structure must have both <i>Longitude</i> and <i>Latitude</i> (or <i>Colatitude</i>) fields defined

Note: Users who are defining subset regions involving scenes with overlaps should add a call to the routine in *SWupdatescene* after calling this routine in order to get correctly defined region.

Example	In this example, we define a region bounded by the 3 degrees longitude, 5 degrees latitude and 7 degrees longitude, 12 degrees latitude. We will consider a cross track to be within the region if its midpoint is within the region.
---------	---

```
cornerlon[0] = 3.;  
cornerlat[0] = 5.;  
cornerlon[1] = 7.;  
cornerlat[1] = 12.;
```

```
regionID = SWdefboxregion(swathID, cornerlon, cornerlat,  
                         HDFE_MIDPOINT);  
  
FORTRAN    integer*4 function swdefboxreg(swathid, cornerlon, cornerlat, mode)  
              integer*4      swathid  
              real*8       cornerlon  
              real*8       cornerlat  
              integer*4     mode
```

The equivalent *FORTRAN* code for the example above is:

```
parameter (HDFE_MIDPOINT=0)  
  
cornerlon(1) = 3.  
  
cornerlat(1) = 5.  
  
cornerlon(2) = 7.  
  
cornerlat(2) = 12.  
  
regionid = swdefboxreg(swathid, cornerlon, cornerlat,  
                      HDFE_MIDPOINT)
```

Set Swath Field Compression

SWdefcomp

intn SWdefcomp(int32 *swathID*, int32 *compcode*, intn *compparm*[])

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>compcode</i>	IN: HDF compression code
<i>compparm</i>	IN: Compression parameters (if applicable)
Purpose	Sets the field compression for all subsequent field definitions.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description	This routine sets the HDF field compression for subsequent swath field definitions. The compression does not apply to one-dimensional fields. The compression schemes currently supported are: run length encoding (HDFE_COMP_RLE = 1), skipping Huffman (HDFE_COMP_SKPHUFF = 3), deflate (gzip) (HDFE_COMP_DEFLATE=4) and no compression (HDFE_COMP_NONE = 0, the default). Deflate compression requires a single integer compression parameter in the range of one to nine with higher values corresponding to greater compression. Compressed fields are written using the standard SWwritefield routine, however, the entire field must be written in a single call. Any portion of a compressed field can then be accessed with the SWreadfield routine. Compression takes precedence over merging so that multi-dimensional fields that are compressed are not merged. The user should refer to the HDF Reference Manual for a fuller explanation of the compression schemes and parameters.

Example	Suppose we wish to compress the <i>Pressure</i> using run length encoding, the <i>Opacity</i> field using deflate compression, the <i>Spectra</i> field with skipping Huffman compression, and use no compression for the <i>Temperature</i> field.
---------	---

```
status = SWdefcomp(swathID, HDFE_COMP_RLE, NULL);

status = SWdefdatafield(swathID, "Pressure", "Track,Xtrack",
DFNT_FLOAT32, HDFE_NOMERGE);

compparm[0] = 5;

status = SWdefcomp(swathID, HDFE_COMP_DEFLATE, compparm);

status = SWdefdatafield(swathID, "Opacity", "Track,Xtrack",
DFNT_FLOAT32, HDFE_NOMERGE);

status = SWdefcomp(swathID, HDFE_COMP_SKPHUFF, NULL);
```

```

status = SWdefdatafield(swathID, "Spectra",
    "Bands,Track,Xtrack", DFNT_FLOAT32, HDFE_NOMERGE);

status = SWdefcomp(swathID, HDFE_COMP_NONE, NULL);

status = SWdefdatafield(swathID, "Temperature", "Track,Xtrack",
DFNT_FLOAT32, HDFE_AUTOMERGE);

```

Note that the HDFE_AUTOMERGE parameter will be ignored in the *Temperature* field definition.

FORTRAN *integer function swdefcomp(swathid, compcode, compparm)*

*integer*4 swathid*

integer compcode

integer compparm

The equivalent *FORTRAN* code for the example above is:

```

parameter (HDFE_COMP_NONE=0)

parameter (HDFE_COMP_RLE=1)

parameter (HDFE_COMP_SKPHUFF=3)

parameter (HDFE_COMP_DEFLATE=4)

integer     compparm(5)

status = swdefcomp(swathid, HDFE_COMP_RLE, compparm)

status = swdefdfld(swathid, "Pressure", "Track,Xtrack",
DFNT_FLOAT32, HDFE_NOMERGE)

compparm(1) = 5

status = swdefcomp(swathid, HDFE_COMP_DEFLATE, compparm)

status = swdefdfld(swathid, "Opacity", "Track,Xtrack",
DFNT_FLOAT32, HDFE_NOMERGE)

status = swdefcomp(swathid, HDFE_COMP_SKPHUFF, compparm)

status = swdefdfld(swathid, "Spectra", "Bands,Track,Xtrack",
DFNT_FLOAT32, HDFE_NOMERGE)

status = swdefcomp(swathid, HDFE_COMP_NONE, compparm)

status = swdefdfld(swathid, "Temperature", "Track,Xtrack",
DFNT_FLOAT32, HDFE_AUTOMERGE)

```

Define a New Data Field Within a Swath

SWdefdatafield

```
intn SWdefdatafield(int32 swathID, char *fieldname, char *dimlist, int32 numbertype,  
int32 merge)
```

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>fieldname</i>	IN:	Name of field to be defined
<i>dimlist</i>	IN:	The list of data dimensions defining the field
<i>numbertype</i>	IN:	The number type of the data stored in the field
<i>merge</i>	IN:	Merge code (HDFE_NOMERGE (0) - no merge, HDFE_AUTOMERGE (1) -merge)

Note: **Illegal characters are: “/” “;” “,”**

Purpose Defines a new data field within the swath.

Return value Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is unknown dimension in the dimension list.

Description This routine defines geolocation fields to be stored in the swath. The dimensions are entered as a string consisting of geolocation dimensions separated by commas. They are entered in C order, that is, the last dimension is incremented first. The API will attempt to merge into a single object those fields that share dimensions and in case of multidimensional fields, numbertype. Two and three dimensional fields will be merged into a single three-dimensional object if the last two dimensions (in C order) are equal. If the merge code for a field is set to HDFE_NOMERGE (0), the API will not attempt to merge it with other fields. Because merging breaks the one-to-one correspondence between HDF-EOS fields and HDF SDS arrays, it should not be set if the user wishes to access the HDF-EOS field directly using HDF routines or, for example, to create an HDF attribute corresponding to the field.

Example In this example, we define a three dimensional data field named *Spectra* with dimensions *Bands*, *DataTrack*, and *DataXtrack*:

```
status = SWdefdatafield(swathID, "Spectra",  
"Bands,DataTrack,DataXtrack", DFNT_FLOAT32,  
HDFE_AUTOMERGE);
```

Note: To assure that the fields defined by SWdefdatafield are properly established in the file, the swath should be detached (and then reattached) before writing to any fields.

FORTRAN

```
integer function swdefdfld(swathid,fieldname,dimlist,numbertype,merge)
    integer*4      swathid
    character(*)   fieldname
    character(*)   dimlist
    integer*4      numbertype
    integer*4      merge
```

The equivalent *FORTRAN* code for the example above is:

```
parameter (DFNT_FLOAT32=5)
parameter (HDFE_AUTOMERGE=1)
status = swdefdfld(swathid, "Spectra",
                   "DataXtrack,DataTrack,Bands", DFNT_FLOAT32,
                   HDFE_AUTOMERGE)
```

Define a New Dimension Within a Swath

SWdefdim

intn SWdefdim(int32 *swathID*, char **fieldname*, int32 *dim*)

<i>swathID</i>	IN: swath returned by SWcreate or SWattach
<i>fieldname</i>	IN: Name of dimension to be defined
<i>dim</i>	IN: The size of the dimension
Purpose	Defines a new dimension within the swath.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is an improper swath id.
Note:	Illegal characters are: “/” “;” “,”
Description	This routine defines dimensions that are used by the field definition routines (described subsequently) to establish the size of the field.
Example	In this example, we define a track geolocation dimension, <i>GeoTrack</i> , of size 2000, a cross track dimension, <i>GeoXtrack</i> , of size 1000 and two corresponding data dimensions with twice the resolution of the geolocation dimensions:

```
status = SWdefdim(swathID, "GeoTrack", 2000);
status = SWdefdim(swathID, "GeoXtrack", 1000);
status = SWdefdim(swathID, "DataTrack", 4000);
status = SWdefdim(swathID, "DataXtrack", 2000);
status = SWdefdim(swathID, "Bands", 5);
```

To specify an unlimited dimension which can be used to define an appendable array, the dimension value should be set to zero or equivalently, *SD_UNLIMITED*:

```
status = SWdefdim(swathID, "Unlim", SD_UNLIMITED);
FORTRAN integer function swdefdim(swathid,fieldname,dim)
integer*4      swathid
character(*)   fieldname
integer*4      dim
The equivalent FORTRAN code for the first example above is:
status = swdefdim(swathid, "GeoTrack", 2000)
The equivalent FORTRAN code for the unlimited dimension example above is:
```

```
parameter (SD_UNLIMITED=0)
status = swdefdim(swathid, "Unlim", SD_UNLIMITED)
```

Define Mapping Between Geolocation and Data Dimensions

SWdefdimmap

intn SWdefdimmap(int32 *swathID*, char **geodim*, char **datadim*, int32 *offset*, int32 *increment*)

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>geodim</i>	IN:	Geolocation dimension name
<i>datadim</i>	IN:	Data dimension name
<i>offset</i>	IN:	The offset of the geolocation dimension with respect to the data dimension
<i>increment</i>	IN:	The increment of the geolocation dimension with respect to the data dimension
Purpose		Defines monotonic mapping between the geolocation and data dimensions.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is incorrect geolocation or data dimension name.
Description		Typically the geolocation and data dimensions are of different size (resolution). This routine established the relation between the two where the offset gives the index of the data element (0-based) corresponding to the first geolocation element and the increment gives the number of data elements to skip for each geolocation element. If the geolocation dimension begins "before" the data dimension, then the offset is negative. Similarly, if the geolocation dimension has higher resolution than the data dimension, then the increment is negative.
Example		In this example, we establish that (1) the first element of the <i>GeoTrack</i> dimension corresponds to the first element of the <i>DataTrack</i> dimension and the data dimension has twice the resolution as the geolocation dimension, and (2) the first element of the <i>GeoXtrack</i> dimension corresponds to the second element of the <i>DataXtrack</i> dimension and the data dimension has twice the resolution as the geolocation dimension:

```
status = SWdefdimmap(swathID, "GeoTrack", "DataTrack", 0,  
                      2);  
  
status = SWdefdimmap(swathID, "GeoXtrack", "DataXtrack", 1,  
                      2);
```

```
FORTRAN    integer function  
           swdefmap(swathid,geodim,datadim,offset,increment)  
           integer*4      swathid  
           character(*)   geodim  
           character(*)   datadim  
           integer*4      offset  
           integer*4      increment
```

The equivalent *FORTRAN* code for the second example above is:

```
status = swdefmap(swathid, "GeoTrack", "DataTrack", 0, 2)  
status = swdefmap(swathid, "GeoXtrack", "DataXtrack", 1, 2)
```

Define a New Geolocation Field Within a Swath

SWdefgeofield

```
intn SWdefgeofield(int32 swathID, char *fieldname, char *dimlist, int32 numbertype,  
                    int32 merge)
```

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>fieldname</i>	IN: Name of field to be defined
<i>dimlist</i>	IN: The list of geolocation dimensions defining the field
<i>numbertype</i>	IN: The number type of the data stored in the field
<i>merge</i>	IN: Merge code (HDFE_NOMERGE (0) - no merge, HDFE_AUTOMERGE (1) -merge)
Purpose	Defines a new geolocation field within the swath.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is unknown dimension in the dimension list.
Description	This routine defines geolocation fields to be stored in the swath. The dimensions are entered as a string consisting of geolocation dimensions separated by commas. They are entered in C order, that is, the last dimension is incremented first. The API will attempt to merge into a single object those fields that share dimensions and in case of multidimensional fields, <i>numbertype</i> . Two and three dimensional fields will be merged into a single three-dimensional object if the last two dimensions (in C order) are equal). If the merge code for a field is set to 0, the API will not attempt to merge it with other fields. Fields using the unlimited dimension will not be merged. Because merging breaks the one-to-one correspondence between HDF-EOS fields and HDF SDS arrays, it should not be set if the user wishes to access the HDF-EOS field directly using HDF routines or, for example, to create an HDF attribute corresponding to the field.
Example	In this example, we define the geolocation fields, <i>Longitude</i> and <i>Latitude</i> with dimensions <i>GeoTrack</i> and <i>GeoXtrack</i> and containing 4 byte floating point numbers. We allow these fields to be merged into a single object:

```
status = SWdefgeofield(swathID, "Longitude",  
                      "GeoTrack,GeoXtrack", DFNT_FLOAT32, HDFE_AUTOMERGE);  
  
status = SWdefgeofield(swathID, "Latitude",  
                      "GeoTrack,GeoXtrack", DFNT_FLOAT32, HDFE_AUTOMERGE);
```

Note: To assure that the fields defined by SWdefgeofield are properly established in the file, the swath should be detached (and then reattached) before writing to any fields.

FORTRAN

```
integer function swdefgfld(swathid, fieldname, dimlist, numbertype, merge)
    integer*4      swathid
    character(*)   fieldname
    character(*)   dimlist
    integer*4      numbertype
    integer*4      merge
```

The equivalent *FORTRAN* code for the first example above is:

```
parameter (DFNT_FLOAT32=5)
parameter (HDFE_AUTOMERGE=1)
status = SWdefgeofield(swathID, "Longitude",
                      "Geotrack,GeoXtrack", DFNT_FLOAT32,HDFE_AUTOMERGE)
```

The dimensions are entered in *FORTRAN* order with the first dimension incremented first.

Define Indexed Mapping Between Geolocation and Data Dimension

SWdefidxmap

intn SWdefidxmap(int32 *swathID*, char **geodim*, char **datadim*, int32 *index*[]),

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>geodim</i>	IN: Geolocation dimension name
<i>datadim</i>	IN: Data dimension name
<i>index</i>	IN: The array containing the indices of the data dimension to which each geolocation element corresponds.
Purpose	Defines a non-regular mapping between the geolocation and data dimension.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is incorrect geolocation or data dimension name.
Description	If there does not exist a regular (linear) mapping between a geolocation and data dimension, then the mapping must be made explicit. Each element of the index array, whose dimension is given by the geolocation size, contains the element number (0-based) of the corresponding data dimension.
Example	In this example, we consider the (simple) case of a geolocation dimension, <i>IdxGeo</i> of size 5 and a data dimension <i>IdxData</i> of size 8.

```
int32 index[5] = {0,2,3,6,7};  
status = SWdefidxmap(swathID, "IdxGeo", "IdxData", index);
```

In this case the 0th element of *IdxGeo* will correspond to the 0th element of *IdxData*, the 1st element of *IdxGeo* to the 2nd element of *IdxData*, etc.

FORTRAN
integer function
swdefimap(*swathid*, *geodim*, *datadim*, *index*)
integer*4 *swathid*
character(*) *geodim*
character(*) *datadim*
integer*4 *index* (*)

The equivalent *FORTRAN* code for the example above is:

```
int32 index[5] = {0,2,3,6,7};  
status = swidefmap(swathid, "IdxGeo", "IdxData", index)
```

Note: The *index* array should be 0-based.

Define a Time Period of Interest

SWdeftimeperiod

```
int32 SWdeftimeperiod(int32 swathID, float64 starttime , float64 stoptime
                      int32 mode)
```

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>starttime</i>	IN:	Start time of period
<i>stoptime</i>	IN:	Stop time of period
<i>mode</i>	IN:	Cross Track inclusion mode
Purpose		Defines a time period for a swath.
Return value		Returns the swath period ID if successful or FAIL (-1) otherwise.
Description		This routine defines a time period for a swath. It returns a swath period ID which is used by the <i>SWextractperiod</i> routine to read all the entries of a data field within the time period. A cross track is within a time period if 1) its midpoint is within the time period "box", or 2) either of its endpoints is within the time period "box", or 3) any point of the cross track is within the time period "box", depending on the inclusion mode designated by the user. All elements within an included cross track are considered to be within the time period even though a particular element of the cross track might be outside the time period. The swath structure must have the <i>Time</i> field defined
Example		In this example, we define a time period with a start time of 35232487.2 and a stop time of 36609898.1. We will consider a cross track to be within the time period if either one of the time values at the endpoints of a cross track are within the time period. <pre>starttime = 35232487.2; stoptime = 36609898.1; periodID = SWdeftimeperiod(swathID, starttime, stoptime, HDFE_ENDPOINT);</pre>

```
FORTRAN    integer*4 function swdeftmeper(swathid, starttime, stoptime, mode)
            integer*4      swathid
            real*8       starttime
            real*8       stoptime
            integer*4      mode
```

The equivalent *FORTRAN* code for the example above is:

```
parameter (HDFE_ENDPOINT=1)
starttime = 35232487.2
stoptime = 36609898.1
periodID = swdeftmeper(swathID, starttime, stoptime,
HDFE_ENDPOINT)
```

Define a Vertical Subset Region

SWdefvrtrregion

int32 SWdefvrtrregion(int32 *swathID*, int32 *regionID*, char **vertObj*, float64 *range*[])

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>regionID</i>	IN:	Region (or period) id from previous subset call
<i>vertObj</i>	IN:	Dimension or field to subset by
<i>range</i>	IN:	Minimum and maximum range for subset
Purpose		Subsets on a monotonic field or contiguous elements of a dimension.
Return value		Returns the swath region ID if successful or FAIL (-1) otherwise.
Description		Whereas the <i>SWdefboxregion</i> and <i>SWdeftimeperiod</i> routines perform subsetting along the “Track” dimension, this routine allows the user to subset along any dimension. The region is specified by a set of minimum and maximum values and can represent either a dimension index (case 1) or field value range(case 2). In the second case, the field must be one-dimensional and the values must be monotonic (strictly increasing or decreasing) in order that the resulting dimension index range be contiguous. (For the current version of this routine, the second option is restricted to fields with number type: INT16, INT32, FLOAT32, FLOAT64.) This routine may be called after <i>SWdefboxregion</i> or <i>SWdeftimeperiod</i> to provide both geographic or time and “vertical” subsetting. In this case the user provides the id from the previous subset call. (This same id is then returned by the function.) This routine may also be called “stand-alone” by setting the region ID to HDFE_NOPREVSUB (-1).

This routine may be called up to eight times with the same region ID. It this way a region can be subsetted along a number of dimensions.

The *SWregioninfo* and *SWextractregion* routines work as before, however because there is no mapping performed between geolocation dimensions and data dimensions the field to be subsetted, (the field specified in the call to *SWregioninfo* and *SWextractregion*) must contain the dimension used explicitly in the call to *SWdefvrtrregion* (case 1) or the dimension of the one-dimensional field (case 2).

Example	Suppose we have a field called <i>Pressure</i> of dimension <i>Height</i> (= 10) whose values increase from 100 to 1000. If we desire all the elements with values between 500 and 800, we make the call:
---------	---

```

range[0] = 500.;
range[1] = 800.;
regionID = SWdefvrtrregion(swathID, HDFE_NOPREVSUB, "Pressure",
range);

```

The routine determines the elements in the *Height* dimension which correspond to the values of the *Pressure* field between 500 and 800.

If we wish to specify the subset as elements 2 through 5 (0 - based) of the *Height* dimension, the call would be:

```

range[0] = 2;
range[1] = 5;
regionID = SWdefvrtrregion(swathID, HDFE_NOPREVSUB,
"DIM:Height", range);

```

The “DIM:” prefix tells the routine that the range corresponds to elements of a dimension rather than values of a field.

In this example, any field to be subsetted must contain the *Height* dimension.

If a previous subset region or period was defined with id, *subsetID*, that we wish to refine further with the vertical subsetting defined above we make the call:

```

regionID = SWdefvrtrregion(swathID, subsetID, "Pressure",
range);

```

The return value, *regionID* is set equal to *subsetID*. That is, the subset region is modified rather than a new one created.

We can further refine the subset region with another call to the routine:

```

freq[0] = 1540.3;
freq[1] = 1652.8;

regionID = SWdefvrtrregion(swathID, regionID, "FreqRange",
freq);

```

```
FORTRAN    integer*4 function swdefvrtrg(swathid, regionid, vertobj, range)
            integer*4      swathid
            integer*4      regionid
            character(*)   vertobj
            real*8        range
```

The equivalent *FORTRAN* code for the examples above is:

```
parameter (HDFE_NOPREVSUB=-1)
range(1) = 500.
range(2) = 800.
regionid = swdefvrtrg(swathid, HDFE_NOPREVSUB, "Pressure",
range)
range(1) = 3 ! Note 1-based element numbers
range(2) = 6
regionid = swdefvrtrg(swathid, HDFE_NOPREVSUB, "DIM:Height",
range)
regionid = swdefvrtrg(swathid, subsetid, "Pressure", range)
regionid = swdefvrtrg(swathid, regionid, "FreqRange", freq)
```

Detach from a Swath Structure

SWdetach

intn SWdetach(int32 *swathID*)

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
Purpose	Detaches from swath interface.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description	This routine should be run before exiting from the swath file for every swath opened by SWcreate or SWattach.
Example	In this example, we detach the swath structure, <i>ExampleSwath</i> :

```
status = SWdetach(swathID);  
FORTRAN integer function swdetach(swathid)  
integer*4      swathid
```

The equivalent *FORTRAN* code for the example above is:

```
status = swdetach(swathid)
```

Retrieve Size of Specified Dimension

SWdiminfo

int32 SWdiminfo(int32 *swathID*, char **dimname*)

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>dimname</i>	IN: Dimension name
Purpose	Retrieve size of specified dimension.
Return value	Size of dimension if successful or FAIL (-1) otherwise. If -1, could signify an improper swath id or dimension name.
Description	This routine retrieves the size of specified dimension.
Example	In this example, we retrieve information about the dimension, "GeoTrack":

```
dimsize = SWdiminfo(swathID, "GeoTrack");
```

The return value, *dimsize*, will be equal to 2000.

FORTRAN integer*4 function swdiminfo(*swathid*,*dimname*)
 integer*4 *swathid*
 character(*) *dimname*

The equivalent *FORTRAN* code for the example above is:

```
dimsize = swdiminfo(swathid, "GeoTrack")
```

Duplicate a Region or Period

SWdupregion

int32 SWdupregion(int32 *regionID*)

regionID IN: Region or period id returned by SWdefboxregion, SWdeftimeperiod, or SWdefvrtrregion.

Purpose Duplicates a region.

Return value Returns new region or period ID if successful or FAIL (-1) otherwise.

Description This routine copies the information stored in a current region or period to a new region or period and generates a new id. It is usefully when the user wishes to further subset a region (period) in multiple ways.

Example In this example, we first subset a swath with *SWdefboxregion*, duplicate the region creating a new region ID, *regionID2*, and then perform two different vertical subsets of these (identical) geographic subset regions:

```
regionID = SWdefboxregion(swathID, cornerlon, cornerlat,  
                         HDFE_MIDPOINT);  
  
regionID2 = SWdupregion(regionID);  
  
regionID = SWdefvrtrregion(swathID, regionID, "Pressure",  
                           rangePres);  
  
regionID2 = SWdefvrtrregion(swathID, regionID2, "Temperature",  
                           rangeTemp);
```

FORTRAN integer*4 swdupreg(*regionid*)

integer*4 *regionid*

The equivalent *FORTRAN* code for the example above is:

```
parameter (HDFE_MIDPOINT=0)  
  
regionid = swdefboxreg(swathid, cornerlon, cornerlat,  
                      HDFE_MIDPOINT)  
  
regionid2 = swdupreg(regionid)  
  
regionid = swdefvrtrreg(swathid, regionid, 'Pressure',  
                        rangePres)  
  
regionid2 = swdefvrtrreg(swathid, regionid2, 'Temperature',  
                        rangeTemp)
```

Read Data from a Defined Time Period

SWextractperiod

```
intn SWextractperiod(int32 swathID, int32 periodID, char * fieldname, int32  
                      external_mode, VOIDP buffer)
```

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>periodID</i>	IN:	Period id returned by SWdeftimeperiod
<i>fieldname</i>	IN:	Field to subset
<i>external_mode</i>	IN:	External geolocation mode
<i>buffer</i>	OUT:	Data buffer
Purpose		Extracts (reads) from subsetted time period.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine reads data into the data buffer from the subsetted time period. Only complete crosstracks are extracted. If the external_mode flag is set to <i>HDFE_EXTERNAL</i> (1) then the geolocation fields and the data field can be in different swaths. If set to <i>HDFE_INTERNAL</i> (0), then these fields must be in the same swath structure.
Example		In this example, we read data within the subsetted time period defined in <i>SWdeftimeperiod</i> from the <i>Spectra</i> field. Both the geolocation fields and the <i>Spectra</i> data field are in the same swath.

```
status = SWextractperiod(SWid, periodID, "Spectra",  
                         HDFE_INTERNAL, datbuf);
```

FORTRAN integer function swextper(*periodid*, *fieldname*, *external_mode*, *buffer*)
 integer*4 *periodid*
 character(*) *fieldname*
 integer*4 *external_mode*
 <valid type> *buffer(*)*

The equivalent *FORTRAN* code for the example above is:

```
parameter (HDFE_INTERNAL=0)  
  
status = swextper(periodid, "Spectra", HDFE_INTERNAL, datbuf)
```

Read Data from a Geographic Region

SWextractregion

```
intn SWextractregion(int32 swathID, int32 regionID, char * fieldname, int32  
                      external_mode, VOIDP buffer)
```

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>regionID</i>	IN: Region id returned by SWdefboxregion
<i>fieldname</i>	IN: Field to subset
<i>external_mode</i>	IN: External geolocation mode
<i>buffer</i>	OUT: Data buffer
Purpose	Extracts (reads) from subsetted region.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description	This routine reads data into the data buffer from the subsetted region. Only complete crosstracks are extracted. If the external_mode flag is set to <i>HDFE_EXTERNAL</i> (1) then the geolocation fields and the data field can be in different swaths. If set to <i>HDFE_INTERNAL</i> (0), then these fields must be in the same swath structure.
Example	In this example, we read data within the subsetted region defined in <i>SWdefboxregion</i> from the <i>Spectra</i> field. Both the geolocation fields and the <i>Spectra</i> data field are in the same swath. <pre>status = SWextractregion(SWid, regionID, "Spectra", HDFE_INTERNAL, datbuf);</pre>
FORTTRAN	<pre>integer function swextreg(swathid, regionid, fieldname, external_mode, buffer)</pre> <pre>integer*4 <i>swathid</i> integer*4 <i>regionid</i> character(*) <i>fieldname</i> integer*4 <i>external_mode</i> <valid type> <i>buffer(*)</i></pre>

The equivalent *FORTTRAN* code for the example above is:

```
parameter (HDFE_INTERNAL=0)

status = swextreg(swathid, regionid, "Spectra",
HDFE_INTERNAL, datbuf)
```

Retrieve Information About a Swath Field

SWfieldinfo

```
intn SWfieldinfo(int32 swathID, char *fieldname, int32 *rank, int32 dims[], int32  
*numbertype, char *dimlist)
```

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>fieldname</i>	IN:	Fieldname
<i>rank</i>	OUT:	Rank of field
<i>dims</i>	OUT:	Array containing the dimension sizes of the field
<i>numbertype</i>	OUT:	Pointer to the numbertype of the field
<i>dimlist</i>	OUT:	List of dimensions in field
Purpose	Retrieve information about a specific geolocation or data field in the swath.	
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. A typical reason for failure is the specified field does not exist.	
Description	This routine retrieves information on a specific data field.	
Example	In this example, we retrieve information about the <i>Spectra</i> data fields:	

```
status = SWfieldinfo(swathID, "Spectra", &rank, dims,  
numbertype, dimlist);
```

The return parameters will have the following values:

rank=3, *numbertype*=5, *dims*[3]={5,4000,2000} and *dimlist*="Bands,
DataTrack, DataXtrack"

If one of the dimensions in the field is appendable, then the current value for that dimension will be returned in the *dims* array.

```
FORTRAN    integer function swfldinfo(swathid, fieldname, rank, dims, numbertype,  
                                dimlist)  
  
           integer*4      swathid  
           character(*)   fieldname  
           integer*4      rank  
           integer*4      dims(*)  
           integer*4      numbertype  
           integer*4      dimlist
```

The equivalent *FORTRAN* code for the example above is:

```
status = swfldinfo(swathid, "Spectra", rank, dims, numbertype,  
                   dimlist)
```

The return parameters will have the following values:

rank=3, numbertype=5, dims[3]={2000,4000,5} and dimlist="DataXtrack,
DataTrack,Bands"

Note that the dimensions array and dimension list are in *FORTRAN* order.

Get Fill Value for a Specified Field

SWgetfillvalue

intn SWgetfillvalue(int32 *swathID*, char **fieldname*, VOIDP *fillvalue*)

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>fieldname</i>	IN: Fieldname
<i>fillvalue</i>	OUT: Space allocated to store the fill value
Purpose	Retrieves fill value for the specified field.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or number type.
Description	It is assumed the number type of the fill value is the same as the field.

Example In this example, we get the fill value for the "Temperature" field:

```
status = SWgetfillvalue(swathID, "Temperature", &tempfill);
```

FORTRAN integer function

```
swgetfill(swathid,fieldname,fillvalue)  
integer*4      swathid  
character*(*)  fieldname  
<valid type>  fillvalue(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = swgetfill(swathid, "Temperature", tempfill)
```

Retrieve type of dimension mapping when first dimension is geodim

SWgeomapinfo

intn SWgeomapinfo(int32 *swathID*, char **geodim*)

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>geodim</i>	IN: Dimension name
Purpose	Retrieve type of dimension mapping for a dimension.
Return value	Returns (2) for indexed mapping, (1) for regular mapping, (0) if dimension is not mapped, or FAIL (-1) otherwise.
Description	This routine checks the type of mapping (regular or indexed).
Example	In this example, we retrieve information about the type of mapping between the “IdxGeo” and “IdxData” dimensions, defined by Swdefidxmap.

```
Regmap = SWgeomapinfo(swathID, geodim);
```

We will have regmap = 2 for indexed mapping between the “IdxGeo” and “IdxData” dimensions.

NOTE: If the dimension has been mapped regular and indexed, the function will return a value of 3.

FORTRAN

```
integer function swgmapinfo(swathid,geodim)
integer*4      swathid
character(*)   geodim
```

The equivalent *FORTRAN* code for the example above is:

```
status = swgmapinfo(swathid, geodim)
```

Retrieve Indexed Geolocation Mapping

SWidxmapinfo

int32 SWidxmapinfo(int32 *swathID*, char **geodim*, char **datadim*, int32 *index*[])

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>geodim</i>	IN:	Indexed Geolocation dimension name
<i>datadim</i>	IN:	Indexed Data dimension name
<i>index</i>	OUT:	Index mapping array
Purpose		Retrieve indexed array of specified geolocation mapping.
Return value		Returns size of indexed array if successful or FAIL (-1) otherwise. A typical reason for failure is the specified mapping does not exist.
Description		This routine retrieves the size of the indexed array and the array of indexed elements of the specified geolocation mapping.
Example		In this example, we retrieve information about the indexed mapping between the "IdxGeo" and "IdxData" dimensions:

```
idxsz = SWidxmapinfo(swathID, "IdxGeo", "IdxData", index);
```

The variable, *idxsz*, will be equal to 5 and *index*[5] = {0,2,3,6,7}.

FORTRAN

```
integer*4 function swimapinfo(swathid, geodim, datadim, index)
integer*4      swathid
character(*)   geodim
character(*)   datadim
integer*4      index(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = swimapinfo(swathid, "IdxGeo", "IdxData", index)
```

Retrieve Information Swath Attributes

SWinqattrs

int32 SWinqattrs(int32 *swathID*, char **attrlist*, int32 **strbufsize*)

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>attrlist</i>	OUT: Attribute list (entries separated by commas)
<i>strbufsize</i>	OUT: String length of attribute list
Purpose	Retrieve information about attributes defined in swath.
Return value	Number of attributes found if successful or FAIL (-1) otherwise.
Description	The attribute list is returned as a string with each attribute name separated by commas. If <i>attrlist</i> is set to NULL, then the routine will return just the string buffer size, <i>strbufsize</i> . This variable does not count the null string terminator.
Example	In this example, we retrieve information about the attributes defined in a swath structure. We assume that there are two attributes stored, <i>attrOne</i> and <i>attr_2</i> :

```
nattr = SWinqattrs(swathID, NULL, &strbufsize);
```

The parameter, *nattr*, will have the value 2 and *strbufsize* will have value 14.

```
nattr = SWinqattrs(swathID, attrlist, &strbufsize);
```

The variable, *attrlist*, will be set to:

"*attrOne,attr_2*".

FORTRAN integer*4 function swinqattrs(*swathid,attrlist,strbufsize*)
 integer*4 *swathid*
 character*(*) *attrlist*
 integer*4 *strbufsize*

The equivalent *FORTRAN* code for the example above is:

```
nattr = SWinqattrs(swathID, attrlist, &strbufsize)
```

Retrieve Information About Data Fields Defined in Swath

SWinqdatafields

int32 SWinqdatafields(int32 *swathID*, char **fieldlist*, int32 *rank[]*, int32 *numbertype[]*)

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>fieldlist</i>	OUT: Listing of data fields (entries separated by commas)
<i>rank</i>	OUT: Array containing the rank of each data field
<i>numbertype</i>	OUT: Array containing the numbertype of each data field
Purpose	Retrieve information about all of the data fields defined in swath.
Return value	Number of data fields found if successful or FAIL (-1) otherwise. A typical reason for failure is an improper swath id.
Description	The field list is returned as a string with each data field separated by commas. The <i>rank</i> and <i>numbertype</i> arrays will have an entry for each field. Output parameters set to <i>NULL</i> will not be returned.
Example	In this example we retrieve information about the data fields:

```
nflds = SWinqdatafields(swathID, fieldlist, rank, numbertype);
```

The parameter, *fieldlist*, will have the value:

"Spectra" with *ndim* = 1, *rank[1]*={3}, *numbertype[1]*={5}

FORTRAN	integer*4 function swinqdfls(<i>swathid</i> , <i>fieldlist</i> , <i>rank</i> , <i>numbertype</i>)
	integer*4 <i>swathid</i>
	character*(*) <i>fieldlist</i>
	integer*4 <i>rank(*)</i>
	integer*4 <i>numbertype(*)</i>

The equivalent *FORTRAN* code for the example above is:

```
nflds = swinqdfls(swathid, fieldlist, rank, numbertype)
```

Retrieve Information About Dimensions Defined in Swath

SWinqdims

int32 SWinqdims(int32 *swathID*, char **dimname*, int32 *dims*[])

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>dimname</i>	OUT: Dimension list (entries separated by commas)
<i>dims</i>	OUT: Array containing size of each dimension
Purpose	Retrieve information about all of the dimensions defined in swath.
Return value	Number of dimension entries found if successful or FAIL (-1) otherwise. A typical reason for failure is an improper swath id.
Description	The dimension list is returned as a string with each dimension name separated by commas. Output parameters set to <i>NULL</i> will not be returned.
Example	In this example, we retrieve information about the dimensions defined in the <i>ExampleSwath</i> structure:

```
ndims = SWinqdims(swathID, dimname, dims);
```

The parameter, *dimname*, will have the value:

"GeoTrack,GeoXtrack,DataTrack,DataXtrack,Bands,Unlim"

with *ndims* = 5, *dims*[5]={2000,1000,4000,2000,5,0}

FORTRAN

```
integer*4 function swinqdims(swathid,dimname,dims)
integer*4      swathid
character(*)   dimname
integer*4      dims(*)
```

The equivalent *FORTRAN* code for the example above is:

```
ndims = swingdims(swathid, dimname, dims)
```

Retrieve Information About Geolocation Fields Defined in Swath

SWinqgeofields

int32 SWinqgeofields(int32 *swathID*, char **fieldlist*, int32 *rank*[], int32 *numbertype*[])

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>fieldlist</i>	OUT: Listing of geolocation fields (entries separated by commas)
<i>rank</i>	OUT: Array containing the rank of each geolocation field
<i>numbertype</i>	OUT: Array containing the numbertype of each geolocation field
Purpose	Retrieve information about all of the geolocation fields defined in swath.
Return value	Number of geolocation fields found if successful or FAIL (-1) otherwise. A typical reason for failure is an improper swath id.
Description	The field list is returned as a string with each geolocation field separated by commas. The <i>rank</i> and <i>numbertype</i> arrays will have an entry for each field. Output parameters set to <i>NULL</i> will not be returned.
Example	In this example, we retrieve information about the geolocation fields:

```
nflds = SWinqgeofields(swathID, fieldlist, rank, numbertype);
```

The parameter, *fieldlist*, will have the value: "Longitude,Latitude" with *nflds* = 2, *rank*[2]={2,2}, *numbertype*[2]={5,5}

FORTRAN integer*4 function swinqgflds(swathid, fieldlist, rank, numbertype)
 integer*4 *swathid*
 character*(*) *fieldlist*
 integer*4 *rank*(*)
 integer*4 *numbertype*(*)

The equivalent *FORTRAN* code for the example above is:

```
nflds = swinqgflds(swathid, fieldlist, rank, numbertype)
```

Retrieve Information About Indexed Mappings Defined in Swath

SWinqidxmaps

int32 SWinqidxmaps(int32 swathID, char *idxmap, int32 idxsizes[])

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>idxmap</i>	OUT: Indexed Dimension mapping list (entries separated by commas)
<i>idxsizes</i>	OUT: Array containing the sizes of the corresponding index arrays.
Purpose	Retrieve information about all of the indexed geolocation/data mappings defined in swath.
Return value	Number of indexed mapping relations found if successful or FAIL (-1) otherwise. A typical reason for failure is an improper swath id.
Description	The dimension mapping list is returned as a string with each mapping separated by commas. The two dimensions in each mapping are separated by a slash (/). Output parameters set to <i>NULL</i> , will not be returned.
Example	In this example, we retrieve information about the indexed dimension mappings:

```
nidxmaps = SWinqidxmaps(swathID, idxmap, idxsizes);
```

The variable, *idxmap*, will contain the string:

"IdxGeo/IdxData" with *nidxmaps* = 1 and *idxsizes[1]*={5}.

FORTRAN integer*4 function

 swinqimaps(*swathid*,*dimmap*,*idxsizes*)

 integer*4 *swathid*
 character(*) *dimmap*
 integer*4 *idxsizes(*)*

The equivalent *FORTRAN* code for the example above is:

```
nidxmaps = swingimaps(swathid, dimmap, idxsizes)
```

Retrieve Information About Dimension Mappings Defined in Swath

SWinqmaps

int32 SWinqmaps(int32 *swathID*, char **dimmap*, int32 *offset[]*, int32 *increment[]*)

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>dimmap</i>	OUT: Dimension mapping list (entries separated by commas)
<i>offset</i>	OUT: Array containing the offset of each geolocation relation
<i>increment</i>	OUT: Array containing the increment of each geolocation relation
Purpose	Retrieve information about all of the (non-indexed) geolocation relations defined in swath.
Return value	Number of geolocation relation entries found if successful or FAIL (-1) otherwise. A typical reason for failure is an improper swath id.
Description	The dimension mapping list is returned as a string with each mapping separated by commas. The two dimensions in each mapping are separated by a slash (/). Output parameters set to <i>NULL</i> will not be returned.
Example	In this example, we retrieve information about the dimension mappings in the <i>ExampleSwath</i> structure:

```
nmaps = SWinqmaps(swathID, dimmap, offset, increment);
```

The variable, *dimmap*, will contain the string:

"GeoTrack/DataTrack,GeoXtrack/DataXtrack" with *nmaps* = 2, *offset[2]={0,1}* and *increment[2]={2,2}*.

FORTRAN integer*4 function

 swinqmaps(*swathid*,*dimmap*,*offset*,*increment*)

 integer*4 *swathid*
 character(*) *dimmap*
 integer*4 *offset(*)*
 integer*4 *increment(*)*

The equivalent *FORTRAN* code for the example above is:

```
nmaps = swingmaps(swathid, dimmap, offset, increment)
```

Retrieve Swath Structures Defined in HDF-EOS File

SWinqswath

int32 SWinqswath(char * *filename*, char **swathlist*, int32 **strbufsize*)

<i>filename</i>	IN: HDF-EOS filename
<i>swathlist</i>	OUT: Swath list (entries separated by commas)
<i>strbufsize</i>	OUT: String length of swath list
Purpose	Retrieves number and names of swaths defined in HDF-EOS file.
Return value	Number of swaths found if successful or FAIL (-1) otherwise.
Description	The swath list is returned as a string with each swath name separated by commas. If <i>swathlist</i> is set to NULL, then the routine will return just the string buffer size, <i>strbufsize</i> . If <i>strbufsize</i> is also set to NULL, the routine returns just the number of swaths. Note that <i>strbufsize</i> does not count the null string terminator.

Example In this example, we retrieve information about the swaths defined in an HDF-EOS file, *HDFEOS.hdf*. We assume that there are two swaths stored, *SwathOne* and *Swath_2*:

```
nswath = SWinqswath("HDFEOS.hdf", NULL, &strbufsize);
```

The parameter, *nswath*, will have the value 2 and *strbufsize* will have value 16.

```
nswath = SWinqswath("HDFEOS.hdf", swathlist, &strbufsize);
```

The variable, *swathlist*, will be set to:

“*SwathOne,Swath_2*”.

FORTRAN integer*4 function swinqswath(*filename,swathlist,strbufsize*)
 character*(*) *filename*
 character*(*) *swathlist*
 integer*4 *strbufsize*

The equivalent *FORTRAN* code for the example above is:

```
nswath = SWinqswath("HDFEOS.hdf", swathlist, &strbufsize)
```

Retrieve Offset and Increment of Specific Dimension Mapping

SWmapinfo

```
intn SWmapinfo(int32 swathID, char *geodim, char *datadim, int32 offset, int32  
                  increment)
```

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>geodim</i>	IN: Geolocation dimension name
<i>datadim</i>	IN: Data dimension name
<i>offset</i>	OUT: Mapping offset
<i>increment</i>	OUT: Mapping increment
Purpose	Retrieve offset and increment of specific monotonic geolocation mapping.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. A typical reason for failure is the specified mapping does not exist.
Description	This routine retrieves offset and increment of the specified geolocation mapping.
Example	In this example, we retrieve information about the mapping between the <i>GeoTrack</i> and <i>DataTrack</i> dimensions:

```
status = SWmapinfo(swathID, "GeoTrack", "DataTrack",  
                  &offset, &increment);
```

The variable *offset* will be 0 and *increment* 2.

FORTRAN

```
integer function swmapinfo(swathid, geodim, datadim, offset, increment)  
  
    integer*4     swathid  
    character*(*) geodim  
    character*(*) datadim  
    integer*4     offset  
    integer*4     increment
```

The equivalent *FORTRAN* code for the example above is:

```
status = swmapinfo(swathid, "GeoTrack", "DataTrack",  
                  offset, increment)
```

Return Number of Specified Objects in a Swath

SWnentries

int32 SWnentries(int32 *swathID*, int32 *entrycode*, int32 **strbufsize*)

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>entrycode</i>	IN: Entrycode
<i>strbufsize</i>	OUT: String buffer size
Purpose	Returns number of entries and descriptive string buffer size for a specified entity.
Return value	Number of entries if successful or FAIL (-1) otherwise. A typical reason for failure is an improper swath id or entry code.
Description	This routine can be called before an inquiry routines in order to determine the sizes of the output arrays and descriptive strings. The string length does not include the NULL terminator.

The entry codes are:

- HDFE_NENTDIM (0) - Dimensions
- HDFE_NENTMAP (1) - Dimension Mappings
- HDFE_NENTIMAP (2) - Indexed Dimension Mappings
- HDFE_NENTGFLD (3) - Geolocation Fields
- HDFE_NENTDFLD (4) - Data Fields

Example	In this example, we determine the number of dimension mapping entries and the size of the map list string.
---------	--

```
nmaps = SWnentries(swathID, HDFE_NENTMAP, &bufsz);
```

The return value, *nmaps*, will be equal to 2 and *bufsz* = 39

FORTRAN	integer*4 function swnentries(<i>swathid</i> , <i>entrycode</i> , <i>bufsize</i>)
	integer*4 <i>swathid</i>
	integer*4 <i>entrycode</i>
	integer*4 <i>bufsize</i>

The equivalent *FORTRAN* code for the example above is:

```
parameter (HDFE_NENTMAP=1)  
nmaps = swnentries(swathid, HDFE_NENTMAP, bufsize)
```

Open HDF-EOS File

SWopen

int32 SWopen(char *filename, intn access)

filename	IN:	Complete path and filename for the file to be opened
access	IN:	DFACC_READ, DFACC_RDWR or DFACC_CREATE
Purpose		Opens or creates HDF file in order to create, read, or write a swath.
Return value		Returns the swath file id handle (fid) if successful or FAIL (-1) otherwise.
Description		This routine creates a new file or opens an existing one, depending on the access parameter.
		Access codes:
	DFACC_READ	Open for read only. If file does not exist, error
	DFACC_RDWR	Open for read/write. If file does not exist, create it
	DFACC_CREATE	If file exist, delete it, then open a new file for read/write
Example		In this example, we create a new swath file named, <i>SwathFile.hdf</i> . It returns the file handle, <i>fid</i> .

```
fid = SWopen("SwathFile.hdf", DFACC_CREATE);
```

FORTRAN integer*4 function swopen(filename, access)
 character*(*) filename
 integer access

The access codes should be defined as parameters:

```
parameter (DFACC_READ=1)  
parameter (DFACC_RDWR=3)  
parameter (DFACC_CREATE=4)
```

The equivalent *FORTRAN* code for the example above is:

```
fid = swopen("SwathFile.hdf", DFACC_CREATE)
```

Note to users of the SDP Toolkit: Please refer to the *Release 5B SDP Toolkit User Guide for the ECS Project (333-CD-510-001)*, Section 6.2.1.2, for information on how to obtain a file name (referred to as a “physical file handle”) from within a PGE. See also Section 9 of this document for code examples.

Return Information About a Defined Time Period

SWperiodinfo

```
intn SWperiodinfo(int32 swathID, int32 periodID, char * fieldname, int32  
*ntype, int32 *rank, int32 dims[], int32 *size)
```

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>periodID</i>	IN:	Period id returned by SWdeftimeperiod
<i>fieldname</i>	IN:	Field to subset
<i>ntype</i>	OUT:	Number type of field
<i>rank</i>	OUT:	Rank of field
<i>dims</i>	OUT:	Dimensions of subset period
<i>size</i>	OUT:	Size in bytes of subset period
Purpose	Retrieves information about the subsetted period.	
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise.	
Description	This routine returns information about a subsetted time period for a particular field. It is useful when allocating space for a data buffer for the subset. Because of differences in number type and geolocation mapping, a given time period will give different values for the dimensions and size for various fields.	
Example	In this example, we retrieve information about the time period defined in <i>SWdeftimeperiod</i> for the <i>Spectra</i> field. We use this to allocate space for data in the subsetted time period.	
<pre>/* Get size in bytes of time period for "Spectra" field*/ status = SWperiodinfo(SWid, periodID, "Spectra", &ntype, &rank, dims, &size); /* Allocate space */ datbuf = (float64 *) malloc(size);</pre>		
FORTTRAN	<pre>integer function swperinfo(<i>swathid</i>, <i>periodid</i>, <i>fieldname</i>, <i>ntype</i>, <i>rank</i>, <i>dims</i>, <i>size</i>) integer*4 <i>swathid</i> integer*4 <i>periodid</i></pre>	

character(*)	<i>fieldname</i>
integer*4	<i>ntype</i>
integer*4	<i>rank</i>
integer*4	<i>dims(*)</i>
integer*4	<i>size</i>

The equivalent *FORTRAN* code for the example above is:

```
status = swperinfo(swid, periodid, "Spectra", ntype, rank, dims, size)
```

Read Swath Attribute

SWreadattr

intn SWreadattr(int32 *swathID*, char **attrname*, VOIDP *datbuf*)

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>attrname</i>	IN: Attribute name
<i>datbuf</i>	OUT: Buffer allocated to hold attribute values
Purpose	Reads attribute from a swath.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or number type or incorrect attribute name.
Description	The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.
Example	In this example, we read a single precision (32 bit) floating point attribute with the name "ScalarFloat":

```
status = SWreadattr(swathID, "ScalarFloat", &f32);
```

FORTRAN integer function swrdattr(*swathid*,*attrname*,*datbuf*)
 integer*4 *swathid*
 character*(*) *attrname*
 <valid type> *datbuf*(*)

The equivalent *FORTRAN* code for the example above is:

```
parameter (DFNT_FLOAT32=5)  
status = swrdattr(swathid, "ScalarFloat", f32)
```

Read Data From a Swath Field

SWreadfield

```
intn SWreadfield(int32 swathID, char *fieldname, int32 start[], int32 stride[], int32  
  edge[], VOIDP buffer)
```

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>fieldname</i>	IN: Name of field to read
<i>start</i>	IN: Array specifying the starting location within each dimension
<i>stride</i>	IN: Array specifying the number of values to skip along each dimension
<i>edge</i>	IN: Array specifying the number of values to read along each dimension
<i>buffer</i>	OUT: Buffer to store the data read from the field
Purpose	Reads data from a swath field.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are improper swath id or unknown fieldname.
Description	The values within <i>start</i> , <i>stride</i> , and <i>edge</i> arrays refer to the swath field (input) dimensions. The output data in <i>buffer</i> is written to contiguously. The default values for <i>start</i> and <i>stride</i> are 0 and 1 respectively and are used if these parameters are set to <i>NULL</i> . The default values for <i>edge</i> are <i>(dim - start) / stride</i> where <i>dim</i> refers is the size of the dimension.
Example	In this example, we read data from the 10th track (0-based) of the <i>Longitude</i> field.

```
float32 track[1000];  
  
int32 start[2]={10,1}, edge[2]={1,1000};  
  
status = SWreadfield(swathID, "Longitude", start, NULL, edge,  
track);
```

```

FORTRAN    integer function
           swrdfld(swathid, fieldname, start, stride, edge,buffer)
           integer*4      swathid
           character*(* ) fieldname
           integer*4      start(*)
           integer*4      stride(*)
           integer*4      edge(*)
           <valid type>   buffer(*)

```

The *start*, *stride*, and *edge* arrays must be defined explicitly, with the *start* array being 0-based.

The equivalent *FORTRAN* code for the example above is:

```

real*4 track(1000)

integer*4 start(2), stride(2), edge(2)

start(1) = 0
start(2) = 10
stride(1) = 1
stride(2) = 1
edge(1) = 1000
edge(2) = 1

status = swrdfld(swathid, "Longitude", start, stride, edge,
                  track)

```

Define a Longitude-Latitude Box Region for a Swath

SWregionindex

```
int32 SWregionindex(int32 swathID, float64 cornerlon[], float64 cornerlat[],
                     int32 mode, char *geodim, int32 idxrange[])
```

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>cornerlon</i>	IN:	Longitude in decimal degrees of box corners
<i>cornerlat</i>	IN:	Latitude in decimal degrees of box corners
<i>mode</i>	IN:	Cross Track inclusion mode
<i>geodim</i>	OUT:	Geolocation track dimension
<i>idxrange</i>	OUT:	The indices of the region in the geolocation track dimension.
Purpose		Defines a longitude-latitude box region for a swath.
Return value		Returns the swath region ID if successful or FAIL (-1) otherwise.
Description		The difference between this routine and SWdefboxregion is the geolocation track dimension name and the range of that dimension are returned in addition to a regionID. Other than that difference they are the same function and this function is used just like SWdefboxregion. This routine defines a longitude-latitude box region for a swath. It returns a swath region ID which is used by the SWextractregion routine to read all the entries of a data field within the region. A cross track is within a region if 1) its midpoint is within the longitude-latitude "box" (HDFE_MIDPOINT), or 2) either of its endpoints is within the longitude-latitude "box" (HDFE_ENDPOINT), or 3) any point of the cross track is within the longitude-latitude "box" (HDFE_ANYPOINT), depending on the inclusion mode designated by the user. All elements within an included cross track are considered to be within the region even though a particular element of the cross track might be outside the region. The swath structure must have both <i>Longitude</i> and <i>Latitude</i> (or <i>Colatitude</i>) fields defined
Example		In this example, we define a region bounded by the 3 degrees longitude, 5 degrees latitude and 7 degrees longitude, 12 degrees latitude. We will consider a cross track to be within the region if its midpoint is within the region. cornerlon[0] = 3.; cornerlat[0] = 5.; cornerlon[1] = 7.;

```

cornerlat[1] = 12.;

regionID = SWregionindex(swathID, cornerlon, cornerlat,
                         HDFE_MIDPOINT, geodim, idxrange);

FORTRAN integer*4 function swregidx(swathid, cornerlon, cornerlat, mode, geodim,
                                    idxrange)
integer*4      swathid
real*8        cornerlon
real*8        cornerlat
integer*4      mode
character(*)   geodim
integer*4      idxrange

```

The equivalent *FORTRAN* code for the example above is:

```

parameter (HDFE_MIDPOINT=0)

cornerlon(1) = 3.
cornerlat(1) = 5.
cornerlon(2) = 7.
cornerlat(2) = 12.

regionid = swregidx(swathid, cornerlon, cornerlat,
                     HDFE_MIDPOINT, geodim, idxrange)

```

Return Information About a Defined Region

SWregioninfo

```
intn SWregioninfo(int32 swathID, int32 regionID, char * fieldname, int32  
*ntype, int32 *rank, int32 dims[], int32 *size)
```

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>regionID</i>	IN:	Region id returned by SWdefboxregion
<i>fieldname</i>	IN:	Field to subset
<i>ntype</i>	OUT:	Number type of field
<i>rank</i>	OUT:	Rank of field
<i>dims</i>	OUT:	Dimensions of subset region
<i>size</i>	OUT:	Size in bytes of subset region
Purpose	Retrieves information about the subsetted region.	
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise.	
Description	This routine returns information about a subsetted region for a particular field. It is useful when allocating space for a data buffer for the region. Because of differences in number type and geolocation mapping, a given region will give different values for the dimensions and size for various fields.	
Example	In this example, we retrieve information about the region defined in <i>SWdefboxregion</i> for the <i>Spectra</i> field. We use this to allocate space for data in the subsetted region.	

```
/* Get size in bytes of region for "Spectra" field*/  
  
status = SWregioninfo(SWid, regionID, "Spectra", &ntype, &rank,  
dims, &size);  
  
/* Allocate space */  
  
datbuf = (float64 *) malloc(size);
```

FORTRAN	integer function swreginfo(<i>swathid, regionid, fieldname, ntype, rank, dims, size</i>)
	integer*4 <i>swathid</i>
	integer*4 <i>regionid</i>
	character*(*) <i>fieldname</i>
	integer*4 <i>ntype</i>
	integer*4 <i>rank</i>
	integer*4 <i>dims(*)</i>
	integer*4 <i>size</i>

The equivalent *FORTRAN* code for the example above is:

```
status = swreginfo(swid, regionid, "Spectra", ntype, rank,  
                  dims, size)
```

Set Fill Value for a Specified Field

SWsetfillvalue

intn SWsetfillvalue(int32 *swathID*, char **fieldname*, VOIDP *fillvalue*)

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>fieldname</i>	IN: Fieldname
<i>fillvalue</i>	IN: Pointer to the fill value to be used
Purpose	Sets fill value for the specified field.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or number type.
Description	The fill value is placed in all elements of the field which have not been explicitly defined. The field must have 2 or more dimensions.
Example	In this example, we set a fill value for the "Temperature" field:

```
tempfill = -999.0;  
  
status = SWsetfillvalue(swathID, "Temperature", &tempfill);
```

FORTRAN integer function

```
swsetfill(swathid,fieldname,fillvalue)  
integer*4      swathid  
character(*)   fieldname  
<valid type>  fillvalue(*)
```

The equivalent *FORTRAN* code for the example above is:

```
tempfill = -999.0;  
  
status = swsetfill(swathid, "Temperature", -999.0)
```

Update map index for a specified region

SWupdateidxmap

```
int32 SWupdateidxmap(int32 swathID, int32 regionID, int32 indexin[], int32  
                  indexout[], int32 indices[z])
```

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach.
<i>regionID</i>	IN: Region id returned by Swdefboxregion.
<i>indexin</i>	IN: The array containing the indices of the data dimension to which each geolocation element corresponds.
<i>indexout</i>	OUT: The array containing the indices of the data dimension to which each geolocation corresponds in the subsetted region. The indexout set to NULL, will not be returned.
<i>indices</i>	OUT: The array containing the indices for start and stop of region.
Purpose	Retrieve indexed array of specified geolocation mapping for a specified region.
Return value	Returns size of updated indexed array if successful or FAIL (-1) otherwise. A typical reason for failure is the specified mapping does not exist.
Description	This routine retrieves the size of the indexed array and the array of indexed elements of the specified geolocation mapping for the specified region.
Example	In this example, we retrieve information about the indexed mapping between the “IdxGeo” and “IdxData” dimensions, defined by Swdefboxregion: <pre>/* Get size of index_region array */ idxsz = SWupdateidxmap(swathID, regionID, index, NULL, indices); /* Allocate memory for index_region */ index_region = (int32*)malloc(sizeof(int32) * idxsz); /* Get the array index_region */ idxsz = Swupdateidxmap(swathID, regionID, index, index_region, indices);</pre>
FORTRAN	integer*4 function swupimap(swathid, regionid, indexin, indexout) integer*4 swathid integer*4 regionid integer*4 indexin(*)

```
integer*4 indexout(*)
```

```
integer*4 indices(2)
```

The equivalent FORTRAN code for the example above is:

```
status = swupdateidxmap(swathid, regionid, index, index_region, indices)
```

Note: The indexed arrays should be 0-based.

Write/Update Swath Attribute

SWwriteattr

```
intn SWwriteattr(int32 swathID, char *attrname, int32 ntype, int32 count, VOIDP  
                  datbuf)
```

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>attrname</i>	IN: Attribute name
<i>ntype</i>	IN: Number type of attribute
<i>count</i>	IN: Number of values to store in attribute
<i>datbuf</i>	IN: Attribute values
Purpose	Writes/Updates attribute in a swath.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or number type.
Description	If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call.
Example	In this example, we write a single precision (32 bit) floating point number with the name "ScalarFloat" and the value 3.14:

```
f32 = 3.14;  
  
status = SWwriteattr(swathid, "ScalarFloat", DFNT_FLOAT32,  
                  1, &f32);
```

We can update this value by simply calling the routine again with the new value:

```
f32 = 3.14159;  
  
status = SWwriteattr(swathid, "ScalarFloat", DFNT_FLOAT32,  
                  1, &f32);
```

```
FORTRAN    integer function swwrattr(swathid, attrname, ntype, count, datbuf)  
              integer*4      swathid  
              character*(*)  attrname  
              integer*4      ntype  
              integer*4      count  
              <valid type>   datbuf(*)
```

The equivalent *FORTRAN* code for the first example above is:

```
parameter (DFNT_FLOAT32=5)  
f32 = 3.14  
status = swwrattr(swathid, "ScalarFloat", DFNT_FLOAT32, 1, f32)
```

Write Field Metadata for an Existing Swath Data Field

SWwritedatameta

```
intn SWwritedatameta(int32 swathID, char *fieldname, char *dimlist, int32  
                  numbertype)
```

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>fieldname</i>	IN: Name of field
<i>dimlist</i>	IN: The list of data dimensions defining the field
<i>numbertype</i>	IN: The number type of the data stored in the field
Purpose	Writes field metadata for an existing swath data field.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is unknown dimension in the dimension list.
Description	This routine writes field metadata for an existing data field. This is useful when the data field was defined without using the swath API. Note that any entries in the dimension list must be defined through the <i>SWdefdim</i> routine before this routine is called.
Example	In this example we write the metadata for the “Band_1” data field used in the swath.

```
status = SWwritedatameta(swathID, "Band_1", "GeoTrack,  
                          GeoXtrack", DFNT_FLOAT32);
```

FORTRAN integer function

 swwrldmeta(*swathid*,*fieldname*,*dimlist*,*numbertype*)
 integer*4 *swathid*
 character*(*) *fieldname*
 character*(*) *dimlist*
 integer*4 *numbertype*

The equivalent *FORTRAN* code for the example above is:

```
status = swwrldmeta(swathID, "Band_1", "GeoXtrack, GeoTrack",  
                          DFNT_FLOAT32)
```

The dimensions are entered in *FORTRAN* order with the first dimension being incremented first.

Write Data to a Swath Field

SWwritefield

```
intn SWwritefield(int32 swathID, char *fieldname, int32 start[], int32 stride[], int32 edge[], VOIDP data)
```

<i>swathID</i>	IN: Swath id returned by SWcreate or SWattach
<i>fieldname</i>	IN: Name of field to write
<i>start</i>	IN: Array specifying the starting location within each dimension (0-based)
<i>stride</i>	IN: Array specifying the number of values to skip along each dimension
<i>edge</i>	IN: Array specifying the number of values to write along each dimension
<i>data</i>	IN: Values to be written to the field
Purpose	Writes data to a swath field.
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reasons for failure are an improper swath id or unknown fieldname.
Description	The values within <i>start</i> , <i>stride</i> , and <i>edge</i> arrays refer to the swath field (output) dimensions. The input data in the <i>data</i> buffer is read from contiguously. The default values for <i>start</i> and <i>stride</i> are 0 and 1 respectively and are used if these parameters are set to <i>NULL</i> . The default values for <i>edge</i> are <i>(dim - start) / stride</i> where <i>dim</i> refers is the size of the dimension. It is the users responsibility to make sure the data buffer contains sufficient entries to write to the field. Note that the data buffer for a compressed field must be the size of the entire field as incremental writes are not supported by the underlying HDF routines.
Example	In this example, we write data to the <i>Longitude</i> field. <pre>float32 longitude [2000][1000]; /* Define elements of longitude array */ status = SWwritefield(swathID, "Longitude", NULL, NULL, NULL, longitude);</pre>

We now update Track 10 (0 - based) in this field:

```
float32 newtrack[1000];

int32 start[2]={10,0}, edge[2]={1,1000};

/* Define elements of newtrack array */

status = SWwritefield(swathID, "Longitude", start, NULL, edge,
newtrack);

FORTRAN    integer function

swwrflld(swathid,fieldname,start,stride,edge,data)
integer*4      swathid
character*(*)  fieldname
integer*4      start(*)
integer*4      stride(*)
integer*4      edge(*)
<valid type>   data(*)
```

The *start*, *stride*, and *edge* arrays must be defined explicitly, with the *start* array being 0-based.

The equivalent *FORTRAN* code for the example above is:

```
real*4 longitude(1000,2000)

integer*4 start(2), stride(2), edge(2)

start(1) = 0
start(2) = 10
stride(1) = 1
stride(2) = 1
edge(1) = 1000
edge(2) = 2000

status = swwrflld(swathid, "Longitude", start, stride, edge,
longitude)
```

We now update Track 10 (0 - based) in this field:

```
real*4 newtrack(1000)

integer*4 start(2), stride(2), edge(2)
```

```
start(1) = 10
start(2) = 0
stride(1) = 1
stride(2) = 1
edge(1) = 1000
edge(2) = 1
status = swwrflld(swathid, "Longitude", start, stride, edge,
newtrack)
```

Write Field Metadata to an Existing Swath Geolocation Field

SWwritegeometa

```
intn SWwritegeometa(int32 swathID, char *fieldname, char *dimlist, int32  
                    numbertype)
```

<i>swathID</i>	IN:	Swath id returned by SWcreate or SWattach
<i>fieldname</i>	IN:	Name of field
<i>dimlist</i>	IN:	The list of geolocation dimensions defining the field
<i>numbertype</i>	IN:	The number type of the data stored in the field
Purpose		Writes field metadata for an existing swath geolocation field.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise. Typical reason for failure is unknown dimension in the dimension list.
Description		This routine writes field metadata for an existing geolocation field. This is useful when the data field was defined without using the swath API. Note that any entries in the dimension list must be defined through the <i>SWdefdim</i> routine before this routine is called.
Example		In this example we write the metadata for the “Latitude” geolocation field used in the swath.

```
status = SWwritegeometa(swathID, "Latitude",  
                      "GeoTrack,GeoXtrack",DFNT_FLOAT32);
```

FORTRAN integer function

 swwrgmeta(*swathid*,*fieldname*,*dimlist*,*numbertype*)

 integer*4 *swathid*
 character*(*) *fieldname*
 character*(*) *dimlist*
 integer*4 *numbertype*

The equivalent *FORTRAN* code for the example above is:

```
status = swwrgmeta(swathID, "Latitude",  
                  "GeoXtrack,GeoTrack",DFNT_FLOAT32)
```

The dimensions are entered in *FORTRAN* order with the first dimension being incremented first.

2.1.3 Grid Interface Functions

This section contains an alphabetical listing of all the functions in the Grid interface. The functions are alphabetized based on their C-language names.

Attach to an Existing Grid Structure

GDattach

int32 GDattach(int32 *fid*, char **gridname*)

<i>fid</i>	IN: Grid file id returned by GDopen
<i>gridname</i>	IN: Name of grid to be attached
Purpose	Attaches to an existing grid within the file.
Return value	Returns the grid handle(<i>gridID</i>) if successful or FAIL(-1) otherwise. Typical reasons for failure are improper grid file id or grid name.
Description	This routine attaches to the grid using the <i>gridname</i> parameter as the identifier.
Example	In this example, we attach to the previously created grid, " <i>ExampleGrid</i> ", within the HDF file, <i>GridFile.hdf</i> , referred to by the handle, <i>fid</i> :

```
gridID = GDattach(fid, "ExampleGrid");
```

The grid can then be referenced by subsequent routines using the handle, *gridID*.

FORTRAN

```
integer*4 function gdattach(fid, gridname)
    integer*4      fid
    character(*)   gridname
```

The equivalent *FORTRAN* code for the example above is:

```
gridid = gdattach(fid, "ExampleGrid")
```

Return Information About a Grid Attribute

GDattrinfo

intn GDattrinfo(int32 *gridID*, char **attrname*, int32 **numbertype*, int32 **count*)

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>attrname</i>	IN:	Attribute name
<i>numbertype</i>	OUT:	Number type of attribute
<i>count</i>	OUT:	Number of total bytes in attribute
Purpose		Returns information about a grid attribute
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine returns number type and number of elements (count) of a grid attribute.
Example		In this example, we return information about the <i>ScalarFloat</i> attribute.

```
status = GDattrinfo(pointID, "ScalarFloat",&nt,&count);
```

The *nt* variable will have the value 5 and *count* will have the value 4.

FORTRAN

```
integer function gdattrinfo(gridid, attrname, ntype, count)
integer*4      gridid
character(*)   attrname
integer*4      ntype
integer*4      count
```

The equivalent *FORTRAN* code for the first example above is:

```
status = gdattrinfo(pointid, "ScalarFloat",nt,count)
```

Write Block SOM Offset

GDblkSOMOffset

intn GDblkSOMOffset(int32 *gridID*, int32 *offset*[*count*], int32 *count*, char **code*)

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>offset</i>	IN:	Offset values for SOM Projection data
<i>count</i>	IN:	Number of offset values to write
<i>code</i>	IN:	Write/Read code
Purpose		Write block SOM offset values.
Return value		Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description		The routine supports structures that contain data which has been written in the Solar Oblique Mercator (SOM) projection. The structure can contain one to many blocks, each with corner points defined by latitude and longitude. The routine can only be used by grids that use the SOM projection. The routine writes the offset values, in pixels, from a standard SOM projection. There is an offset value for every block in the grid except for the first block. The count parameter is used as a check for the number of offset values. This routine will also return the offset values, but the user must know how large the offset array needs to be before calling the function, in that case the code value would be "r" and the count parameter has to be provided also.
Example		In this example, we first show how the SOM projection is defined using GDdefproj, then we show how the SOM projection is modified using GDblkSOMOffset: The first parameter is the Grid id, the second is the projection code for the SOM projection, the third is the zone code, not needed for the SOM projection, the fourth is the sphere code, not needed for the SOM projection and the last parameter is the projection parameter array. Each projection supported by the Grid interface has a unique set of variables that are used by the GCTP library and they are passed to the GCTP library through this array. As you can see below, the twelfth parameter is set to a non-zero value, it is set to the size of the number of blocks in the data field. This is required if the function GDblkSOMOffset is going to be called. The GCTP library doesn't use this parameter for the SOM projection so that is used by the HDF-EOS library only. The GDblkSOMOffset function checks that parameter first before anything else is done. projparm[0] = 6378137.0;

```
projparm[1] = 0.006694348;  
projparm[3] = EHconvAng(98.161, HDFE_DEG_DMS);  
projparm[4] = EHconvAng(87.11516945924, HDFE_DEG_DMS);  
projparm[8] = 0.068585416 * 1440;  
projparm[9] = 0.0;  
projparm[11] = 6;  
  
status = GDdefproj(GDid_som, GCTP_SOM, NULL, NULL, projparm);  
  
Now that the projection has been defined, GDbblkSOMoffset can be called:  
  
offset[5] = {5, 10, 12, 8, 2};  
  
count = 5;  
  
code = "w";  
  
status = GDbblkSOMoffset(gridID, offset, count, code);
```

This set the offset for the second block to 5 pixels, the third block to 10 pixels, fourth block to 12 pixels, fifth to 8 pixels and the sixth block to 2 pixels.

- NOTE: This routine is currently implemented in “C” only. If the need arises, a FORTRAN function will be added.
- Interblock subsetting is not currently supported by the ECS Science Data Server, at this time. That is, a response to a request to return data contained within a specified latitude/longitude box, will be in an integral number of blocks.

Related Documents

- An Album of Map Projections, USGS Professional Paper 1453, Snyder and Voxland, 1989
Map Projections - A Working Manual, USGS Professional Paper 1395, Snyder, 1987

Close an HDF-EOS File

GDclose

intn GDclose(int32 *fid*)

fid IN: Grid file id returned by GDopen

Purpose Closes file.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise.

Description This routine closes the HDF grid file.

Example

```
status = GDclose(fid);
```

FORTRAN integer function gdclose(int32 *fid*)
integer*4 *fid*

The equivalent *FORTRAN* code for the example above is:

```
status = gdclose(fid)
```

Retrive Compression Information for Field

GDcompinfo

intn GDcompinfo(int32 *gridID*, char **fieldname*, int32 **compcode*, intn *compparm*[])

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN: Fieldname
<i>compcode</i>	OUT: HDF compression code
<i>compparm</i>	OUT: Compression parameters
Purpose	Retrieves compression information about a field.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description	This routine returns the compression code and compression parameters for a given field.
Example	To retreive the compression information about the <i>Opacity</i> field defined in the <i>GDdefcomp</i> section:

```
status = GDcompinfo(gridID, "Opacity", compcode, compparm);
```

The *compcode* parameter will be set to 4 and *compparm*[0] to 5.

FORTRAN

```
integer function gdcompinfo(gridid,fieldname compcode, compparm)
integer*4      gridid
character*(*)  fieldname
integer*4      compcode
integer        compparm
```

The equivalent *FORTRAN* code for the example above is:

```
status = gdcompinfo(gridid, 'Opacity', compcode, compparm)
```

The *compcode* parameter will be set to 4 and *compparm*(1) to 5.

Create a New Grid Structure

GDcreate

```
int32 GDcreate(int32 fid, char *gridname, int32 xysize, int32 yysize, float64  
          upleftpt[], float64 lowrightpt[])
```

<i>fid</i>	IN: Grid file id returned by GDopen
<i>gridname</i>	IN: Name of grid to be created
<i>xysize</i>	IN: Number of columns in grid
<i>yysize</i>	IN: Number of rows in grid
<i>upleftpt</i>	IN: Location, of upper left corner of the upper left pixel
<i>lowrightpt</i>	IN: Location, of lower right corner of the lower right pixel
Purpose	Creates a grid within the file.
Return value	Returns the grid handle(<i>gridID</i>) or FAIL(-1) otherwise.
Description	The grid is created as a Vgroup within the HDF file with the name <i>gridname</i> and class <i>GRID</i> . This routine establishes the resolution of the grid, ie, the number of rows and columns, and it's location within the complete global projection through the <i>upleftpt</i> and <i>lowrightpt</i> arrays. These arrays should be in meters for all GCTP projections other than the Geographic Projection and EASE grid, which should be in packed degree format. q.v. below.
Example	In this example, we create a UTM grid bounded by 54 E to 60 E longitude and 20 N to 30 N latitude. We divide it into 120 bins along the x-axis and 200 bins along the y-axis

```
uplft[0]=210584.50041;  
uplft[1]=3322395.95445;  
  
lowrgt[0]=813931.10959;  
lowrgt[1]=2214162.53278;  
  
xdim=120;  
ydim=200;  
  
gridID = GDcreate(fid, "UTMGrid", xdim, ydim, uplft, lowrgt);
```

The grid structure is then referenced by subsequent routines using the handle, *gridID*.

The *xdim* and *ydim* values are referenced in the field definition routines by the reserved dimensions: *XDim* and *YDim*.

For the Polar Stereographic, Goode Homolosine and Lambert Azimuthal projections, we have established default values in the case of an entire hemisphere for the first projection, the entire globe for the second and the entire polar or equitorial projection for the third. Thus, if we have a Polar Stereographic projection of the Northern Hemisphere then the *uplft* and *lowrgt* arrays can be replaced by *NULL* in the function call.

In the case of the Geographic projection (linear scale in both longitude latitude), and EASE grid (i.e., BCEA projection) the *upleftpt* and *lowrightpt* arrays contain the longitude and latitude of these points in packed degree format (DDDDMMMSSS.SS).

Note:

upleftpt - Array that contains the X-Y coordinates of the upper left corner of the upper left pixel of the grid. First and second elements of the array contain the X and Y coordinates respectively. The upper left X coordinate value should be the lowest X value of the grid. The upper left Y coordinate value should be the highest Y value of the grid.

lowrightpt - Array that contains the X-Y coordinates of the lower right corner of the lower right pixel of the grid. First and second elements of the array contain the X and Y coordinates respectively. The lower right X coordinate value should be the highest X value of the grid. The lower right Y coordinate value should be the lowest Y value of the grid.

If the projection id geographic (i.e., projcode=0) or Behrmann Cylindrical equal Area (i.e., projcode = GCTP_BCEA = 98) then the X-Y coordinates should be specified in degrees/minutes/seconds (DDDDMMMSSS.SS) format. The first element of the array holds the longitude and the second element holds the latitude. For geographic latitudes are from -90 to +90 and longitudes are from -180 to +180 (west is negative). For EASE grid latitudes are from -86.72 to +86.72 and longitudes are from -180 to +180.

For all other projection types the X-Y coordinates should be in **meters** in double precision. These coordinates have to be computed using the GCTP software with the same projection parameters that have been specified in the projparm array. For UTM projections use the same zone code and its sign (positive or negative) while computing both upper left and lower right corner X-Y coordinates irrespective of the hemisphere.

To convert lat/long to x-y coordinates, it is also possible to use SDP Toolkit routines: PGS_GCT_Init() or PGS_GCT_Proj(). More information is contained in the *SDP Toolkit Users Guide for the ECS Project*

```
FORTRAN    integer*4 function gdcreate(fid, gridname, xdimsize, ydimsize, upleftpt,  
           lowrightpt)  
           integer*4      fid  
           character(*)   gridname  
           integer*4      xdimsize  
           interger*4     ydimsize  
           real*8        upleftpt  
           real*8        lowrightpt
```

The equivalent *FORTRAN* code for the example above is:

```
gridid = gdcreate(fid, "UTMGrid", xdim, ydim, uplft,  
                  lowrgt)
```

The default values for the Polar Stereographic and Goode Homolosine can be designated by setting all elements in the *uplft* and *lowrgt* arrays to 0.

Define Region of Interest by Latitude/Longitude

GDdefboxregion

int32 GDdefboxregion(int32 *gridID*, float64 *cornerlon[]*, float64 *cornerlat[]*)

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>cornerlon</i>	IN: Longitude in decimal degrees of box corners
<i>cornerlat</i>	IN: Latitude in decimal degrees of box corners
Purpose	Defines a longitude-latitude box region for a grid.
Return value	Returns the grid region ID if successful or FAIL (-1) otherwise.
Description	This routine defines a longitude-latitude box region for a grid. It returns a grid region ID which is used by the <i>GExtractregion</i> routine to read all the entries of a data field within the region.
Example	In this example, we define the region to be the first quadrant of the Northern hemisphere.

```
cornerlon[0] = 0.;  
cornerlat[0] = 90.;  
cornerlon[1] = 90.;  
cornerlat[1] = 0.;  
  
regionID = GDdefboxregion(GDid, cornerlon, cornerlat);
```

FORTRAN integer*4 function gddefboxreg(*gridid*, *cornerlon*, *cornerlat*)
 integer*4 *gridid*
 real*8 *cornerlon*
 real*8 *cornerlat*

The equivalent *FORTRAN* code for the example above is:

```
cornerlon(1) = 0.  
cornerlat(1) = 90.  
cornerlon(2) = 90.  
cornerlat(2) = 0.  
  
regionid = gddefboxreg(gridid, cornerlon,cornerlat)
```

Set Grid Field Compression

GDdefcomp

intn GDdefcomp(int32 *gridID*, int32 *compparm*, intn *compparm*[])

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>compparm</i>	IN:	HDF compression code
<i>compparm</i>	IN:	Compression parameters (if applicable)
Purpose		Sets the field compression for all subsequent field definitions.
Return value		Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description		This routine sets the HDF field compression for subsequent grid field definitions. The compression does not apply to one-dimensional fields. The compression schemes currently supported are: run length encoding (HDFE_COMP_RLE = 1), skipping Huffman (HDFE_COMP_SKPHUFF = 3), deflate (gzip) (HDFE_COMP_DEFLATE=4) and no compression (HDFE_COMP_NONE = 0, the default). Deflate compression requires a single integer compression parameter in the range of one to nine with higher values corresponding to greater compression. Compressed fields are written using the standard <i>GDwritefield</i> routine, however, the entire field must be written in a single call. If this is not possible, the user should consider tiling. See <i>GDdefile</i> for further information. Any portion of a compressed field can then be accessed with the <i>GDreadfield</i> routine. Compression takes precedence over merging so that multi-dimensional fields that are compressed are not merged. The user should refer to the HDF Reference Manual for a fuller explanation of the compression schemes and parameters.
Example		Suppose we wish to compress the <i>Pressure</i> using run length encoding, the <i>Opacity</i> field using deflate compression, the <i>Spectra</i> field with skipping Huffman compression, and use no compression for the <i>Temperature</i> field.

```
status = GDdefcomp(gridID, HDFE_COMP_RLE, NULL);

status = GDdeffield(gridID, "Pressure", "YDim,XDim",
DFNT_FLOAT32, HDFE_NOMERGE);

compparm[0] = 5;

status = GDdefcomp(gridID, HDFE_COMP_DEFLATE, compparm);

status = GDdeffield(gridID, "Opacity", "YDim,XDim",
DFNT_FLOAT32, HDFE_NOMERGE);
```

```

status = GDdefcomp(gridID, HDFE_COMP_SKPHUFF, NULL);

status = GDdeffield(gridID, "Spectra", "Bands,YDim,XDim",
DFNT_FLOAT32, HDFE_NOMERGE);

status = GDdefcomp(gridID, HDFE_COMP_NONE, NULL);

status = GDdeffield(gridID, "Temperature", "YDim,XDim",
DFNT_FLOAT32, HDFE_AUTOMERGE);

```

Note that the HDFE_AUTOMERGE parameter will be ignored in the *Temperature* field definition.

FORTRAN	integer function gddefcomp(<i>gridid</i> , <i>compcode</i> , <i>compparm</i>)
	integer*4 <i>gridid</i>
	integer <i>compcode</i>
	integer <i>compparm</i>

The equivalent *FORTRAN* code for the example above is:

```

parameter (HDFE_COMP_NONE=0)
parameter (HDFE_COMP_RLE=1)
parameter (HDFE_COMP_SKPHUFF=3)
parameter (HDFE_COMP_DEFLATE=4)
integer     compparm(5)
status = gddefcomp(gridid, HDFE_COMP_RLE, compparm)
status = gddeffld(gridid, "Pressure", "YDim,XDim",
DFNT_FLOAT32, HDFE_NOMERGE)
compparm(1) = 5
status = gddefcomp(gridid, HDFE_COMP_DEFLATE, compparm)
status = gddeffld(gridid, "Opacity", "YDim,XDim", DFNT_FLOAT32,
HDFE_NOMERGE)
status = gddefcomp(gridid, HDFE_COMP_SKPHUFF, compparm)
status = gddeffld(gridid, "Spectra", "Bands,YDim,XDim",
DFNT_FLOAT32, HDFE_NOMERGE)
status = gddefcomp(gridid, HDFE_COMP_NONE, compparm)
status = gddeffld(gridid, "Temperature", "YDim,XDim",
DFNT_FLOAT32, HDFE_AUTOMERGE)

```

Define a New Dimension Within a Grid

GDdefdim

intn GDdefdim(int32 *gridID*, char **dimname*, int32 *dim*)

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>dimname</i>	IN: Name of dimension to be defined
<i>dim</i>	IN: The size of the dimension
Purpose	Defines a new dimension within the grid.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reason for failure is an improper grid id.
Description	This routine defines dimensions that are used by the field definition routines (described subsequently) to establish the size of the field.
Example	In this example, we define a dimension, <i>Band</i> , with size 15.

```
status = GDdefdim(gridID, "Band", 15)
```

To specify an unlimited dimension which can be used to define an appendable array, the dimension value should be set to zero or equivalently, *SD_UNLIMITED*:

```
status = GDdefdim(gridID, "Unlim", SD_UNLIMITED);
```

FORTRAN

```
integer function gddefdim(gridid, fieldname, dim)
integer*4      gridid
character(*)   fieldname
integer*4      dim
```

The equivalent *FORTRAN* code for the example above is:

```
parameter (SD_UNLIMITED=0)
status = gddefdim(gridid, "Band", 15)
status = gddefdim(gridid, "Unlim", SD_UNLIMITED)
```

Define a New Data Field Within a Grid

GDdeffield

intn GDdeffield(int32 *gridID*, char **fieldname*, char **dimlist*, int32 *numbertype*, int32 *merge*)

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN: Name of field to be defined
<i>dimlist</i>	IN: The list of data dimensions defining the field
<i>numbertype</i>	IN: The number type of the data stored in the field
<i>merge</i>	IN: Merge code (HDFE-NOMERGE (0) - no merge, HDFE_AUTOMERGE (1) -merge)
Purpose	Defines a new data field within the grid.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reason for failure is an unknown dimension in the dimension list.
Description	This routine defines data fields to be stored in the grid. The dimensions are entered as a string consisting of geolocation dimensions separated by commas. They are entered in C order, that is, the last dimension is incremented first. The API will attempt to merge into a single object those fields that share dimensions and in case of multidimensional fields, <i>numbertype</i> . Two and three dimensional fields will be merged into a single three-dimensional object if the last two dimensions (in C order) are equal). If the merge code for a field is set to 0, the API will not attempt to merge it with other fields. Fields using the unlimited dimension will not be merged. Because merging breaks the one-to-one correspondence between HDF-EOS fields and HDF SDS arrays, it should not be set if the user wishes to access the HDF-EOS field directly using HDF routines or, for example, to create an HDF attribute corresponding to the field.
Example	In this example, we define a grid field, <i>Temperature</i> with dimensions <i>XDim</i> and <i>YDim</i> (as established by the <i>GDcreate</i> routine) containing 4-byte floating point numbers and a field, <i>Spectra</i> , with dimensions <i>XDim</i> , <i>YDim</i> , and <i>Bands</i> :
FORTRAN	<pre>status = GDdeffield(gridID, "Temperature", "YDim,XDim", DFNT_FLOAT32, HDFE_AUTOMERGE); status = GDdeffield(gridID, "Spectra", "Bands,YDim,XDim", DFNT_FLOAT32, HDFE_NOMERGE);</pre> <p>integer function gddeffld(<i>gridid</i>, <i>fieldname</i>, <i>dimlist</i>, <i>numbertype</i>, <i>merge</i>)</p>

```
integer*4      gridid  
character(*)   fieldname  
character(*)   dimlist  
integer*4      numbertype  
integer*4      merge
```

The equivalent *FORTRAN* code for the example above is:

```
parameter (DFNT_FLOAT32=5)  
parameter (HDFE_NOMERGE=0)  
parameter (HDFE_AUTOMERGE=1)  
  
status = gddeffld(gridid, "Temperature", "XDim,YDim",  
DFNT_FLOAT32, DFE_AUTOMERGE)  
  
status = gddeffld(gridid, "Spectra", "XDim,YDim,Bands",  
DFNT_FLOAT32, HDFE_NOMERGE)
```

The dimensions are entered in *FORTRAN* order with the first dimension incremented first.

Define the Origin of the Grid Data

GDdeforigin

intn GDdeforigin(int32 *gridID*, int32 *origincode*)

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>origincode</i>	IN:	Location of the origin of the grid data
Purpose	Defines the origin of the grid data	
Return Value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise	
Description	The routine is used to define the origin of the grid data. This allows the user to select any corner of the grid as the origin.	

Origin Codes:

HDFE_GD_UL(Default)(0)	Upper Left corner of grid
HDFE_GD_UR(1)	Upper Right corner of grid
HDFE_GD_LL(2)	Lower Left corner of grid
HDFE_GD_LR(3)	Lower Right corner of grid

Example In this example we define the origin of the grid to be the Lower Right corner:

```
status = GDdeforigin(gridID, HDFE_GD_LR);
```

FORTRAN integer function gddeforg(*gridid*, *origincode*)
 integer*4 *gridid*
 integer*4 *origincode*

The equivalent *FORTRAN* code for the above example is :

```
parameter (HDFE_GD_LR=3)  
status = gddeforg(gridid, HDFE_GD_LR)
```

Define a Pixel Registration Within a Grid

GDdefpixreg

intn GDdefpixreg(int32 *gridID*, int32 *pixreg*)

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>pixreg</i>	IN: Pixel registration
Purpose	Defines pixel registration within grid cell
Return Value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description	This routine is used to define whether the pixel center or pixel corner (as defined by the <i>GDdeforigin</i> routine) is used when requesting the location (longitude and latitude) of a given pixel.

Registration Codes:

HDFE_CENTER (0) (Default) Center of pixel cell

HDFE_CORNER (1) Corner of a pixel cell

Example	In this example, we define the pixel registration to be the corner of the pixel cell:
---------	---

```
status = GDdefpixreg(gridID, HDFE_CORNER);
```

FORTRAN	integer function gddefpixreg(<i>gridid</i> , <i>pixreg</i>) integer*4 <i>gridid</i> integer*4 <i>pixreg</i>
---------	---

The equivalent *FORTRAN* code for the example above is:

```
parameter (HDFE_CORNER=1)  
  
status = gddefpixreg(gridid, HDFE_CORNER)
```

Define Grid Projection

GDdefproj

```
intn GDdefproj(int32 gridID, int32 projcode, int32 zonecode, int32 spherecode, float64 projparm[])
```

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>projcode</i>	IN: GCTP projection code
<i>zonecode</i>	IN: GCTP zone code used by UTM projection
<i>spherecode</i>	IN: GCTP spheroid code
<i>projparm</i>	IN: GCTP projection parameter array
Purpose	Defines projection of grid
Return Value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise
Description	Defines the GCTP projection and projection parameters of the grid.
Example	In this example, we define a Universal Transverse Mercator (UTM) grid bounded by 54 E - 60 E longitude and 20 N - 30 N latitude – UTM zonecode 40, using default spheroid (Clarke 1866), spherecode = 0

```
spherecode = 0;  
zonecode = 40;  
  
status = GDdefproj(gridID, GCTP_UTM, zonecode, spherecode,  
NULL);
```

In this next example we define a Polar Stereographic projection of the Northern Hemisphere (True scale at 90 N, 0 Longitude below pole) using the International 1967 spheroid.

```
spherecode = 3;  
  
for (i = 0; i < 13; i++) projparm[i] = 0;  
/* Set Long below pole & true scale in DDDMMSSS.SSS form */  
projparm[5] = 90000000.00;  
  
status = GDdefproj(gridID, GCTP_PS, NULL, spherecode,  
projparm);
```

Finally we define a Geographic projection. In this case neither the zone code, sphere code or the projection parameters are used.

	status = GDdefproj(gridID, GCTP_GEO, NULL, NULL, NULL)
FORTRAN	integer function gddefproj(gridid, projcode, zonecode, spherecode, projparm)
	integer*4 <i>gridid</i>
	integer*4 <i>projcode</i>
	integer*4 <i>zonecode</i>
	integer*4 <i>spherecode</i>
	real*8 <i>projparm(*)</i>

The equivalent FORTRAN code for the examples above is:

```

parameter (GCTP_UTM=1)

spherecode = 0

zonecode = 40

status = gddefproj(gridid, GCTP_UTM, zonecode, spherecode,
                    dummy)

parameter (GCTP_PS=6)

spherecode = 6

do i=1,13

    projparm(i) = 0

enddo

projparm(6) = 90000000.00

status = gddefproj(gridid, GCTP_PS, dummy, spherecode,
                    projparm)

parameter (GCTP_GEO=0)

status = gddefproj(gridid, GCTP_GEO, dummy, dummy, dummy)

```

Note: projcode, zonecode, spherecode and projection parameter information are listed in Section 1.6, GCTP Usage.

Define Tiling Parameters

GDdeftile

intn GDdeftile(int32 *gridID*, int32 *tilecode*, int32 *tilerank*, int32 *tiledims*[])

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>tilecode</i>	IN:	Tile code: HDF_TILE, HDF_NOTILE (default)
<i>tilerank</i>	IN:	The number of tile dimensions
<i>tiledims</i>	IN:	Tile dimensions
Purpose		Defines tiling dimensions for subsequent field definitions
Return Value		Returns SUCCEED(0) if successful or FAIL(-1) otherwise
Description		This routine defines the tiling dimensions for fields defined following this function call, analogous to the procedure for setting the field compression scheme using <i>GDdefcomp</i> . The number of tile dimensions and subsequent field dimensions must be the same and the tile dimensions must be integral divisors of the corresponding field dimensions. A tile dimension set to 0 will be equivalent to 1.
Example		We will define four fields in a grid, two two-dimensional fields of the same size with the same tiling, a three-dimensional field with a different tiling scheme, and a fourth with no tiling. We assume that <i>XDim</i> is 200 and <i>YDim</i> is 300.
		<pre>tiledims[0] = 100; tiledims[1] = 200; status = GDdeftile(gridID, HDFE_TILE, 2, tiledims); status = GDdeffield(gridID, "Pressure", "YDim,XDim", DFNT_INT16, HDFE_NOMERGE); status = GDdeffield(gridID, "Temperature", "YDim,XDim", DFNT_FLOAT32, HDFE_NOMERGE); tiledims[0] = 1; tiledims[1] = 150; tiledims[2] = 100; status = GDdeftile(gridID, HDFE_TILE, 3, tiledims);</pre>

```

status = GDdeffield(gridID, "Spectra", "Bands,YDim,XDim",
DFNT_FLOAT32, HDFE_NOMERGE);

status = GDdeftile(gridID, HDFE_NOTILE, 0, NULL);

status = GDdeffield(gridID, "Communities", "YDim,XDim",
DFNT_INT32, HDFE_AUTOMERGE);

```

FORTRAN

```

integer function gddeftle(gridid, tilecode,tilerank,tiledims)
integer*4      gridid
integer*4      tilecode
integer*4      tilerank
integer*4      tiledims(*)

```

The equivalent *FORTRAN* code for the example above is:

```

parameter (HDFE_NOTILE=0)
parameter (HDFE_TILE=1)
tiledims(1) = 200
tiledims(2) = 100
status = gddeftle(gridid, HDFE_TILE, 2, tiledims)
status = gddeffld(gridid, 'Pressure', 'XDim,YDim', DFNT_INT16,
HDFE_NOMERGE)
status = gddeffld(gridid, 'Temperature', 'XDim,YDim',
DFNT_FLOAT32, HDFE_NOMERGE)
tiledims[1] = 100
tiledims[2] = 150
tiledims[3] = 1
status = gddeftle(gridid, HDFE_TILE, 3, tiledims)
status = gddeffld(gridid, 'Spectra', 'XDim,YDim,Bands',
DFNT_FLOAT32, HDFE_NOMERGE)
status = gddeftile(gridid, HDFE_NOTILE, 0, tiledims);
status = gddeffld(gridid, 'Communities', 'XDim,YDim',
DFNT_INT32, HDFE_AUTOMERGE)

```

Define a Time Period of Interest

GDdeftimeperiod

```
int32 GDdeftimeperiod(int32 gridID, int32 periodID, float64 starttime, float64 stoptime)
```

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>periodID</i>	IN: Period (or region) id from previous subset call
<i>starttime</i>	IN: Start time of period
<i>stoptime</i>	IN: Stop time of period
Purpose	Defines a time period for a grid.
Return value	Returns the grid period ID if successful or FAIL (-1) otherwise.
Description	This routine defines a time period for a grid. It returns a grid period ID which is used by the <i>GDextractperiod</i> routine to read all the entries of a data field within the time period.. The grid structure must have the <i>Time</i> field defined. This routine may be called after <i>GDdefboxregion</i> to provide both geographic and time subsetting . In this case the user provides the id from the previous subset call. (This same id is then returned by the function.) Furthermore it can be called before or after <i>GDdefvrregion</i> to further refine a region. This routine may also be called “stand-alone” by setting the input id to HDFE_NOPREVSUB (-1).

Example In this example, we define a time period with a start time of 35232487.2 and a stop time of 36609898.1.

```
starttime = 35232487.2;  
stoptime = 36609898.1;  
  
periodID = GDdeftimeperiod(gridID, HDFE_NOPREVSUB  
starttime, stoptime);
```

If we had previously performed a geographic subset with id, *regionID*, then we could further time subset this region with the call:

```
periodID = GDdeftimeperiod(gridID, regionID, starttime,  
stoptime);
```

Note that *periodID* will have the same value as *regionID*.

```
FORTRAN    integer*4 function gddeftmeper(gridid, periodID, starttime, stoptime)
            integer*4      gridid
            integer*4      periodID
            real*8       starttime
            real*8       stoptime
```

The equivalent *FORTRAN* code for the examples above are:

```
parameter (HDFE_NOPREVSUB=-1)
starttime = 35232487.2
stoptime = 36609898.1
periodid = gddeftmeper(swathid, HDFE_NOPREVSUB, starttime,
                      stoptime)
periodid = gddeftmeper(swathid, regionid, starttime,
                      stoptime)
```

Define a Vertical Subset Region

GDdefvrtrregion

int32 GDdefvrtrregion(int32 *gridID*, int32 *regionID*, char **vertObj*, float64 *range*[])

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>regionID</i>	IN:	Region (or period) id from previous subset call
<i>vertObj</i>	IN:	Dimension or field to subset
<i>range</i>	IN:	Minimum and maximum range for subset
Purpose		Subsets on a monotonic field or contiguous elements of a dimension.
Return value		Returns the grid region ID if successful or FAIL (-1) otherwise.
Description		Whereas the <i>GDdefboxregion</i> routine subsets along the <i>XDim</i> and <i>YDim</i> dimensions, this routine allows the user to subset along any other dimension. The region is specified by a set of minimum and maximum values and can represent either a dimension index (case 1) or field value range(case 2) . In the second case, the field must be one-dimensional and the values must be monotonic (strictly increasing or decreasing) in order that the resulting dimension index range be contiguous. (For the current version of this routine, the second option is restricted to fields with number type: INT16, INT32, FLOAT32, FLOAT64.) This routine may be called after <i>GDdefboxregion</i> to provide both geographic and “vertical” subsetting . In this case the user provides the id from the previous subset call. (This same id is then returned by the function.) This routine may also be called “stand-alone” by setting the input id to HDFE_NOPREVSUB (-1). This routine may be called up to eight times with the same region ID. It this way a region can be subsetted along a number of dimensions.
		The <i>GDregioninfo</i> and <i>GDEXTRACTregion</i> routines work as before, however the field to be subsetted, (the field specified in the call to <i>GDregioninfo</i> and <i>GDEXTRACTregion</i>) must contain the dimension used explicitly in the call to <i>GDdefvrtrregion</i> (case 1) or the dimension of the one-dimensional field (case 2).
Example		Suppose we have a field called <i>Pressure</i> of dimension <i>Height</i> (= 10) whose values increase from 100 to1000. If we desire all the elements with values between 500 and 800, we make the call: <code>range[0] = 500.; range[1] = 800.;</code>

```
regionID = GDdefvrtrregion(gridID, HDFE_NOPREVSUB, "Pressure",
range);
```

The routine determines the elements in the *Height* dimension which correspond to the values of the *Pressure* field between 500 and 800.

If we wish to specify the subset as elements 2 through 5 (0 - based) of the *Height* dimension, the call would be:

```
range[0] = 2;
range[1] = 5;
regionID = GDdefvrtrregion(gridID, HDFE_NOPREVSUB, "DIM:Height",
range);
```

The “DIM:” prefix tells the routine that the range corresponds to elements of a dimension rather than values of a field.

If a previous subset region or period was defined with id, *subsetID*, that we wish to refine further with the vertical subsetting defined above we make the call:

```
regionID = GDdefvrtrregion(gridID, subsetID, "Pressure", range);
```

The return value, *regionID* is set equal to *subsetID*. That is, the subset region is modified rather than a new one created.

In this example, any field to be subsetted must contain the *Height* dimension.

FORTRAN

```
integer*4 function gddefvrtrreg(gridid, regionid, vertobj, range)
integer*4      gridid
integer*4      regionid
character(*)   vertobj
real*8        range
```

The equivalent *FORTRAN* code for the examples above is:

```
parameter (HDFE_NOPREVSUB=-1)
range(1) = 500.
range(2) = 800.
regionid = gddefvrtrreg(gridid, HDFE_NOPREVSUB, "Pressure",
range)
range(1) = 3 ! Note 1-based element numbers
range(2) = 6
regionid = gddefvrtrreg(gridid, HDFE_NOPREVSUB, "DIM:Height",
range)
regionid = gddefvrtrreg(gridid, subsetid, "Pressure", range)
```

Detach from Grid Structure

GDdetach

intn GDdetach(int32 *gridID*)

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
Purpose	Detaches from grid interface.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description	This routine should be run before exiting from the grid file for every grid opened by GDcreate or GDattach.
Example	In this example, we detach the grid structure, <i>ExampleGrid</i> :

```
status = GDdetach(gridID);  
FORTRAN integer function gddetach(gridid)  
integer*4      gridid
```

The equivalent *FORTRAN* code for the example above is:

```
status = gddetach(gridid)
```

Retrieve Size of Specified Dimension

GDdiminfo

int32 GDdiminfo(int32 *gridID*, char **dimname*)

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>dimname</i>	IN: Dimension name
Purpose	Retrieve size of specified dimension.
Return value	Size of dimension if successful or FAIL(-1) otherwise. A typical reason for failure is an improper grid id or dimension name.
Description	This routine retrieves the size of specified dimension.

Example In this example, we retrieve information about the dimension, "Bands":

```
dimsize = GDdiminfo(gridID, "Bands");
```

The return value, *dimsize*, will be equal to 15

FORTRAN integer*4 function gddiminfo(*gridid*,*dimname*)
integer*4 *gridid*
character(*) *dimname*

The equivalent *FORTRAN* code for the example above is:

```
dimsize = gddiminfo(gridid, "Bands")
```

Duplicate a Region or Period

GDdupregion

int32 GDdupregion(int32 *regionID*)

regionID IN: Region or period id returned by GDdefboxregion, GDdeftimeperiod, or GDdefvrtrregion.

Purpose Duplicates a region.

Return value Returns new region or period ID if successful or FAIL (-1) otherwise.

Description This routine copies the information stored in a current region or period to a new region or period and generates a new id. It is usefully when the user wishes to further subset a region (period) in multiple ways.

Example In this example, we first subset a grid with *GDdefboxregion*, duplicate the region creating a new region ID, *regionID2*, and then perform two different vertical subsets of these (identical) geographic subset regions:

```
regionID = GDdefboxregion(gridID, cornerlon, cornerlat);
regionID2 = GDdupregion(regionID);

regionID = GDdefvrtrregion(gridID, regionID, "Pressure",
rangePres);

regionID2 = GDdefvrtrregion(gridID, regionID2, "Temperature",
rangeTemp);
```

FORTRAN integer*4 function gddupreg(*regionid*)
integer*4 *regionid*

The equivalent *FORTRAN* code for the example above is:

```
regionid = gddefboxreg(gridid, cornerlon, cornerlat)
regionid2 = gddupreg(regionid)

regionid = gddefvrtrreg(gridid, regionid, 'Pressure',
rangePres)

regionid2 = gddefvrtrreg(gridid, regionid2, 'Temperature',
rangeTemp)
```

Read a Region of Interest from a Field

GDextractregion

intn GDextractregion(int32 *gridID*, int32 *regionID*, char **fieldname*, VOIDP *buffer*)

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>regionID</i>	IN:	Region (period) id returned by GDdefboxregion (GDdeftimeperiod)
<i>fieldname</i>	IN:	Field to subset
<i>buffer</i>	OUT:	Data Buffer
Purpose		Extracts (reads) from subsetted region.
Return value		Returns SUCCEED (0) if successful or FAIL (-1) otherwise.
Description		This routine reads data into the data buffer from a subsetted region as defined by GDdefboxregion.
Example		In this example, we extract data from the “Temperature” field from the region defined in <i>GDdefboxregion</i> . We first allocate space for the data buffer. The size of the subsetted region for the field is given by the Gdregioninfo routine.

```
datbuf = (float32) calloc(size, 4);  
  
status = GDextractregion(GDid, regionID, "Temperature",  
datbuf32);
```

FORTRAN

```
integer*4 function gdextreg(gridid, regionid, fieldname, datbuf)  
  
integer*4      gridid  
integer*4      regionid  
character(*)   fieldname  
<valid type>  buffer(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = gdextreg(gridid, regionid, "Temperature", datbuf)
```

Retrieve Information About Data Field in a Grid

GDfieldinfo

```
intn GDfieldinfo(int32 gridID, char *fieldname, int32 rank, int32 dims[], int32  
*numbertype, char *dimlist)
```

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN: Fieldname
<i>rank</i>	OUT: Pointer to rank of the field
<i>dims</i>	OUT: Array containing the dimension sizes of the field
<i>numbertype</i>	OUT: Pointer to the numbertype of the field
<i>dimlist</i>	OUT: Dimension list
Purpose	Retrieve information about a specific geolocation or data field in the grid.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise. A typical reason for failure is the specified field does not exist.
Description	This routine retrieves information on a specific data field.
Example	In this example, we retrieve information about the <i>Spectra</i> data fields:

```
status = GDfieldinfo(gridID, "Spectra", &rank, dims,  
&numbertype, dimlist);
```

The return parameters will have the following values:

rank=3, *numbertype*=5, *dims*[3]={ 15,200,120 } and
dimlist="Bands,YDim,XDim"

FORTRAN

```
integer function gdflinfo (gridid, fieldname, rank, dims, numbertype,  
dimlist)  
  
integer*4      gridid  
character(*)   fieldname  
integer*32     rank  
integer*4      dims(*)  
integer*4      numbertype  
character(*)   dimlist
```

The equivalent *FORTRAN* code for the example above is:

```
status = gdfldinfo(gridid, "Spectra", dims, rank, numbertype,  
dimlist)
```

The return parameters will have the following values:

rank=3, *numbertype*=5, *dims*[3]={120,200,15} and

dimlist="XDim,YDim,Bands"

Note that the dimensions array and the dimension list are in *FORTRAN* order.

Get Fill Value for Specified Field

GDgetfillvalue

intn GDgetfillvalue(int32 *gridID*, char **fieldname*, VOIDP *fillvalue*)

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN:	Fieldname
<i>fillvalue</i>	OUT:	Space allocated to store the fill value
Purpose	Retrieves fill value for the specified field.	
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reasons for failure are an improper grid id or number type or incorrect fill value.	

Description It is assumed the number type of the fill value is the same as the field.

Example In this example, we get the fill value for the "Temperature" field:

```
status = GDgetfillvalue(gridID, "Temperature", &tempfill);
```

FORTRAN integer function gdgetfill(*gridid,fieldname,fillvalue*)

```
integer*4      gridid
```

```
character*(*)  fieldname
```

```
<valid type>  fillvalue(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = gdgetfill(gridid, "Temperature", tempfill)
```

Get Row/Columns for Specified Longitude/Latitude Pairs

GDgetpixels

```
intn GDgetpixels(int32 gridID, int32 nLonLat, float64 lonVal[], float64 latVal[], int32 pixRow[], int32 pixCol[])
```

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>nLonLat</i>	IN: Number of longitude/latitude pairs
<i>lonVal</i>	IN: Longitude values in degrees
<i>latVal</i>	IN: Latitude values in degrees
<i>pixRow</i>	OUT: Pixel Rows
<i>pixCol</i>	OUT: Pixel Columns
Purpose	Returns the pixel rows and columns for specified longitude/latitude pairs.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description	This routine converts longitude/latitude pairs into (0 - based) pixel rows and columns. The origin is the upper left-hand corner of the grid. This routine is the pixel subsetting equivalent of <i>GDdefboxregion</i> .
Example	To convert two pairs of longitude/latitude values to rows and columns, make the following call:

```
lonArr[0] = 134.2;  
latArr[0] = -20.8;  
lonArr[1] = 15.8;  
latArr[1] = 84.6;  
  
status = GDgetpixels(gridID, 2, lonArr, latArr, rowArr,  
colArr);
```

The row and column of the two pairs will be returned in the *rowArr* and *colArr* arrays.

```
FORTRAN    integer function gdgetpix(gridid, nlonlat, lonval, latval, pixrow, pixcol)
            integer*4      gridid
            integer*4      nlonlat
            real*8   lonval
            real*8   latval
            integer*4      pixrow
            integer*4      pixcol
```

The equivalent *FORTRAN* code for the example above is:

```
lonarr(1) = 134.2
latarr(1) = -20.8
lonarr(2) = 15.8
latarr(2) = 84.6
status = gdgetpix(gridid, 2, lonarr, latarr, rowarr, colarr)
```

Note that the row and columns values will be 1 - based.

Get Field Values for Specified Row/Columns

GDgetpixvalues

```
int32 GDgetpixvalues(int32 gridID, int32 nPixels, int32 pixRow[], int32 pixCol[], char *fieldname, VOIDP buffer)
```

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>nPixels</i>	IN:	Number of pixels
<i>pixRow</i>	IN:	Pixel Rows
<i>pixCol</i>	IN:	Pixel Columns
<i>fieldname</i>	IN:	Field from which to extract data values
<i>buffer</i>	OUT:	Buffer for data values
Purpose	Read field data values for specified pixels.	
Return value	Returns size of data buffer if successful or FAIL(-1) otherwise.	
Description	This routine reads data from a data field for the specified pixels. It is the pixel subsetting equivalent of <i>GExtractregion</i> . All entries along the non-geographic dimensions (ie, NOT <i>XDim</i> and <i>YDim</i>) are returned. If the buffer is set to NULL, no data is returned but the data buffer size can be determined from the function return value.	
Example	To read values from the <i>Spectra</i> field with dimensions, <i>Bands</i> , <i>YDim</i> , and <i>XDim</i> , make the following call:	

```
float64      *datbuf;  
  
bufsiz = GDgetpixvalues(gridID, 2, rowArr, colArr, "Spectra",  
NULL);  
  
/* bufsiz will be equal to 2 * NBANDS * 8 where NBANDS is  
the value for the Bands dimension */  
  
datbuf = (float64 *) malloc(bufsiz);  
  
bufsiz = GDgetpixvalues(gridID, 2, rowArr, colArr, "Spectra",  
datbuf);
```

```
FORTRAN    integer*4 function gdgetpixval(gridid, npixels, pixrow, pixcol, fieldname,  
          buffer)  
           integer*4      gridid  
           integer*4      nlonlat  
           integer*4      pixrow  
           integer*4      pixcol  
           character(*)   fieldname  
           <valid type>   buffer(*)
```

The equivalent *FORTRAN* code for the example above is:

```
real*8 datbuf(2,NBANDS)  
  
bufsiz = gdgetpixval(gridid, 2, rowarr, colarr, "Spectra",  
datbuf)
```

Return Information About a Grid Structure

GDgridinfo

```
intn GDgridinfo(int32 gridID, int32 *xysize, int32 *yysize, float64 upleft[z], float64  
                  lowright[z])
```

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>xysize</i>	OUT: Number of columns in grid
<i>yysize</i>	OUT: Number of rows in grid
<i>upleft</i>	OUT: Location, in meters, of upper left corner
<i>lowright</i>	OUT: Location, in meters, of lower right corner
Purpose	Returns position and size of grid
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise
Description	This routine returns the number of rows, columns and the location, in meters, of the upper left and lower right corners of the grid image.
Example	In this example, we retrieve information from a previously created grid with a call to GDattach:

```
status = GDgridinfo(gridID, &xysize, &yysize, upleft,  
                  lowrgt);
```

FORTRAN integer function gdgridinfo(*gridid*, *xysize*, *yysize*, *upleft*, *lowright*)
 integer*4 *gridid*
 integer*4 *xysize*
 integer*4 *yysize*
 real*8 *upleft*(z)
 real*8 *lowright*(z)

The equivalent FORTRAN code for the example above is:

```
status = gdgridinfo(gridid, xysize, yysize, upleft,  
                  lowrgt);
```

Retrieve Information About Grid Attributes

GDinqattrs

int32 GDinqattrs(int32 *gridID*, char **attrlist*, int32 **strbufsize*)

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>attrlist</i>	OUT: Attribute list (entries separated by commas)
<i>strbufsize</i>	OUT: String length of attribute list
Purpose	Retrieve information about attributes defined in grid.
Return value	Number of attributes found if successful or FAIL (-1) otherwise.
Description	The attribute list is returned as a string with each attribute name separated by commas. If <i>attrlist</i> is set to NULL, then the routine will return just the string buffer size, <i>strbufsize</i> . This variable does not count the null string terminator.
Example	In this example, we retrieve information about the attributes defined in a grid structure. We assume that there are two attributes stored, <i>attrOne</i> and <i>attr_2</i> : nattr = GDinqattrs(gridID, NULL, strbufsize); The parameter, <i>nattr</i> , will have the value 2 and <i>strbufsize</i> will have value 14. nattr = GDinqattrs(gridID, attrlist, strbufsize); The variable, <i>attrlist</i> , will be set to: "attrOne,attr_2".
FORTRAN	integer*4 function gdinqattrs(<i>gridid</i> , <i>attrlist</i> , <i>strbufsize</i>) integer*4 <i>gridid</i> character(*) <i>attrlist</i> integer*4 <i>strbufsize</i> The equivalent <i>FORTRAN</i> code for the example above is: nattr = gdinqattrs(gridid, attrlist, strbufsize)

Retrieve Information About Dimensions Defined in Grid

GDinqdims

int32 GDinqdims(int32 *gridID*, char **dimname*, int32 *dims*[])

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>dimname</i>	OUT: Dimension list (entries separated by commas)
<i>dims</i>	OUT: Array containing size of each dimension
Purpose	Retrieve information about dimensions defined in grid.
Return value	Number of dimension entries found if successful or FAIL(-1) otherwise. A typical reason for failure is an improper grid id.
Description	The dimension list is returned as a string with each dimension name separated by commas. Output parameters set to <i>NULL</i> will not be returned.
Example	To retrieve information about the dimensions, use the following statement:

```
ndim = GDinqdims(gridID, dimname, dims);
```

The parameter, *dimname*, will have the value: "Xgrid,Ygrid,Bands"

with *dims*[3]={120,200,15}

FORTRAN

```
integer*4 function gdinqdims(gridid,dimname,dims)
integer*4      gridid
character(*)   dimname
integer*4      dims(*)
```

The equivalent *FORTRAN* code for the example above is:

```
ndim = gdinqdims(gridid, dimname, dims)
```

Retrieve Information About Data Fields Defined in Grid

GDinqfields

int32 GDinqfields(int32 *gridID*, char **fieldlist*, int32 *rank*[], int32 *numbertype*[])

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>fieldlist</i>	OUT: Listing of data fields (entries separated by commas)
<i>rank</i>	OUT: Array containing the rank of each data field
<i>numbertype</i>	OUT: Array containing the numbertype of each data field
Purpose	Retrieve information about the data fields defined in grid.
Return value	Number of data fields found if successful or FAIL(-1) otherwise. A typical reason is an improper grid id.
Description	The field list is returned as a string with each data field separated by commas. The <i>rank</i> and <i>numbertype</i> arrays will have an entry for each field. Output parameters set to <i>NULL</i> will not be returned.
Example	To retrieve information about the data fields, use the following statement:

```
nfld = GDinqfields(gridID, fieldlist, rank, numbertype);
```

The parameter, *fieldlist*, will have the value: "*Temperature,Spectra*"

with *rank*[2]={2,3}, *numbertype*[2]={5,5}

FORTRAN integer*4 function gdinqflds(*gridid*, *fieldlist*, *rank*, *numbertype*)
 integer*4 *gridid*
 character(*) *fieldlist*
 integer*4 *rank*(*)
 integer*4 *numbertype*(*)

The equivalent *FORTRAN* code for the example above is:

```
nfld = gdinqflds(gridID, fieldlist, rank, numbertype);
```

The parameter, *fieldlist*, will have the value: "*Spectra,Temperature*"

with *rank*[2]={3,2}, *numbertype*[2]={5,5}

Retrieve Grid Structures Defined in HDF-EOS File

GDinqgrid

int32 GDinqgrid(char * *filename*, char **gridlist*, int32 **strbufsize*)

<i>filename</i>	IN: HDF-EOS filename
<i>gridlist</i>	OUT: Grid list (entries separated by commas)
<i>strbufsize</i>	OUT: String length of grid list
Purpose	Retrieves number and names of grids defined in HDF-EOS file.
Return value	Number of grids found or FAIL (-1) otherwise.
Description	The grid list is returned as a string with each grid name separated by commas. If <i>gridlist</i> is set to NULL, then the routine will return just the string buffer size, <i>strbufsize</i> . If <i>strbufsize</i> is also set to NULL, the routine returns just the number of grids. Note that <i>strbufsize</i> does not count the null string terminator.
Example	In this example, we retrieve information about the grids defined in an HDF-EOS file, <i>HDFEOS.hdf</i> . We assume that there are two grids stored, <i>GridOne</i> and <i>Grid_2</i> :

```
ngrid = GDinqgrid("HDFEOS.hdf", NULL, strbufsize);
```

The parameter, *ngrid*, will have the value 2 and *strbufsize* will have value 16.

```
ngrid = GDinqgrid("HDFEOS.hdf", gridlist, strbufsize);
```

The variable, *gridlist*, will be set to:

“*GridOne,Grid_2*”.

FORTRAN integer*4 function gdinqgrid(*filename,gridlist,strbufsize*)
 character*(*) *filename*
 character*(*) *gridlist*
 integer*4 *strbufsize*

The equivalent *FORTRAN* code for the example above is:

```
ngrid = gdinqgrid('HDFEOS.hdf', gridlist, strbufsize)
```

Perform Bilinear Interpolation on Grid Field

GDinterpolate

```
int32 GDinterpolate(int32 gridID, int32 nInterp, float64 lonVal[], float64 latVal[], char *fieldname, float64 interpVal[])
```

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>nInterp</i>	IN:	Number of interpolation points
<i>lonVal</i>	IN:	Longitude of interpolation points
<i>latVal</i>	IN:	Latitude of interpolation points
<i>fieldname</i>	OUT:	Field from which to interpolate data values
<i>interpVal</i>	OUT:	Buffer for interpolated data values
Purpose	Performs bilinear interpolation on a grid field.	
Return value	Returns size in bytes of interpolated data values if successful or FAIL(-1) otherwise.	
Description	This routine performs bilinear interpolation on a grid field. It assumes that the pixel data values are uniformly spaced which is strictly true only for an infinitesimally small region of the globe but is a good approximation for a sufficiently small region. The default position of the pixel value is pixel center, however if the pixel registration has been set to HDFE_CORNER (with the <i>GDdefpixreg</i> routine) then the value is located at one of the four corners (HDFE_GD_UL, _UR, _LL, _LR) specified by the <i>GDdeforigin</i> routine. All entries along the non-geographic dimensions (ie, NOT XDim and YDim) are interpolated and all interpolated values are returned as FLOAT64. The data buffer size can be determined by setting the <i>interpVal</i> parameter to NULL. The reference for the interpolation algorithm is <i>Numerical Recipes in C</i> (2 nd ed). (Note for the current version of this routine, the number type of the field to be interpolated is restricted to INT16, INT32, FLOAT32, FLOAT64.)	
Example	To interpolate the <i>Spectra</i> field at two geographic data points:	
	<pre>lonVal[0] = 134.2; latVal[0] = -20.8; lonVal[1] = 15.8; latVal[1] = 84.6;</pre>	

```

float64      *interpVal;

bufsiz = GDinterpolate(gridID, 2, lonVal, latVal, "Spectra",
NULL);

/* bufsiz will be equal to 2 * NBANDS * 8 where NBANDS is the
value for the Bands dimension */

interpVal = (float64 *) malloc(bufsiz);

bufsiz = GDinterpolate(gridID, 2, lonVal, latVal, "Spectra",
interpVal);

FORTRAN    integer*4 function gdinterpolate(gridid, ninterp, lonval, latval, fieldname,
interpval)
            integer*4      gridid
            integer*4      ninterp
            real*8        lonval
            real*8        latval
            character(*)  fieldname
            real*8        interpval

```

The equivalent *FORTRAN* code for the example above is:

```

real*8      interpval(NBANDS, 2)

bufsiz = gdinterpolate(gridid, 2, lonval, latval, "Spectra",
interpval)

```

Return Number of Specified Objects in a Grid

GDnentries

int32 GDnentries(int32 *gridID*, int32 *entrycode*, int32 **strbufsize*)

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>entrycode</i>	IN: Entrycode
<i>strbufsize</i>	OUT: String buffer size
Purpose	Returns number of entries and descriptive string buffer size for a specified entity.
Return value	Number of entries if successful or FAIL(-1) otherwise. A typical reason for failure is an improper grid id or entry code.
Description	This routine can be called before using the inquiry routines in order to determine the sizes of the output arrays and descriptive strings. The string length does not include the NULL terminator. The entry codes are: HDFE_NENTDIM (0) - Dimensions HDFE_NENTDFLD (4) - Data Fields
Example	In this example, we determine the number of data field entries and the size of the field list string.

```
ndims = GDnentries(gridID, HDFE_NENTDFLD, &bufsz);
```

FORTRAN integer*4 function gdnentries(*gridid*,*entrycode*, *bufsize*)
 integer*4 *gridid*
 integer*4 *entrycode*
 integer*4 *bufsize*

The equivalent *FORTRAN* code for the example above is:

```
ndims = gdnentries(gridid, 4, bufsize)
```

Open HDF-EOS File

GDopen

int32 GDopen(char *filename, intn access)

filename	IN:	Complete path and filename for the file to be opened
access	IN:	DFACC_READ, DFACC_RDWR or DFACC_CREATE
Purpose		Opens or creates HDF file in order to create, read, or write a grid.
Return value		Returns the grid file id handle(fid) if successful or FAIL(-1) otherwise.
Description		This routine creates a new file or opens an existing one, depending on the access parameter.

Access codes:

DFACC_READ	Open for read only. If file does not exist, error
DFACC_RDWR	Open for read/write. If file does not exist, create it
DFACC_CREATE	If file exist, delete it, then open a new file for read/write

Example In this example, we create a new grid file named, *GridFile.hdf*. It returns the file handle, *fid*.

```
fid = GDopen("GridFile.hdf", DFACC_CREATE);  
FORTRAN integer*4 function gdopen(filename, access)  
character*(*) filename  
integer access
```

The access codes should be defined as parameters:

```
parameter (DFACC_READ=1)  
parameter (DFACC_RDWR=3)  
parameter (DFACC_CREATE=4)
```

The equivalent *FORTRAN* code for the example above is:

```
fid = gdopen("GridFile.hdf", DFACC_CREATE)
```

Note to users of the SDP Toolkit: Please refer to the *Release 5B SDP Toolkit User Guide for the ECS Project (333-CD-510-001)*, Section 6.2.1.2 for information on how to obtain a file name (referred to as a "physical file handle") from within a PGE. See also Section 9 of this document for code examples.

Return Grid Origin Information

GDorigininfo

intn GDorigininfo(int32 *gridID*, int32 **origincode*)

gridID IN: Grid id returned by GDcreate or GDattach

origincode IN: Origin code

Purpose Retrieve origin code.

Return value Origin code if successful or FAIL (-1) otherwise.

Description This routine retrieves the origin code.

Example In this example, we retrieve the origin code defined in *GDdeforigin*.

```
status = GDorigininfo(gridID, &origincode);
```

The return value, *origincode*, will be equal to 3

FORTRAN integer function gdorginfo(*gridid*,*origincode*)

```
integer*4      gridid
```

```
integer*4      origincode
```

The equivalent *FORTRAN* code for the above example is :

```
status = gdorginfo(gridid, origincode)
```

Return Pixel Registration Information

GDpixreginfo

intn GDpixreginfo(int32 *gridID*, int32 **pixregcode*)

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>pixregcode</i>	IN:	Pixel registration code
Purpose		Retrieve pixel registration code.
Return value		Pixel registration code if successful or FAIL (-1) otherwise.
Description		This routine retrieves the pixel registration code.
Example		In this example, we retrieve the pixel registration code defined in <i>GDdefpixreg</i> .

status = GDpixreginfo(*gridID*, &*pixregcode*);

The return value, *pixregcode*, will be equal to 1

FORTRAN integer function gdpreginfo(*gridid*,*pixregcode*)
 integer*4 *gridid*
 integer*4 *pixregcode*

The equivalent *FORTRAN* code for the above example is :

status = gdpreginfo(*gridid*, *pixregcode*)

Retrieve Grid Projection Information

GDprojinfo

```
intn GDprojinfo(int32 gridID, int32 *projcode, int32 *zonecode, int32 *spherecode,  
                 float64 projparm[])
```

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>projcode</i>	OUT: GCTP projection code
<i>zonecode</i>	OUT: GCTP zone code used by UTM projection
<i>spherecode</i>	OUT: GCTP spheroid code
<i>projparm</i>	OUT: GCTP projection parameter array
Purpose	Retrieves projection information of grid
Return Value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise
Description	Retrieves the GCTP projection code, zone code, spheroid code and the projection parameters of the grid
Example	In this example, we are retrieving the projection information from a grid attached to with GDattached:

```
status = GDprojinfo(gridID, &projcode, &zonecode, &spherecode,  
                     projparm);
```

FORTRAN

```
integer function gdprojinfo( gridid, projcode, zonecode, spherecode,  
                           projparm)  
  
    integer*4      gridid  
    integer*4      projcode  
    integer*4      zonecode  
    integer*4      spherecode  
    real*8        projparm(*)
```

The equivalent FORTRAN code for the example above is:

```
status = gdprojinfo(gridid, projcode, zonecode, spherecode,  
                     projparm)
```

Read Grid Attribute

GDreadattr

intn GDreadattr(int32 *gridID*, char **attrname*, VOIDP *datbuf*)

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>attrname</i>	IN:	Attribute name
<i>datbuf</i>	OUT:	Buffer allocated to hold attribute values
Purpose		Reads attribute from a grid.
Return value		Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reasons for failure are an improper grid id or number type or incorrect attribute name.
Description		The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types.
Example		In this example, we read a single precision (32 bit) floating point attribute with the name "ScalarFloat":

```
status = GDreadattr(gridID, "ScalarFloat", &f32);
```

FORTRAN integer function gdrdattr(*gridid*, *attrname*,*datbuf*)

```
integer*4      gridid  
character(*)   attrname  
<valid type>  datbuf(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = gdrdattr(gridid, "ScalarFloat", f32)
```

Read Data From a Grid Field

GDreadfield

```
intn GDreadfield(int32 gridID, char *fieldname, int32 start[], int32 stride[], int32  
    edge[], VOIDP buffer)
```

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN: Name of field to read
<i>start</i>	IN: Array specifying the starting location within each dimension
<i>stride</i>	IN: Array specifying the number of values to skip along each dimension
<i>edge</i>	IN: Array specifying the number of values to write along each dimension
<i>buffer</i>	IN: Buffer to store the data read from the field
Purpose	Reads data from a grid field.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reasons for failure are improper grid id or unknown fieldname.
Description	The values within <i>start</i> , <i>stride</i> , and <i>edge</i> arrays refer to the grid field (input) dimensions. The output data in <i>buffer</i> is written to contiguously. The default values for <i>start</i> and <i>stride</i> are 0 and 1 respectively and are used if these parameters are set to <i>NULL</i> . The default values for <i>edge</i> are (<i>dim</i> - <i>start</i>) / <i>stride</i> where <i>dim</i> refers to the size of the dimension.
Example	In this example, we read data from the 10th row (0-based) of the <i>Temperature</i> field. <pre>float32 row[120]; int32 start[2]={10,1}, edge[2]={1,120}; status = GDreadfield(gridID, "Temperature", start, NULL, edge, row);</pre>

```

FORTRAN    integer function
           gdrdfld(gridid,fieldname,start,stride,edge,buffer)
           integer*4      gridid
           character*(*)  fieldname
           integer*4      start(*)
           integer*4      stride(*)
           integer*4      edge(*)
           <valid type>   buffer(*)

```

The *start*, *stride*, and *edge* arrays must be defined explicitly, with the *start* array being 0-based.

The equivalent *FORTRAN* code for the example above is:

```

real*4 row(2000)

integer*4 start(2), stride(2), edge(2)

start(1) = 10
start(2) = 0
stride(1) = 1
stride(2) = 1
edge(1) = 2000
edge(2) = 1

status = gdrdfld(gridid, "Temperature", start, stride, edge,
row)

```

Read from Tile within Field

GDreadtile

intn GDreadtile(int32 *gridID*, char **fieldname*, int32 *tilecoords[]*, VOIDP *buffer*)

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN:	Fieldname
<i>tilecoords</i>	IN:	Array of tile coordinates
<i>buffer</i>	OUT:	Data to be written to tile
Purpose		Reads from tile within field.
Return value		Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description		This routine reads a single tile of data from a field. If the data is to be read tile by tile, this routine is more efficient than <i>GDrreadfield</i> . In all other cases, the later routine should be used. <i>GDreadtile</i> does not work on non-tiled fields. Note that the coordinates in terms of tiles, not data elements.
Example		In this example, we read one tile from the <i>Temperature</i> field (see <i>GDdeftile</i> example) located at the second column of the first row of tiles. <i>Buffer</i> should contain space for $200 * 100 * 4 = 80000$ bytes.

```
tilecoords[0] = 0;
tilecoords[1] = 1;
status = GDreadtile(gridid, "Temperature", tilecoords, buffer);
```

FORTRAN

```
integer function gdrdtile(gridid, fieldname, tilecoords, buffer)
integer*4      gridid
character(*)   fieldname
integer*4      tilecoords(*)
<valid type>  buffer(*)
```

The equivalent *FORTRAN* code for the first example above is:

```
tilecoords(1) = 1;
tilecoords(2) = 0;
status = gdrdtile(gridid, "Temperature", tilecoords, buffer)
```

Note that *tilecoords* for *FORTRAN* are reversed from the C language example but the values are still 0-based.

Return Information About a Region

GDregioninfo

```
intn GDregioninfo(int32 gridID, int32 regionID, char * fieldname, int32 *nype, int32  
                  *irank, int32 dims[], int32 *size, float64 upleftpt[], float64  
                  lowrightpt[])
```

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>regionID</i>	IN:	Region (period) id returned by GDdefboxregion (GDdeftimeperiod)
<i>fieldname</i>	IN:	Field to subset
<i>nype</i>	OUT:	Number type of field
<i>rank</i>	OUT:	Rank of field
<i>dims</i>	OUT:	Dimensions of subset region
<i>size</i>	OUT:	Size in bytes of subset region
<i>upleftpt</i>	OUT:	Upper left point of subset region
<i>lowrightpt</i>	OUT:	Lower right point of subset region
Purpose	Retrieves information about the subsetted region.	
Return value	Returns SUCCEED (0) if successful or FAIL (-1) otherwise.	
Description	This routine returns information about a subsetted region for a particular field. It is useful when allocating space for a data buffer for the region. Because of differences in number type and geolocation mapping, a given region will give different values for the dimensions and size for various fields. The <i>upleftpt</i> and <i>lowrightpt</i> arrays can be used when creating a new grid from the subsetted region.	
Example	In this example, we retrieve information about the region defined in <i>GDdefboxregion</i> for the <i>Temperature</i> field. We use this to allocate space for data in the subsetted region.	

```
status = GDregioninfo(GDid, regionID, "Temperature", &nype,  
                  &rank, dims, &size, upleft, lowright);
```

```
FORTRAN    integer function gdreginfo(gridid, regionid, fieldname, ntype, rank, dims,  
           size, upleftpt, lowrightpt)  
  
           integer*4      gridid  
           integer*4      gridid  
           character(*)   fieldname  
           integer*4      ntype  
           integer*4      rank  
           integer*4      dims(*)  
           integer*4      size  
           real*8        upleftpt  
           real*8        lowrightpt
```

The equivalent *FORTRAN* code for the example above is:

```
status = gdreginfo(gridid, regid, "Spectra", ntype, rank, dims,  
size, upleftpt, lowrightpt)
```

Set Fill Value for a Specified Field

GDsetfillvalue

intn GDsetfillvalue(int32 *gridID*, char **fieldname*, VOIDP *fillvalue*)

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN: Fieldname
<i>fillvalue</i>	IN: Pointer to the fill value to be used
Purpose	Sets fill value for the specified field.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reasons for failure are an improper grid id or number type.
Description	The fill value is placed in all elements of the field which have not been explicitly defined.
Example	In this example, we set a fill value for the "Temperature" field:

```
tempfill = -999.0;  
  
status = GDsetfillvalue(gridID, "Temperature", &tempfill);
```

FORTRAN integer function

```
gdsetfill(gridid,fieldname,fillvalue)  
integer*4      gridid  
character(*)   fieldname  
<valid type>  fillvalue(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = gdsetfill(gridid, "Temperature", -999.0)
```

Set Tile Cache Parameters

GDsettilecache

intn GDsettilecache(int32 *gridID*, char **fieldname*, int32 *maxcache*, int32 *cachecode*)

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN:	Fieldname
<i>maxcache</i>	IN:	Maximum number of tiles to cache in memory
<i>cachecode</i>	IN:	Currently must be set to 0
Purpose		Sets tile cache parameters
Return Value		Returns SUCCEED(0) if successful or FAIL(-1) otherwise
Description		This routine sets the maximum cache for tiling. If the cache is set fro a fewer number of tiles than needed for a particular subset of the field, there can be serious efficiency problems. Therefore it is recommended that this routine not be used unless one is aware for each field, the expected size of a particular subset and it's position relative to the tiles. The <i>maxcache</i> value should be set to the number of tiles which fit along the fastest varying dimension.
Example		In this example, we set <i>maxcache</i> to 10 tiles. The particular subsetting envisioned for the <i>Spectra</i> field (defined in the <i>GDdeftile</i> example) would never cross more than 10 tiles along the field's fastest varying dimension, ie, <i>XDim</i> ..

```
status = GDsettilecache(gridID, "Spectra", 10, 0);
```

FORTRAN

```
integer function gdsettleche(gridid, fieldname,maxcache,cachecode)
integer*4      gridid
character(*)   fieldname
integer*4      maxcache
integer*4      cachecode
```

The equivalent *FORTRAN* code for the example above is:

```
status = gdsettleche(gridid, 'Spectra', 10, 0)
```

Set Tiling/Compression Parameters

GDsettilecomp

intn GDsettilecomp(int32 *gridID*, char *fieldname*, int32 *tilerank*, int32 *tiledims*, int32 *compcode*, intn **compparm*)

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN:	Field name
<i>tilerank</i>	IN:	The number of tile dimensions
<i>tiledims</i>	IN:	Tile dimensions
<i>compcode</i>	IN:	HDF compression code
<i>compparm</i>	IN:	Compression parameters(if applicable)
Purpose		Set tiling and compression parameters for a field that has fill values.
Return value		Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description		This routine was added as a fix to a bug in HDF-EOS. The current method of implementation didn't allow the user to have a field with fill values and use tiling and compression. This function allows the user to access all of these features. This function must be called in a particular order.
Example		<p>This function must be used in a particular sequence with other HDF_EOS Grid functions.</p> <ol style="list-style-type: none">(1) GDdeffield – Define field(2) GDsetfillvalue – Set fill value for field(3) GDsettilecomp – Set tiling(chunking) and compression parameters for field <pre>tile_dim[0] = 1; tile_dim[1] = 128; tile_dim[2] = 512; compparm[1] = 5; status = GDsettilecomp(gridID, "AveSceneElev", 3, tile_dim, HDFE_COMP_DEFLATE, compparm);</pre>
NOTE:		This routine is currently implemented in "C" only. If the need arises, a FORTRAN function will be added.

Retreive Tiling Information for Field

GDtileinfo

```
intn GDtileinfo(int32 gridID, char *fieldname, int32 *tilecode, int32 *tilerank, int32 tiledims[])
```

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN: Fieldname
<i>tilecode</i>	OUT: Tile code: HDF_TILE, HDF_NOTILE
<i>tilerank</i>	OUT: The number of tile dimensions
<i>tiledims</i>	OUT: Tile dimensions
Purpose	Retrieves tiling information about a field.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description	This routine returns the tiling code, tiling rank, and tiling dimensions for a given field.
Example	To retreive the tiling information about the <i>Pressure</i> field defined in the <i>GDdeffile</i> section:

```
status = GDtileinfo(gridID, "Pressure", &tilecode, &tilerank,  
tiledims);
```

The *tilecode* parameter will be set to 1, the *tilerank* to 2, and *tiledims* to {100,200}.

FORTRAN

```
integer function gdtileinfo(gridid,fieldname tilecode,tilerank,tiledims)  
integer*4      gridid  
character*(*)  fieldname  
integer*4      tilecode  
integer*4      tilerank  
integer*4      tiledims(*)
```

The equivalent *FORTRAN* code for the example above is:

```
status = gdtileinfo(gridid, 'Pressure', tilecode, tilerank,  
tiledims)
```

The *tilecode* parameter will be set to 1, the *tilerank* to 2, and *tiledims* to {200,100}.

Write/Update Grid Attribute

GDwriteattr

intn GDwriteattr(int32 <i>gridID</i> , char * <i>attrname</i> , int32 <i>ntype</i> , int32 <i>count</i> , voidp <i>datbuf</i>)	VOIDP
<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>attrname</i>	IN: Attribute name
<i>ntype</i>	IN: Number type of attribute
<i>count</i>	IN: Number of values to store in attribute
<i>datbuf</i>	IN: Attribute values
Purpose	Writes/Updates attribute in a grid.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reasons for failure are an improper grid id or number type.
Description	If the attribute does not exist, it is created. If it does exist, then the value(s) is (are) updated. The attribute is passed by reference rather than value in order that a single routine suffice for all numerical types. Because of this a literal numerical expression should not be used in the call.
Example	In this example, we write a single precision (32 bit) floating point number with the name "ScalarFloat" and the value 3.14: <pre>f32 = 3.14; status = GDwriteattr(gridid, "ScalarFloat", DFNT_FLOAT32, 1, &f32);</pre> We can update this value by simply calling the routine again with the new value: <pre>f32 = 3.14159; status = GDwriteattr(gridid, "ScalarFloat", DFNT_FLOAT32, 1, &f32);</pre>
FORTRAN	integer function gdwrattr(<i>gridid</i> , <i>attrname</i> , <i>ntype</i> , <i>count</i> , <i>datbuf</i>) integer*4 <i>gridid</i> character*(*) <i>attrname</i> integer*4 <i>ntype</i> integer*4 <i>count</i> <valid type> <i>datbuf(*)</i>

The equivalent *FORTRAN* code for the first example above is:

```
parameter (DFNT_FLOAT32=5)
f32 = 3.14
status = gdwrattr(gridid, "ScalarFloat", DFNT_FLOAT32, 1,
                  f32)
```

Write Data to a Grid Field

GDwritefield

```
intn GDwritefield(int32 gridID, char *fieldname, int32 start[], int32 stride[], int32 edge[], VOIDP data)
```

<i>gridID</i>	IN: Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN: Name of field to write
<i>start</i>	IN: Array specifying the starting location within each dimension (0-based)
<i>stride</i>	IN: Array specifying the number of values to skip along each dimension
<i>edge</i>	IN: Array specifying the number of values to write along each dimension
<i>data</i>	IN: Values to be written to the field
Purpose	Writes data to a grid field.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description	The values within <i>start</i> , <i>stride</i> , and <i>edge</i> arrays refer to the grid field (output) dimensions. The input data in the <i>data</i> buffer is read from contiguously. The default values for <i>start</i> and <i>stride</i> are 0 and 1 respectively and are used if these parameters are set to <i>NULL</i> . The default values for <i>edge</i> are <i>(dim - start) / stride</i> where <i>dim</i> refers to the size of the dimension. Note that the data buffer for a compressed field must be the size of the entire field as incremental writes are not supported by the underlying HDF routines. If this is not possible due to, for example, memory limitations, then the user should consider tiling. See <i>GDdeftile</i> for further information.
Example	In this example, we write data to the <i>Temperature</i> field. <pre>float32 temperature [200][120]; /* Define elements of temperature array */ status = GDwritefield(gridID, "Temperature", NULL, NULL, NULL, temperature);</pre> We now update Row 10 (0 - based) in this field: <pre>float32 newrow[2000]; int32 start[2]={0,10}, edge[2]={2000,1}; /* Define elements of newrow array */ status = GDwritefield(gridID, "Temperature", start, NULL, edge, newrow);</pre>

```

FORTRAN    integer function
           gdwrfld(gridid,fieldname,start,stride,edge,data)
           integer*4      gridid
           character(*)   fieldname
           integer*4      start(*)
           integer*4      stride(*)
           integer*4      edge(*)
           <valid type>  data(*)

```

The *start*, *stride*, and *edge* arrays must be defined explicitly, with the *start* array being 0-based.

The equivalent *FORTRAN* code for the example above is:

```

real*4 temperature(2000,1000)
integer*4 start(2), stride(2), edge(2)
start(1) = 0
start(2) = 0
stride(1) = 1
stride(2) = 1
edge(1) = 2000
edge(2) = 1000
status = gdwrfld(gridid, "Temperature", start, stride, edge,
                  temperature)

```

We now update Row 10 (0 - based) in this field:

```

real*4 newrow(2000)
integer*4 start(2), stride(2), edge(2)
start(1) = 10
start(2) = 0
stride(1) = 1
stride(2) = 1
edge(1) = 2000
edge(2) = 1
status = gdwrfld(gridid, "Temperature", start, stride, edge,
                  newrow)

```

Write Field Metadata for an Existing Field Not Defined With the Grid API

GDwritefieldmeta

intn GDwritefieldmeta(int32 *gridID*, char **fieldname*, char **dimlist*, int32 *numbertype*)

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN:	Name of field that metadata information is to be written
<i>dimlist</i>	IN:	Dimension list of field
<i>numbertype</i>	IN:	Number type of data in field
Purpose		Writes field metadata for an existing grid field not defined with the Grid API
Return Value		Returns SUCCEED(0) if successful or FAIL(-1) otherwise
Description		This routine writes the field metadata for a grid field not defined by the Grid API

Example

```
status = GDwritefieldmeta(gridID, "ExternField",
                           "Ydim,Xdim", DFNT_FLOAT32);
```

FORTRAN integer function gdwrmeta(gridid, *fieldname*, *dimlist*, *numbertype*)
 integer*4 *gridid*
 character(*) *fieldname*
 character(*) *dimlist*
 integer*4 *numbertype*

The equivalent *FORTRAN* code for the example above is:

```
status = gdwrmeta(gridid, "ExternField, "Xdim,Ydim",
                   DFNT_FLOAT32)
```

Write to Tile within Field

GDwritetile

intn GDwritetile(int32 *gridID*, char **fieldname*, int32 *tilecoords*[], VOIDP *data*)

<i>gridID</i>	IN:	Grid id returned by GDcreate or GDattach
<i>fieldname</i>	IN:	Fieldname
<i>tilecoords</i>	IN:	Array of tile coordinates
<i>data</i>	IN:	Data to be written to tile
Purpose		Writes to tile within field.
Return value		Returns SUCCEED(0) if successful or FAIL(-1) otherwise. Typical reasons for failure are an improper grid id or number type.
Description		This routine writes a single tile of data to a field. If the data to be written to a field can be arranged tile by tile, this routine is more efficient than <i>GDwritefield</i> . In all other cases, the later routine should be used. <i>GDwritetile</i> does not work on non-tiled fields. Note that the coordinates in terms of tiles, not data elements.
Example		In this example, we write one tile to the <i>Temperature</i> field (see <i>GDdeffile</i> example) at the second column of the first row of tiles. Note that there are $200 * 100 * 4 = 80000$ bytes in <i>data</i> : <pre>tilecoords[0] = 0; tilecoords[1] = 1; status = GDwritetile(gridid, "Temperature", tilecoords, data);</pre>
FORTAN		<pre>integer function gdwrtle(gridid, fieldname, tilecoords, data) integer*4 gridid character(*) fieldname integer*4 tilecoords(*) <valid type> data(*)</pre>

The equivalent *FORTAN* code for the first example above is:

```
tilecoords(1) = 1
tilecoords(2) = 0
status = gdwrtle(gridid, "Temperature", tilecoords, data)
```

Note that *tilecoords* for FORTAN are reversed from the C language example but the values are still 0-based.

2.1.4 HDF-EOS Utility Routines

This section contains an alphabetical listing of the HDF-EOS utility routines.

Convert Among Angular Units

EHconvAng

float64 EHconvAng(float64 *inAngle*, intn *code*)

<i>inAngle</i>	IN: Input angle
<i>code</i>	IN: Conversion code
Purpose	Convert among various angular units.
Return value	Returns angle in desired units if successful or FAIL (-1) otherwise.
Description	This routine converts angles between three units, decimal degrees, radians, and packed degrees-minutes-seconds. In the later unit, an angle is expressed as a integral number of degrees and minutes and a float point value of seconds packed as a single float64 number as follows: DDDMMMSSS.SS. The six conversion codes are: HDFE_RAD_DEG (0), HDFE_DEG_RAD (1), HDFE_DMS_DEG (2), HDFE_DEG_DMS (3), HDFE_RAD_DMS (0), and HDFE_DMS_RAD (1), where the first three letter code (RAD - radians, DEG - decimal degrees, DMS - packed degrees-minutes-seconds) corresponds to the input angle and the second to the desired output angular unit.

Example To convert 27.5 degrees to packed format:

```
inAng = 27.5;  
outAng = EHconvAng(inAng, HDFE_DEG_DMS);  
“outAng” will contain the value: 27030000.00.
```

FORTRAN real*8 function ehconvang(*inangle,code*)
 real*8 *inangle*
 integer *code*

The equivalent *FORTRAN* code for the example above is:

```
inangle = 27.5  
outangle = ehconvang(inangle,3)
```

Get HDF-EOS Version String

EHgetversion

intn EHgetversion(int32 *fid*, char **version*)

<i>fid</i>	IN: File id returned by <i>SWopen</i> , <i>GDopen</i> , or <i>PTopen</i> .
<i>version</i>	OUT: HDF-EOS version string
Purpose	Get HDF-EOS version string.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description	This routine returns the HDF-EOS version string of an HDF-EOS file. This designates the version of HFD-EOS that was used to create the file. This string is of the form: “HDFEOS_V <i>maj.min</i> ” where <i>maj</i> is the major version and <i>min</i> is the minor version.

Example To get the HDF-EOS version (assumed to be 2.7) used to create the HDF-EOS file: “SwathFile.hdf”:

```
char version[16];  
  
fid = SWopen("SwathFile.hdf", DFACC_READ);  
  
status = EHgetversion(fid, version);  
  
“version” will contain the string: “HDFEOS_V2.7”.
```

FORTRAN integer function ehgetver(*fid*,*version*)
integer*4 *fid*
character*(*) *version*

The equivalent *FORTRAN* code for the example above is:

```
character*16 version  
fid = swopen("SwathFile.hdf",1)  
status = ehgetver(fid, version)
```

Get HDF File ids

EHidinfo

intn EHidinfo(int32 *fid*, int32 **HDFfid*, int32 **sdInterfaceID*)

<i>fid</i>	IN: File id returned by <i>SWopen</i> , <i>GDopen</i> , or <i>PTopen</i> .
<i>HDFfid</i>	OUT: HDF file ID (returned by <i>Hopen</i>)
<i>sdInterfaceID</i>	OUT: SD interface ID (returned by <i>SDstart</i>)
Purpose	Get HDF file IDs.
Return value	Returns SUCCEED(0) if successful or FAIL(-1) otherwise.
Description	This routine returns the HDF file ids corresponding to the HDF-EOS file id returned by <i>SWopen</i> , <i>GDopen</i> , or <i>PTopen</i> . These ids can then be used to create or access native HDF structure such as SDS arrays, Vdatas, or HDF attributes within an HDF-EOS file.
Example	To create a vdata within an existing HDF-EOS file:

```
char version[16];  
  
fid = SWopen("SwathFile.hdf", DFACC_RDWR);  
  
status = EHgetid(fid, &HDFfid, &sdInterfaceID);  
  
vdata_id = VSattach(HDFfid, -1, "w");  
  
[Define vdata fields]  
  
VSdetach(vdata_id);  
  
SWclose(fid);
```

Note that the file is opened and closed using the HDF-EOS open and close routines.

To access the SDS id of an HDF-EOS (unmerged) grid field:

```
fid = SWopen("GridFile.hdf", DFACC_RDWR);  
  
status = EHgetid(fid, &HDFfid, &sdInterfaceID);  
  
idx = SDnametoindex(sdInterfaceID, "GridField");  
  
sdsID = SDselect(sdInterfaceID, idx);
```

The user can now apply the HDF SD interface directly to the field.

FORTRAN integer function ehidinfo(*fid,hdffid,sdid*)

```
integer*4      fid  
integer*4      hdffid  
integer*4      sdid
```

Convert EASE grid coordinates (r,s) to (longitude, latitude)

GDrss2ll

```
intn GDrss2ll(int32 projcode, float64 projparm[], int32 xdimsize, int32 ydimsize,
               int32 npnts, float64 r[], float64 s[], float64 longitude[], float64
               latitude[], int32 pixcen, int32 pixcnr)
```

<i>projcode</i>	IN:	GCTP projection code (GCTP_BCEA)
<i>projparm</i>	IN:	Projection parameters
<i>xdimsize</i>	IN:	xdimsize from <i>GDcreate</i>
<i>ydimsize</i>	IN:	ydimsize from <i>GDcreate</i>
<i>pixcen</i>	IN:	pixel center code
<i>npnts</i>	IN:	number of lon-lat points
<i>r</i>	IN:	array of EASE grid's r coordinate
<i>s</i>	IN:	array of EASE grid's s coordinate
<i>pixcen</i>	IN:	Code from <i>GDpixreginfo</i>
<i>pixcnr</i>	IN:	Code from <i>GDorigininfo</i>
<i>longitude</i>	OUT:	longitude array (decimal degrees)
<i>latitude</i>	OUT:	latitude array (decimal degrees)

Purpose Converts EASE grid's (r,s) coordinates to longitude and latititude.

Return value Returns SUCCEED(0) if successful or FAIL(-1) otherwise.

Description This routine converts EASE grid's (r,s) coordinates to longitude and latititude in decimal degrees. The input parameters *xdimsize* and *ydimsize* are 1383 and 586 respectively. The codes HDFE_CORNER and HDFE_GD_UL should be used for *pixcen* and *pixcnr* respectively.

Example

```
int32 i, npnts = 2;
int32      projcode;
float64    projparm[13];
float64    rcord[2], scord[2];
```

```

float64      lon[2], lat[2];

int32 xdimsize,ydimsize;
xdimsize = 1383 ;
ydimsize = 586;
rrecord[0]= 0. ;
scord[0]= 0. ;
rrecord[1]= 691.5;
scord[1]= 293. ;
for(i=0; i<13; i++) projparm[i] = 0.0;
status = GDrs2ll(GCTP_BCEA, projparm, xdimsize,ydimsize,
npts, rrecord, scord, lon, lat, HDFE_CORNER, HDFE_GD_UL);

```

FORTRAN integer function gdrls2ll(projcode, projparm, xdimsize, ydimsize, npts, r,
s, longitude, latitude, pixcen, pixcnr)

```

integer*4      projcode
integer*4      pixcen
integer*4      pixcnr
real*8        projparm(*)
integer*4      xdimsize
integer*4      ydimsize
integer*4      xdimsize
integer*4      npts
real*8        r(*)
real*8        s(*)
real*8        longitude(*)
real*8        latitude()

```

The Equivalent FORTRAN code for the example above is:

```
parameter (GCTP_BCEA = 98)
parameter (HDFE_CORNER = 1)
parameter (HDFE_GD_UL = 0)
do I=1,13
    projparm(i) = 0.0
enddo
npnts = 2
xdimsize = 1383
ydimsize = 586
rcord(1)= 0.
scord(1)= 0.
rcord(2)= 691.5
scord(2)= 293.
status = gdrs211(GCTP_BCEA, projparm, xdimsize,
&ydimsize, npnts, rcord, scord, longitude,
&latitude, HDFE_CORNER, HDFE_GD_UL)
```

This page intentionally left blank.

Abbreviations and Acronyms

AI&T	Algorithm Integration & Test
AIRS	Atmospheric Infrared Sounder
API	application program interface
ASTER	Advanced Spaceborne Thermal Emission and Reflection Radiometer
CCSDS	Consultative Committee on Space Data Systems
CDRL	Contract Data Requirements List
CDS	CCSDS day segmented time code
CERES	Clouds and Earth Radiant Energy System
CM	configuration management
COTS	commercial off-the-shelf software
CUC	constant and unit conversions
CUC	CCSDS unsegmented time code
DAAC	distributed active archive center
DBMS	database management system
DCE	distributed computing environment
DCW	Digital Chart of the World
DEM	digital elevation model
DTM	digital terrain model
ECR	Earth centered rotating
ECS	EOSDIS Core System
EDC	Earth Resources Observation Systems (EROS) Data Center
EDHS	ECS Data Handling System
EDOS	EOSDIS Data and Operations System
EOS	Earth Observing System
EOSAM	EOS AM Project (morning spacecraft series)
EOSDIS	Earth Observing System Data and Information System
EOSPM	EOS PM Project (afternoon spacecraft series)

ESDIS	Earth Science Data and Information System (GSFC Code 505)
FDF	flight dynamics facility
FOV	field of view
ftp	file transfer protocol
GCT	geo-coordinate transformation
GCTP	general cartographic transformation package
GD	grid
GPS	Global Positioning System
GSFC	Goddard Space Flight Center
HDF	hierarchical data format
HITC	Hughes Information Technology Corporation
http	hypertext transport protocol
I&T	integration & test
ICD	interface control document
IDL	interactive data language
IP	Internet protocol
IWG	Investigator Working Group
JPL	Jet Propulsion Laboratory
LaRC	Langley Research Center
LIS	Lightening Imaging Sensor
M&O	maintenance and operations
MCF	metadata configuration file
MET	metadata
MODIS	Moderate-Resolution Imaging Spectroradiometer
MSFC	Marshall Space Flight Center
NASA	National Aeronautics and Space Administration
NCSA	National Center for Supercomputer Applications
netCDF	network common data format
NGDC	National Geophysical Data Center
NMC	National Meteorological Center (NOAA)

ODL	object description language
PC	process control
PCF	process control file
PDPS	planning & data production system
PGE	product generation executive (formerly product generation executable)
POSIX	Portable Operating System Interface for Computer Environments
PT	point
QA	quality assurance
RDBMS	relational data base management system
RPC	remote procedure call
RRDB	recommended requirements database
SCF	Science Computing Facility
SDP	science data production
SDPF	science data processing facility
SGI	Silicon Graphics Incorporated
SMF	status message file
SMP	Symmetric Multi–Processing
SOM	Space Oblique Mercator
SPSO	Science Processing Support Office
SSM/I	Special Sensor for Microwave/Imaging
SW	swath
TAI	International Atomic Time
TBD	to be determined
TDRSS	Tracking and Data Relay Satellite System
TRMM	Tropical Rainfall Measuring Mission (joint US – Japan)
UARS	Upper Atmosphere Research Satellite
UCAR	University Corporation for Atmospheric Research
URL	universal reference locator
USNO	United States Naval Observatory
UT	universal time

UTC	Coordinated Universal Time
UTCF	universal time correlation factor
UTM	universal transverse mercator
VPF	vector product format
WWW	World Wide Web