Radiation Response Worker Exposure Guidelines 1-2-3

Total Effective Dose Equivalent (TEDE) Guideline	Activity	Condition
5 <u>rem</u>	All occupational exposures	 Dose limit to emergency workers: 5 rem Use all reasonable measures to minimize dose For most <u>Radiological Dispersal Devices</u>, radiation control measures will maintain exposures below 5 rem Some rescues may involve exposures > 5 rem When 5 rem limit is exceeded, worker monitoring must be made available and volunteers for such activities should be made fully aware of the risks
10 rem	Protecting valuable property necessary for public welfare (e.g., a power plant)	 Exposures to emergency workers protecting valuable property necessary for public welfare may exceed 5 rem Use all reasonable measures to minimize dose When 5 rem limit is exceeded, worker monitoring must be made available and volunteers for such activities should be made fully aware of the risks For potential doses > 10 rem, special medical monitoring programs should be enployed, and exposure should be tracked in terms of the unit of absorbed dose (<u>rad</u>) rather than TEDE (rem).
25 rem	Lifesaving or protection of large populations	 During large incidents (e.g., <u>Improvised Nuclear Devices</u>) exposures to emergency workers may exceed 5 rem Emergency response activities may include: lifesaving, protection of large populations, prevention of mass spread of destruction Use all reasonable measures to minimize dose When 5 rem limit is exceeded, worker monitoring must be made available and volunteers for such activities should be made fully aware of the risks For potential doses > 10 rem, special medical monitoring programs should be employed, and exposure should be tracked in terms of the unit of absorbed dose (<u>rad</u>) rather than TEDE (rem).

¹ Adapted from <u>Protective Action Guides for Radiological Dispersal Device (RDD) and Improvised Nuclear Device (IND) Incidents</u> (PDF - 481 KB), (DHS/FEMA draft document, published in Federal Register January 3, 2006, Z-RIN 1660-ZA02)

- Made by on-scene Incident Commander during incident when exceeding 5 rem is unavoidable
- Reflect actual incident circumstances/worker activity (e.g., need to save lives or critical infrastructure)
- Require informed consent from responding worker
- 3 Decision points for restricting response workers' activities have been recommended by various other agencies.

Agency	Summary Information	Original Document
National Council on Radiation Protection and Measurement (NCRP)	NCRP Radiation Protection Guidelines: Control of Radiation Dose in the Control Zones	Key Elements of Preparing Emergency Responders for Nuclear and Radiological Terrorism (NCRP Commentary No. 19, December 2005, page 19, purchase required; see Free Overview (PDF - 219 KB))
3,		Manual for First Responders to a Radiological Emergency (PDF - 2.2 MB) (CTIF, IAEA, PAHO, WHO, October 2006, page 41)
Conference of Radiation Control Program Directors, Inc. (CRCPD)	Dose Guidelines	Handbook for Responding to a Radiological Dispersal Device (Dirty Bomb): First Responder's Guide: The First 12 Hours (CRCPD Publication 06-6), page 28. Conference of Radiation Control Program Directors, Inc. Frankfort, Kentucky, 2006.
		<u>Protecting People Against Radiation Exposure in the Event of a Radiological Attack</u> (International Commission on Radiological Protection, ICRP Publication 96, 2005, page 51)



² Emergency response decisions resulting in worker exposure doses greater than 5 rem