

D.3.5 Description of Essential Fish Habitat for Alaska Stocks of Pacific Salmon

D.3.5.1 EFH Information Levels for Alaska Stocks of Pacific Salmon

Salmon Species	Freshwater Eggs	Freshwater Larvae and Juveniles	Estuarine Juveniles	Marine Juveniles	Marine Immature and Maturing Adults	Freshwater Adults
Pink	1	1	1	1	1	1
Chum	1	1	1	1	1	1
Sockeye	1	1	1	1	1	1
Chinook	1	1	1	1	1	1
Coho	1	1	1	1	1	1

D.3.5.2 EFH Text Descriptions for Alaska Stocks of Pacific Salmon

EFH Description for Pink Salmon

Freshwater Eggs

EFH for pink salmon eggs is the general distribution area for this life stage, located in gravel substrates in those waters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a), as depicted in Figures D-156 through D-161.

Freshwater Larvae and Juveniles

EFH for larval and juvenile pink salmon is the general distribution area for this life stage, located in those waters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a) and contiguous rearing areas within the boundaries of ordinary high water during the spring, generally migrate in darkness in the upper water column. Fry leave streams in within 15 days and the duration of migration from a stream towards sea may last 2 months, as depicted in Figures D-156 through D-161.

Estuarine Juveniles

Estuarine EFH for juvenile pink salmon is the general distribution area for this life stage, located in estuarine areas, as identified by the salinity transition zone (ecotone) and the mean higher tide line, within nearshore waters and generally present from late April through June, as depicted in Figures D-156 through D-161.

Marine Juveniles

Marine EFH for juvenile pink salmon is the general distribution area for this life stage, located in all marine waters off the coast of Alaska from the mean higher tide line to the 200-nautical mile (nm) limit of the U.S. EEZ, including the GOA, EBS, Chukchi Sea, and Arctic Ocean, as depicted in Figure D-162.

Marine Immature and Maturing Adults

EFH for immature and maturing adult pink salmon is the general distribution area for this life stage, located in marine waters off the coast of Alaska to depths of 200 m and range from the mean higher tide line to the 200-nm limit of the U.S. EEZ, including the GOA, EBS, Chukchi Sea, and Arctic Ocean.

Mature adult pink salmon frequently spawn in intertidal areas and are known to associate with smaller coastal streams, as depicted in Figure D-162.

Freshwater Adults

EFH for pink salmon is the general distribution area for this life stage, located in freshwaters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a) and wherever there are spawning substrates consisting of medium to coarse gravel containing less than 15 percent fine sediment (less than 2-mm diameter), 15 to 50 cm in depth from June through September, as depicted in Figures D-156 through D-161.

EFH Description for Chum Salmon

Freshwater Eggs

EFH for chum salmon eggs is the general distribution area for this life stage, located in gravel substrates in those waters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a), as depicted in Figures D-163 through D-168.

Freshwater Larvae and Juveniles

EFH for larval and juvenile chum salmon is the general distribution area for this life stage, located in those waters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a) and contiguous rearing areas within the boundaries of ordinary high water and contiguous rearing areas within the boundaries of ordinary high water during the spring, generally migrate in darkness in the upper water column. Fry leave streams in within 15 days and the duration of migration from a stream towards sea may last 2 months, as depicted in Figures D-163 through D-168.

Estuarine Juveniles

Estuarine EFH for juvenile chum salmon is the general distribution area for this life stage, located in estuarine areas, as identified by the salinity transition zone (ecotone) and the mean higher tide line, within nearshore waters from late April through June, as depicted in Figures D-163 through D-168.

Marine Juveniles

Marine EFH for juvenile chum salmon is the general distribution area for this life stage, located in all marine waters off the coast of Alaska to approximately 50 m in depth from the mean higher tide line to the 200-nm limit of the EEZ, including the GOA, EBS, Chukchi Sea, and Arctic Ocean, as depicted in Figure D-169.

Marine Immature and Maturing Adults

EFH for immature and maturing adult chum salmon is the general distribution area for this life stage, located in marine waters off the coast of Alaska to depths of 200 m and ranging from the mean higher tide line to the 200-nm limit of the EEZ, including the GOA, EBS, Chukchi Sea, and Arctic Ocean, as depicted in Figure D-169.

Freshwater Adults

EFH for chum salmon is the general distribution area for this life stage, located in freshwaters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a) and wherever there are spawning substrates consisting of medium to coarse gravel containing less than 15 percent fine sediment (less than 2-mm diameter) and finer substrates can be used in upwelling areas of streams and sloughs from June through January, as depicted in Figures D-163 through D-168.

EFH Description for Sockeye Salmon

Freshwater Eggs

EFH for sockeye salmon eggs is the general distribution area for this life stage, located in gravel substrates in those waters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a), as depicted in Figures D-170 through D-175.

Freshwater Larvae and Juveniles

EFH for larval and juvenile sockeye salmon is the general distribution area for this life stage, located in those waters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a) and contiguous rearing areas within the boundaries of ordinary high water. Juvenile sockeye salmon require year-round rearing habitat. Fry generally migrate downstream to a lake or, in systems lacking a freshwater lake, to estuarine and riverine rearing areas for up to 2 years. Fry out migration occurs from approximately April to November and smolts generally migrate during the spring and summer, as depicted in Figures D-170 through D-175.

Estuarine Juveniles

Estuarine EFH for juvenile sockeye salmon is the general distribution area for this life stage, located in estuarine areas, as identified by the salinity transition zone (ecotone) and the mean higher tide line, within nearshore waters. Under-yearling, yearling, and older smolts occupy estuaries from March through early August, as depicted in Figures D-170 through D-175.

Marine Juveniles

Marine EFH for juvenile sockeye salmon is the general distribution area for this life stage, located in all marine waters off the coast of Alaska to depths of 50 m and range from the mean higher tide line to the 200-nm limit of the U.S. EEZ, including the GOA, EBS, Chukchi Sea, and Arctic Ocean from mid-summer until December of their first year at sea, as depicted in Figure D-176.

Marine Immature and Maturing Adults

EFH for immature and maturing adult sockeye salmon is the general distribution area for this life stage, located in marine waters off the coast of Alaska to depths of 200 m and range from the mean higher tide line to the 200-nm limit of the U.S. EEZ, including the GOA, EBS, Chukchi Sea, and Arctic Ocean, as depicted in Figure D-176.

Freshwater Adults

EFH for sockeye salmon is the general distribution area for this life stage, located in freshwaters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a) and wherever there are spawning substrates consisting of medium to coarse gravel containing less than 15 percent fine sediment (less than 2-mm diam.) and finer substrates can be used in upwelling areas of streams and sloughs from June through September. Sockeye often spawn in lake substrates, as well as in streams, as depicted in Figures D-170 through D-175.

EFH Description for Chinook Salmon

Freshwater Eggs

EFH for Chinook salmon eggs is the general distribution for this life stage, located in gravel substrates in those waters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a) (see Figures D-177 through D-182).

Freshwater Larvae and Juveniles

EFH for larval and juvenile Chinook salmon is the general distribution area for this life stage, located in those waters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a) and contiguous rearing areas within the boundaries of ordinary high water. Juvenile Chinook salmon out-migrate from freshwater areas in April toward the sea and may spend up to a year in a major tributaries or rivers, such as the Kenai, Yukon, Taku, and Copper Rivers (see Figures D-177 through D-182).

Estuarine Juveniles

Estuarine EFH for juvenile Chinook salmon is the general distribution area for this life stage, located in estuarine areas, as identified by the salinity transition zone (ecotone) and the mean higher tide line, within nearshore waters. Chinook salmon smolts and post-smolt juveniles may be present in these estuarine habitats from April through September (see Figures D-177 through D-182).

Marine Juveniles

Marine EFH for juvenile Chinook salmon is the general distribution area for this life stage, located in all marine waters off the coast of Alaska from the mean higher tide line to the 200-nm limit of the EEZ, including the GOA, EBS, Chukchi Sea, and Arctic Ocean. Juvenile marine Chinook salmon are at this life stage from April until annulus formation in January or February during their first winter at sea (see Figure D-183).

Marine Immature and Maturing Adults

EFH for immature and maturing adult Chinook salmon is the general distribution area for this life stage, located in marine waters off the coast of Alaska and ranging from the mean higher tide line to the 200-nm limit of the U.S. EEZ, including the GOA, EBS, Chukchi Sea, and Arctic Ocean (see Figure D-183).

Freshwater Adults

EFH for adult Chinook salmon is the general distribution area for this life stage, located in fresh waters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a) wherever there are spawning substrates consisting of gravels from April through September (see Figures D-177 through D-182).

EFH Description for Coho Salmon

Freshwater Eggs

EFH for coho salmon eggs is the general distribution area for this life stage, located in gravel substrates in those waters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a), as depicted in Figures D-184 through D-189.

Freshwater Larvae and Juveniles

EFH for larval and juvenile coho salmon is the general distribution area for this life stage, located in those waters identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a) and contiguous rearing areas within the boundaries of ordinary high water. Fry generally migrate to a lake, slough, or estuary and rear in these areas for up to 2 years, as depicted in Figures D-184 through D-189.

Estuarine Juveniles

Estuarine EFH for juvenile coho salmon is the general distribution area for this life stage, located in estuarine areas, as identified by the salinity transition zone (ecotone) and the mean higher tide line,

within nearshore waters. Juvenile coho salmon require year-round rearing habitat and also migration habitat from April to November to provide access to and from the estuary.

Marine Juveniles

Marine EFH for juvenile coho salmon is the general distribution area for this life stage, located in all marine waters off the coast of Alaska from the mean higher tide line to the 200-nm limit of the U.S. EEZ, including the GOA, EBS, Chukchi Sea, and Arctic Ocean, as depicted in Figure D-190.

Marine Immature and Maturing Adults

EFH for immature and maturing adult coho salmon is the general distribution area for this life stage, located in marine waters off the coast of Alaska to 200 m in depth and range from the mean higher tide line to the 200-nm limit of the U.S. EEZ, including the GOA, EBS, Chukchi Sea, and Arctic Ocean, as depicted in Figure D-190.

Freshwater Adults

EFH for coho salmon is the general distribution area for this life stage, located in freshwaters as identified in ADF&G's *Catalogue of Waters Important for the Spawning, Rearing, or Migration of Anadromous Fishes* (ADF&G 1998a) and wherever there are spawning substrates consisting mainly of gravel containing less than 15 percent fine sediment (less than 2-mm diameter) from July to December, as depicted in Figures D-184 through D-189.

D.3.5.3 EFH Map Descriptions for Alaska Stocks of Pacific Salmon

Figures D-155 through D-190 show EFH distribution under Alternative 3 by region for the Alaska stocks of Pacific salmon as described in Section D.3.5.2.