

Detection of Ki-67 (MIB-1) in Formalin-Fixed, Paraffin-Embedded Human Tissue

Reagent and Antibody Information

[1X Wash Buffer](#)

[3% Hydrogen Peroxide](#)

[1% BSA Diluent](#)

[1X Citrate Buffer](#)

[DAB Chromagen](#)

[Hematoxylin](#)

Staining Kit: Vectastain Elite ABC Kit (Mouse IgG)

Vector Laboratories, Inc.

Burlingame, CA 94010

www.vectorlabs.com

1-800-227-6666

Catalog # PK-6102

Note: This kit contains all reagents necessary to make the blocking solution and secondary antibody.

Avidin / Biotin Blocking Kit

Vector Laboratories, Inc.

Burlingame, CA 94010

www.vectorlabs.com

1-800-227-6666

Catalog # SP-2001

Primary Antibody: Monoclonal Mouse Anti-Human Ki-67 Antibody (MIB-1)

Dakocytomation Corporation

Carpinteria CA 93013

www.dakousa.com

1-800-235-5763

Code No. M7240

Negative Control Serum: Purified Mouse IgG1 Isotype Control Serum

BD Biosciences

San Jose, CA 95131

www.bdpharma.com

1-877-232-8995

Catalog # 557273

Staining Procedure

Positive Control Tissue: Breast carcinoma
Stain Localization: Nuclear

1. Deparaffinize and hydrate slides through the following solutions:

Solution	Repetitions	Time
Xylene	2 times	5 minutes
100% Ethanol	2 times	3 minutes
95% Ethanol	2 times	3 minutes
1X Wash Buffer	2 times	5 minutes

2. Quench endogenous peroxidase by placing the slides in 3% hydrogen peroxide for 15 minutes.
3. Rinse the slides in 2 changes of 1X Wash Buffer for 5 minutes each.

4. Heat-Induced Epitope Retrieval Using The Decloaker

Add 500 ml of distilled water to the pan inside the decloaker.

Place a full rack of slides into a Tissue Tek® container with 200 ml of 1X citrate buffer

(Insert blank slides into any empty slots in the rack to ensure even heating of slides)

Place the container stably inside the pan and decloak for 5 minutes. *Maximum Pressure* _____

Depressurize for 10 minutes.

Remove pan top and cool for 10 minutes. *Temperature Before Cooling Slides* _____

Rinse the slides in 2 changes of distilled water for 3 minutes each time.

5. Rinse slides in 2 changes of 1X Wash Buffer for 5 minutes each.

Vectastain Mouse Elite Staining Kit

Exp Date _____ New Kit: yes / no

6. Apply the block from the Mouse Elite Kit, and incubate for 20 minutes at room temperature.

DO NOT RINSE SLIDES. CONTINUE TO AVIDIN-BIOTIN BLOCK.

7. Avidin / Biotin Blocking Kit

Lot # _____ Exp. Date _____ New Kit: yes / no

Apply avidin block for 15 minutes at room temperature.

Quick rinse in 1X Wash Buffer.

Apply biotin block for 15 minutes at room temperature.

DO NOT RINSE SLIDES WITH BUFFER BEFORE ADDING PRIMARY ANTIBODY.
ONLY WIPE EXCESS BUFFER.

8. Apply primary antibody at a 1:100 dilution, and incubate for 1 hour at room temperature.

Lot # _____ Exp Date _____

For negative control slides, dilute the protein concentration of the normal mouse serum to match that of the primary antibody. Make a 1:100 dilution from this normalized serum, and apply to the slides. Incubate for 1 hour at room temperature.

Lot # _____ Date Reconstituted _____

9. Rinse the slides in 2 changes of 1X Wash Buffer for 5 minutes each.
10. Apply the secondary antibody from Mouse Elite Kit, and incubate for 30 minutes at room temperature.
11. Rinse the slides in 2 changes of 1X Wash Buffer for 5 minutes each.
12. Apply the label complex from the Mouse Elite Kit, and incubate for 30 minutes at room temperature. (Prepare at least 30 minutes prior to use.)
13. Rinse the slides in 2 changes of 1X Wash Buffer for 5 minutes each.
14. Apply the DAB chromagen and incubate in the dark for 6 minutes at room temperature. (Add 1 drop of DAB per ml of substrate)
Lot # _____ Exp Date _____ New Kit: yes / no
15. Rinse the slides in tap water 3 minutes.
16. Counterstain with Harris Hematoxylin for 20 seconds.
17. Rinse the slides in tap water until water is clear.
18. Gently agitate slides in 1X Wash Buffer until they turn blue.
19. Dehydrate through the following solutions:

Solutions	Repetitions	Time
95% Ethanol	1 time	3 minutes
100% Ethanol	3 times	3 minutes
Xylene	2 times	5 minutes

20. Coverslip

Updated 06/03/08