Author: L. Jones

### Internet/Email Access from TWP Facilities and AMF Site

### I. Purpose:

This document provides instructions on how to access the internet/email from TWP facilities.

### II. Cautions and Hazards

Before hooking up your computer, make sure it has virus protection software, and the virus signatures are up to date (Note: It should be checked before leaving for TWP facilities or AMF site). When you access the Internet, you are putting the entire facility at risk to infection.

### **III.** Requirements:

None

#### IV. Procedure:

### A. Accessing Internet/Email from TWP Facilities and AMF Site

- 1. In the D-Van, plug in the communications line available from the right wall it comes from the DS rack on the other side of the transportainer.
- 2. Right-click on "My Network Places," and then go to "Properties." (Note: You can also go directly to "View Network Connects."
- 3. Right-click on "Local Area Connection," and then select "Properties."
- 4. Go to bottom of list in table, highlight "Internet Protocol (TCP/IP)," and then click on "Properties."
- 5. Carefully write down the default IP address information on your computer so you can reconfigure your computer when you leave the facility for home or your next destination.
- 6. Enter IP addresses for the TWP facility or the AMF site at which you are (see addresses below).
- 7. Once entered, click on "OK" or "Close" it now has the IP address for the facility or the site at which you are.
- 8. For LANL personnel, click on VPN and connect, and you should be ready for internet browsing and e-mailing (VPN is needed for e-mail but not for the Internet).

Author: L. Jones

# B. Verifying Correct IP Address

 To verify that you have the correct IP address, go to Start > Program > Accessories > Command prompts, and then type "ipconfig" and hit "Enter." The correct IP addresses show up.

### V. References:

None.

### VI. Attachments:

1. IP Address List

Author: L. Jones

### Attachment 1: IP Address List

<u> Manus</u>
---------------

IP address:	198.252.143.243	(243 – 247 available)
Subnet mask:	255.255.255.240	
Default gateway:	198.252.143.241	
Preferred DNS server:	192.148.93.23	(same worldwide)
Alternate DNS server:	134.178.6.5	(same worldwide)
<u>Nauru</u>		
IP address:	198.129.81.243	(243 – 247 available)
Subnet mask:	255.255.255.240	
Default gateway:	198.129.81.1	
Preferred DNS server:	192.148.93.23	(same worldwide)
Alternate DNS server:	134.178.6.5	(same worldwide)
<u>Darwin</u>		
ID addroce:	102 169 0 0	(0, 13) available)

IF audress.	192.100.0.9	(9 – 15 avaliable)
Subnet mask:	255.255.255.224	
Default gateway:	192.168.0.1	
Preferred DNS server:	192.148.93.23	(same worldwide)
Alternate DNS server:	134.178.6.5	(same worldwide)

## AMF Niger

IP address:	193.220.181.147 (1	47 – MA; 148, 149 – guest; 150 – VOIP)
Subnet mask:	255.255.255.248	
Default gateway:	193.220.181.145	
Preferred DNS server:	130.202.101.6	(same worldwide)
Alternate DNS server:	134.178.6.5	(same worldwide)