

Please Note: Prior to the SAF installation please Contact you IT Department to perform the install of the Microsoft Active X Data Objects Library. You MUST have Administrative Privileges for the installation.

Directions:

If Microsoft Access is using version [Microsoft ActiveX Data Objects 2.1 Library](#) you MUST download the latest version [Microsoft ActiveX Data Objects 2.8 Library from Microsoft](#) for the install of the SAF to work properly.

**Here is the instructions for installing the SAF to your PC.
Make sure you have Administrative rights on your PC prior to beginning the installation, otherwise it will not work.**

- 1. Create a folder on your C:\Drive called C:\NIOSH.**
- 2. Once this is created download the zip file and store the file in the NIOSH folder you just created.**
- 3. Open the folder and you will see the Setup.zip file, right click and select Extract all. Click next and on the following screen browse to the C:\NIOSH Folder.**
- 4. Click Next, and the screen should say Show Extracted Files.**
- 5. Click Finish, and close any windows that are open. (At this point the file resides on your PC.)**
- 6. Click Start, Run, then the Browse Button. Click my computer, local disk C:\, NIOSH Folder, then the Files Folder. At the bottom of the same screen where it says Files of Type - Programs, select the drop down arrow to the right and select All Files**
- 7. Select the saf_v7.msi now listed in the screen, highlight and click the Open button, then the OK Button. The installation should then begin at this point.**