PNRPDF Auxillary

# **PNRPDF**

#### **PURPOSE**

Compute the standard power-normal probability density function.

## **DESCRIPTION**

The standard power-normal distribution has the following probability density function:

$$f(x,\sigma,p) = \left(\frac{p}{x\sigma}\right) \phi\left(\frac{x}{\sigma}\right) \left(\Phi\left(\frac{-x}{\sigma}\right)\right)^{p-1} \qquad x > 0, \, \sigma > 0, \, p > 0$$
 (EQ Aux-274)

where  $\sigma$  is the shape parameter, p is the power parameter, and  $\Phi$  and  $\phi$  are the cumulative distribution function and the probability density function for the standard normal distribution respectively.

If p is 1, this distribution reduces to the normal distribution.

## **SYNTAX**

LET < y2 > = PNRPDF(< y1 >, , < s >) < SUBSET/EXCEPT/FOR qualification >

where <y1> is a non-negative number, parameter, or variable;

is a positive number, parameter, or variable that specifies the power parameter;

<s> is an optional positive number, parameter, or variable that specifies the shape parameter;

<y2> is a variable or a parameter (depending on what <y1> is) where the computed power-normal pdf value is stored; and where the <SUBSET/EXCEPT/FOR qualification> is optional.

If the <s> parameter is omitted, it defaults to 1.

## **EXAMPLES**

LET A = PNRPDF(3,2,1)

LET X2 = PNRPDF(X1,POW,SD)

LET X2 = PNRPDF(X1,1,0.5)

## NOTE

The general power-normal distribution has the following probability density function:

$$f(x, \mu, \sigma, p) = \left(\frac{p}{x\sigma}\right) \phi \left(\frac{(x-\mu)}{\sigma}\right) \left(\Phi\left(\frac{-(x-\mu)}{\sigma}\right)\right)^{p-1} \qquad x > 0, \ \sigma > 0, \ p > 0$$
 (EQ Aux-275)

where  $\mu$  is the location parameter,  $\sigma$  is the shape parameter and p is the power parameter.

#### **DEFAULT**

None

#### **SYNONYMS**

None

### **RELATED COMMANDS**

NORPPF

PNRCDF = Compute the power-normal cumulative distribution function.

PNRPPF = Compute the power-normal percent point function.

**PLNCDF** Compute the power-lognormal cumulative distribution function. **PLNPDF** Compute the power-lognormal probability density function. **PLNPPF** Compute the power-lognormal percent point function. **LGNCDF** Compute the lognormal cumulative distribution function. **LGNPDF** Compute the lognormal probability density function. **LGNPPF** Compute the lognormal percent point function. **NORCDF** Compute the normal cumulative distribution function. **NORPDF** Compute the normal probability density function.

Compute the normal percent point function.

Auxillary PNRPDF

## **REFERENCE**

"A Computer Program POWNOR for Fitting the Power-Normal and -Lognormal Models to Life or Strength Data from Specimens of Various Sizes," Nelson and Doganaksoy, NIST-IR 4760, March 1992.

# **APPLICATIONS**

Reliability

## IMPLEMENTATION DATE

95/5

## **PROGRAM**

XILABEL CDF'S
YLIMITS 0 1
MAJOR YTIC MARK NUMBER 6
TITLE SD=1, P=10000, 3000, 1000, 300, 100, 50, 20, 5, 1, 0.5, 0.2 0.1
TITLE SIZE 2

. PLOT PNRPDF(X,10000,1) FOR X = -5 .05 5 AND PLOT PNRPDF(X,3000,1) FOR X = -5 .05 5 AND PLOT PNRPDF(X,1000,1) FOR X = -5 .05 5 AND PLOT PNRPDF(X,300,1) FOR X = -5 .05 5 AND PLOT PNRPDF(X,100,1) FOR X = -5 .05 5 AND PLOT PNRPDF(X,100,1) FOR X = -5 .05 5 AND

PLOT PNRPDF(X,50,1) FOR X = -5.055 AND PLOT PNRPDF(X,20,1) FOR X = -5.055 AND

PLOT PNRPDF(X,5,1) FOR X = -5.055 AND

PLOT PNRPDF(X,1,1) FOR X = -5.055 AND

PLOT PNRPDF(X,0.5,1) FOR X = -5.055 AND

PLOT PNRPDF(X,0.2,1) FOR X = -5.055 AND

PLOT PNRPDF(X,0.1,1) FOR X = -5.05.5

