mT0R **Antibody**

√ 100 ul (10 Western mini-blots)



Orders 877-616-CELL (2355)

orders@cellsignal.com

Support 877-678-TECH (8324)

info@cellsignal.com

Web www.cellsignal.com

rev. 06/12/07

This product is for in vitro research use only and is not intended for use in humans or animals.

Applications	Species Cross-Reactivity	Molecular Wt.	Source	
W, IP	H, M, R, Mk	289 kDa	Rabbit	

Background: The mammalian target of rapamycin, mTOR, also know as FRAP or RAFT (1-3), is a Ser/Thr protein kinase. mTOR acts as a sensor for ATP and amino acids, balancing the availability of nutrients and cell growth (4,5). When sufficient nutrients are available, mTOR responds to a phosphatidic acid-mediated signal (6), transmits a positive signal to p70 S6 kinase and participates in the inactivation of the eIF4E inhibitor, 4E-BP1. These events result in the translation of specific mRNA subpopulations. mTOR is phosphorylated at Ser2448 via the PI3 kinase/Akt signaling pathway and autophosphorylated at Ser2481 (7,8). mTOR plays a key role in cellular growth and homeostasis and its regulation is frequently altered in tumors. For these reasons, mTOR is currently under investigation as a potential target for anti-cancer therapy (9).

Specificity/Sensitivity: mTOR Antibody detects endogenous levels of total mTOR. It cross-reacts weakly with some other proteins based on Western analysis.


Source/Purification: Polyclonal antibodies are produced by immunizing rabbits with a synthetic peptide (KLH-coupled) corresponding to residues surrounding Ser2481 of human mTOR. Antibodies are purified by protein A and peptide affinity chromatography.

Selected Application References:

Suzuki, A. et al. (2004) ARK5 is a tumor invasion-associated factor downstream of Akt signaling. Mol. Cell. Biol. 24. 3526-3535. Application: W.

Background References:

- (1) Sabers, C.J. et al. (1995) J. Biol. Chem. 270, 815-822.
- (2) Brown, E.J. et al. (1994) Nature 369, 756-758.
- (3) Sabatini, D.M. et al. (1994) Cell 78, 35-43.
- (4) Gingras, A.C. et al. (2001) Genes Dev. 15, 807-826.
- (5) Dennis, P.B. et al. (2001) Science 294, 1102-1105.
- (6) Fang, Y. et al. (2001) Science 294, 1942-1945.
- (7) Navé, B.T. et al. (1999) Biochem. J. 344 Pt 2, 427-431.
- (8) Peterson, R.T. et al. (2000) J. Biol. Chem. 275, 7416-7423.
- (9) Huang, S. and Houghton, P.J. (2003) Curr. Opin. Pharmacol. 3, 371-377.



Western blot analysis of extracts from 293 cells (starved for 16 hours), untreated or EGF-treated (100 ng/ml), using Phospho-mTOR (Ser2448) antibody #2971 (upper) or mTOR Antibody (lower).

76

Storage: Supplied in 10 mM sodium HEPES (pH 7.5), 150 mM NaCl, 100 µg/ml BSA and 50% glycerol. Store at -20°C. Do not aliquot the antibody.

Recommended Antibody Dilutions:

Western Blotting Immunoprecipitation 1:100

Companion Products:

Phospho-elF4G (Ser1108) Antibody #2441

Phospho-mTOR (Ser2448) Antibody #2971

Phospho-mTOR (Ser2481) Antibody #2974

Phospho-p70 S6 Kinase (Thr389) Antibody #9205

Phospho-4E-BP1 (Ser65) Antibody #9451

Phospho-S6 Ribosomal Protein (Ser235/236) Antibody #2211

Rapamycin (FRAP/mTOR Inhibitor) #9904

Phototope®-HRP Western Blot Detection System, Anti-rabbit IgG, HRP-linked Antibody #7071

Anti-rabbit IgG, HRP-linked Antibody #7074

Prestained Protein Marker, Broad Range (Premixed Format)

Biotinylated Protein Ladder Detection Pack #7727 20X LumiGLO® Reagent and 20X Peroxide #7003

IMPORTANT: For Western blots, incubate membrane with diluted antibody in 5% w/v BSA, 1X TBS, 0.1% Tween-20 at 4°C with gentle shaking, overnight.

W—Western IP—Immunoprecipitation IHC—Immunohistochemistry IC—Immunocytochemistry

IF-Immunofluorescence

Applications Kev:



Western Immunoblotting Protocol (Primary Ab Incubation In BSA)

For Western blots, incubate membrane with diluted antibody in 5% w/v BSA, 1X TBS, 0.1% Tween-20 at 4°C with gentle shaking, overnight.

A Solutions and Reagents

NOTE: Prepare solutions with Milli-Q or equivalently purified water.

- 1. 1X Phosphate Buffered Saline (PBS)
- 1X SDS Sample Buffer: 62.5 mM Tris-HCI (pH 6.8 at 25°C), 2% w/v SDS, 10% glycerol, 50 mM DTT, 0.01% w/v bromophenol blue or phenol red
- 3. Transfer Buffer: 25 mM Tris base, 0.2 M glycine, 20% methanol (pH 8.5)
- 10X Tris Buffered Saline (TBS): To prepare 1 liter of 10X TBS: 24.2 g Tris base, 80 g NaCl; adjust pH to 7.6 with HCl (use at 1X).
- **5.** Nonfat Dry Milk (weight to volume [w/v])
- Blocking Buffer: 1X TBS, 0.1% Tween-20 with 5% w/v nonfat dry milk; for 150 ml, add 15 ml 10X TBS to 135 ml water, mix. Add 7.5 g nonfat dry milk and mix well. While stirring, add 0.15 ml Tween-20 (100%).
- 7. Wash Buffer: 1X TBS, 0.1% Tween-20 (TBS/T)
- 8. Bovine Serum Albumin (BSA)
- Primary Antibody Dilution Buffer: 1X TBS, 0.1% Tween-20 with 5% BSA; for 20 ml, add 2 ml 10X TBS to 18 ml water, mix. Add 1.0 g BSA and mix well. While stirring, add 20 µl Tween-20 (100%).
- 10. Phototope®-HRP Western Blot Detection System #7071: Includes biotinylated protein ladder, secondary anti-rabbit (#7074) antibody conjugated to horseradish peroxidase (HRP), anti-biotin antibody conjugated to HRP, LumiGLO® chemiluminescent reagent and peroxide.
- 11. Prestained Protein Marker, Broad Range (Premixed Format) #7720
- **12.** Biotinylated Protein Ladder Detection Pack #7727
- Blotting Membrane: This protocol has been optimized for nitrocellulose membranes, which CST recommends. PVDF membranes may also be used.

B Protein Blotting

A general protocol for sample preparation is described below.

- 1. Treat cells by adding fresh media containing regulator for desired time.
- 2. Aspirate media from cultures; wash cells with 1X PBS; aspirate.
- 3. Lyse cells by adding 1X SDS sample buffer (100 µl per well of 6-well plate or 500 µl per plate of 10 cm diameter plate). Immediately scrape the cells off the plate and transfer the extract to a microcentrifuge tube. Keep on ice.
- 4. Sonicate for 10–15 seconds to shear DNA and reduce sample viscosity.
- **5.** Heat a 20 μ l sample to 95–100°C for 5 minutes; cool on ice.
- **6.** Microcentrifuge for 5 minutes.
- 7. Load 20 µl onto SDS-PAGE gel (10 cm x 10 cm).

NOTE: CST recommends loading prestained molecular weight markers (#7720, 10 μ I/lane) to verify electrotransfer and biotinylated protein ladder (#7727, 10 μ I/lane) to determine molecular weights.

8. Electrotransfer to nitrocellulose or PVDF membrane.

C Membrane Blocking and Antibody Incubations

NOTE: Volumes are for 10 cm x 10 cm (100 cm²) of membrane; for different sized membranes, adjust volumes accordingly.

- (Optional) After transfer, wash nitrocellulose membrane with 25 ml TBS for 5 minutes at room temperature.
- 2. Incubate membrane in 25 ml of blocking buffer for 1 hour at room temperature.
- Wash three times for 5 minutes each with 15 ml of TBS/T.
- Incubate membrane and primary antibody (at the appropriate dilution) in 10 ml primary antibody dilution buffer with gentle agitation <u>overnight</u> at 4°C.
- 5. Wash three times for 5 minutes each with 15 ml of TBS/T.
- 6. Incubate membrane with HRP-conjugated secondary antibody (1:2000) and HRP-conjugated anti-biotin antibody (1:1000) to detect biotinylated protein markers in 10 ml of blocking buffer with gentle agitation for 1 hour at room temperature.
- 7. Wash three times for 5 minutes each with 15 ml of TBS/T.

D Detection of Proteins

 Incubate membrane with 10 ml LumiGL0® (0.5 ml 20X LumiGL0®, 0.5 ml 20X Peroxide and 9.0 ml Milli-Q water) with gentle agitation for 1 minute at room temperature.

NOTE: LumiGLO® substrate can be further diluted if signal response is too fast.

Drain membrane of excess developing solution (do not let dry), wrap in plastic wrap and expose to x-ray film. An initial 10-second exposure should indicate the proper exposure time.

NOTE: Due to the kinetics of the detection reaction, signal is most intense immediately following LumiGLO® incubation and declines over the following 2 hours.



Immunoprecipitation Protocol / (For Analysis By Western Immunoblotting)

A Solutions and Reagents

NOTE: Prepare solutions with Milli-Q or equivalently purified water.

- 1. 1X Phosphate Buffered Saline (PBS)
- 1X Cell Lysis Buffer: 20 mM Tris (pH 7.5), 150 mM NaCl, 1 mM EDTA, 1 mM EGTA, 1% Triton X-100, 2.5 mM Sodium pyrophosphate, 1 mM β-glycerophosphate, 1 mM Na,VO,, 1 μg/ml Leupeptin

NOTE: CST recommends adding 1 mM PMSF before use*.

- **3. Transfer Buffer:** 25 mM Tris base, 0.2 mM glycine, 20% methanol (pH 8.5)
- 4. Protein A or G Agarose Beads: (Can be stored for 2 weeks at 4°C.) Please prepare according to manufacturer's instructions. Use Protein A for rabbit IgG pull down and Protein G for mouse IgG pull down.
- 3X SDS Sample Buffer: 187.5 mM Tris-HCI (pH 6.8 at 25°C), 6% w/v SDS, 30% glycerol, 150 mM DTT, 0.03% w/v bromophenol blue

B Preparing Cell Lysates

- Aspirate media. Treat cells by adding fresh media containing regulator for desired time.
- To harvest cells under nondenaturing conditions, remove media and rinse cells once with ice-cold PBS.

- Remove PBS and add 0.5 ml 1X ice-cold cell lysis buffer plus 1 mM PMSF* to each plate (10 cm) and incubate the plates on ice for 5 minutes.
- 4. Scrape cells off the plates and transfer to microcentrifuge tubes. Keep on ice.
- 5. Sonicate samples on ice four times for 5 seconds each.
- Microcentrifuge for 10 minutes at 4°C, and transfer the supernatant to a new tube. If necessary, lysate can be stored at -80°C.

C Immunoprecipitation

- 2. Add either protein A or G agarose beads (20 μ l of 50% bead slurry). Incubate with gentle rocking for 1–3 hours at 4°C.
- Microcentrifuge for 30 seconds at 4°C. Wash pellet five times with 500 µl of 1X cell lysis buffer. Keep on ice during washes.
- Resuspend the pellet with 20 µl 3X SDS sample buffer. Vortex, then microcentrifuge for 30 seconds.
- **5.** Heat the sample to 95–100°C for 2–5 minutes.
- **6.** Load the sample (15–30 μ I) on SDS-PAGE gel (12–15%).
- 7. Analyze sample by Western blotting (see Western Immunoblotting Protocol).