

7

United States
Environmental Protection
Agency

Office of Air Quality
Planning and Standards
Research Triangle Park, NC 27711

EPA-450/4-87-009
May 1987

Air



NETWORK DESIGN AND OPTIMUM SITE EXPOSURE CRITERIA FOR PARTICULATE MATTER



EPA-450/4-87-009
May 1987

Network Design and Optimum Site Exposure Criteria for Particulate Matter

by

R. C. Koch and H. E. Rector
GEOMET Technologies, Inc.
1801 Research Boulevard
Rockville, Maryland 20850

Contract Number 68-02-3584

Project Officer

David Lutz
U.S. Environmental Protection Agency
Research Triangle Park NC 27711

U. S. Environmental Protection Agency
Office of Air Quality Planning and Standards
Research Triangle Park NC 27711

DISCLAIMER

The development of this document has been funded by the United States Environmental Protection Agency under contract 68-02-3584. It has been subject to the Agency's peer and administrative review, and it has been approved for publication as an EPA document.

Mention of trade names or commercial products does not constitute endorsement or recommendation for use.

CONTENTS

Figures	iv
Tables	vi
1. Introduction	1
2. Characteristics of PM ₁₀	3
General Principles	3
Instrumentation	6
Relationship of PM ₁₀ to TSP and Other Measures of Particulate Matter	8
Spatial/Temporal Patterns	9
3. Monitoring Objectives for PM ₁₀	16
Evaluation of Ambient Air Quality	18
Enforcement of Source-Specific Regulations	18
Evaluation/Development of Control Plans	19
Air Quality Maintenance Planning	19
Protection of Public Health	20
Development & Testing of Models	20
Research	20
4. Elements of Site Selection	22
Representative Scales	22
Analysis of the Area to Be Monitored	24
Taxonomy of Representative Sites	41
5. Site Selection Methodology	44
Overview of Methodology	44
Analyze Existing Ambient PM Monitoring Data	47
Review of Local Situation	49
Selection of Monitoring Sites	84
Installation and Followup	87
6. Example Study	89
7. References	101
Appendix	
A. Meteorological data tabulations for CDM program	106

FIGURES

<u>Number</u>		<u>Page</u>
1	Average volume distribution for seven sites in the California ACHEX study in 1972	4
2	Idealized time and coarse particle mass and chemical composition	5
3	Distribution of annual mean IP/TSP ratios	10
4	Distribution of 24-hour IP/TSP ratios	11
5	Seasonal variations in urban, suburban, and rural areas for four size ranges of particles	12
6	Complex processes affecting transport and transformation of airborne particulate matter	15
7	Illustration of various spatial scales of representativeness	23
8	Characteristics of lake coast air flow	33
9	Hourly positions of lake breeze front of August 13, 1967, with the ground track of the NACR Queen air plotted	34
10	Flow zones around a building	35
11	Flow characteristics among multiple buildings	36
12	Idealized urban heat island air flow	36
13	Annual wind roses for U.S. locations	39
14	Planning cycle for monitoring	45
15	Procedure for selecting PM ₁₀ monitoring sites	46
16	Twelve-month running geometric means	50
17	TSP roses for four sites near a coking plant	52
18	Steps for locating regional scale monitoring site	60
19	Steps for locating a neighborhood scale monitoring site in an urban area	61
20	Steps for locating micro-/middle scale monitoring sites in urban areas.	62
21	Steps for locating monitoring sites near isolated major sources	63
22	Average measured daytime PM concentrations from a major Philadelphia highway.	66
23	Example of background site selection within 24 km of City A	68
24	Concentration as a function of wind speed, computed using HIWAY2 model	70
25	Concentration as a function of wind direction, computed using HIWAY2 model	71
26	Concentration as a function of stability class, computed using HIWAY2 model	72
27	Downwind distance to maximum concentration and maximum relative concentration as a function of Pasquill stability class and effective plume height in rural terrain	78

FIGURES (Concluded)

<u>Number</u>		<u>Page</u>
28	Downwind distance to maximum concentration and maximum xu/Q as a function of stability class and effective plume height in urban terrain	79
29	TSP monitoring sites in Baltimore City	91
30	TSP monitoring sites in the Baltimore AQCR, excluding Baltimore City	92
31	Annual mean TSP concentration for 1980	93
32	Annual mean TSP concentration for 1981	94
33	Maximum 24-hour TSP concentration for 1980	96
34	Maximum 24-hour TSP concentration for 1981	97
35	Wind persistence rose for Baltimore-Washington International Airport for 1973-1977	99

TABLES

<u>Number</u>		<u>Page</u>
1	National Estimates of Particulate Emissions	6
2	Summary of National 1979 Particulate Matter Emissions by Source Category.	13
3	Principal Data Uses for PM ₁₀	17
4	Identification and Classification of Land Use Types . . .	26
5	Estimates of the PM ₁₀ Fraction of Total Particulate Matter Emissions for Selected Categories of Process Emissions	28
6	Estimates of the PM ₁₀ Fraction of Total Particulate Matter Emissions for Selected Categories of Uncontrolled Process Fugitive Emissions and Uncontrolled Open Sources	30
7	Estimates of the St. Louis, Missouri, Heat Island Circulation	37
8	Dispersion Classifications	40
9	TSP Data for SAROAD Station #391720001	51
10	Available EPA Models for Six Monitoring Situations . . .	58
11	Distances from Major Point that Affect Regional Scale Monitors	65
12	Maximum Concentrations Near Downwind Edge of Typical Urban Area Sources	73
13	Example Determination of the Number of Neighborhood Monitoring Sites	74
14	Significant Impact Distances of Small Ground-Level Area Sources	75
15	Significant Impact Distances of Highways	75
16	Significant Impact Distances of Elevated Sources	76
17	Sample Work Table for Overlap	83
18	Hi-Vol Measurements of TSP in the Vicinity of Baltimore .	90
19	TSP Emissions by Eight Largest Point Sources in Baltimore City	95
20	Fugitive Emissions Based on 1977 Survey	95

SECTION 1

INTRODUCTION

The primary purpose of this document is to assist in planning a network of monitoring sites for measuring particulate matter. The measurements will conform to the new PM₁₀ standard, which replaces the former TSP standard.¹ As a secondary objective, this document will aid in understanding the relationship between PM₁₀ measurements and the quality of air that is sampled. The information contained here will prove useful to both air quality surveillance personnel and the users of air quality monitoring data. In this document, the siting process is viewed dynamically.

Information received from monitoring sites can be used to feed back into the siting process in order to improve the site selections. The information can also be used to improve air quality simulation models or other analytical tools used in the siting process; however, the process of improving air quality models is not covered in this report.

Monitoring is undertaken to collect needed data. In planning a monitoring network, these data needs must be well defined and understood. This document provides suggestions for helping to identify what these data needs may be. The data needs may change with time as the monitoring results help characterize the local situation and as health effects research clarifies the significant characteristics of air quality exposure. These considerations apply especially to particulate matter, which is made up of highly variable components in space and time.

The major sections of this report treat the following topics:

- Characteristics of PM₁₀
- Monitoring objectives
- Elements of site selection
- Methodology for siting PM₁₀ monitors
- Examples of siting studies.

¹ TSP refers to total suspended particulate matter, and PM₁₀ refers to particulate matter that includes particles in the nominal size range of 10 μ m and smaller aerodynamic diameter.

The principal steps in the siting methodology described in Section 5 include the following:

1. Determine needs for monitoring data
2. Assemble and analyze available particulate matter data
3. Model levels of PM_{10}
4. Determine PM_{10} monitoring network requirements
5. Select location and placement of PM_{10} monitors
6. Document and review site selection.

The appendixes include descriptions of sources of data that may be useful in the site selection process.

SECTION 2

CHARACTERISTICS OF PM₁₀

PM₁₀ is the indicator for the National Ambient Air Quality Standard (NAAQS) particulate matter, which replaces total suspended particulate matter (TSP). "PM₁₀" means particulate matter with an aerodynamic diameter less than or equal to a nominal 10 μm , as measured by the reference method described in Appendix J, 40 CFR 50, and in accordance with 40 CFR 53, or as measured by an equivalent method designated in accordance with 40 CFR 53. In siting monitors for measuring PM₁₀, it is desirable to understand the general principles that govern the generation, transformation, and removal of particulate matter; the basic workings of available instrumentation; and the significant factors that control the spatial and temporal patterns of PM₁₀.

GENERAL PRINCIPLES

Particulate matter as an air pollutant includes a broad class of airborne liquid or solid substances that vary greatly in chemical and physical properties. One important characteristic is size, because larger particles are not collected in the human respiratory tract and are therefore not a health hazard. Because of irregularities in shape, density, composition, and structure of atmospheric aerosols, individual particles are conveniently characterized by their aerodynamic equivalent diameters (AED). Particles with the same fall velocity are defined as having the same AED, which for convenience is specified as the diameter of a uniform sphere with unit density that obtains the fall velocity (e.g., see Corn 1976).

Throughout this document, most references to particle size refer to AED. When the effects of particles on visibility and light scattering are considered, the use of a different definition of particle size more closely related to actual physical size may be necessary. The primary health hazards from particulate matter are due to its deposition in the human respiratory tract. The impact of particle size and chemical composition on the deposition process is discussed in the EPA staff review of the NAAQS for particulate matter (EPA 1981a).

The atmospheric aerosols that make up PM₁₀ measurements will vary both in size distribution and in chemical composition. Generally, three distinct size modes are present, although the smallest size mode is often difficult to detect. This is shown by the data in Figure 1, which were collected in the California ACHEX study (Whitby 1980). The smallest size mode (<0.1 μm) is short-lived and most often observed as a distinct class near combustion sources. The small nuclei (Aitken) mode particles grow rapidly by coagulation into the next largest size mode. The middle size (accumulation) mode particles (0.1-2.5 μm) are formed mainly by coagulation of and vapor condensation on the nuclei mode particles.

The largest coarse size mode particles ($>2.5 \mu\text{m}$) generally make up most of the mass and include particles formed by anthropogenic processes and reentrained surface dust. The two smaller size modes make up what is generally referred to as fine particulate, and the largest size mode is coarse particulate.




Figure 1. Average volume size distribution for seven sites in the California ACHEX study in 1972 (Whitby 1980).

These two classes, fine and coarse particulates, have different sources and behave independently in the atmosphere. Fine particles mainly result from combustion processes, including the condensation and atmospheric transformation of exhaust gases to form PM. Mechanical processes and wind erosion produce coarse particles. Figure 2 summarizes the principal differences in size and composition of the two types of particles. Fine particles typically consist of sulfates, nitrates, carbonaceous organics, ammonium, and lead. Coarse particles typically consist of oxides of silicon, iron, aluminum, sea salt, tire particles, and plant particles.




Figure 2. Idealized time and coarse particle mass and chemical composition (U.S. Environmental Protection Agency 1981b).

Both manmade and natural sources emit atmospheric PM. Natural sources in the United States emit about 84 million metric tons annually, while manmade sources emit 125 to 383 million metric tons annually. Dust, sea spray, wild fires, biogenic emanations, and volcanoes are the principal natural sources. Most of the manmade emissions are fugitives from roads (unpaved and paved), construction activities, agricultural tilling, mining activities, and industrial processes. The emissions are estimated using approximations. Reliable estimates of particle emissions from the combustion of fuel and well-defined sources are also available (see Table 1), but these are estimated to include only about 10 percent of the total manmade emissions. However, almost all of these manmade emissions are fine particles, while the natural and fugitive emissions are coarse particles, of which 50 percent or less are smaller than 10 μm . Most of the sources of coarse particles exist in rural areas where population densities are low.

TABLE 1. NATIONAL ESTIMATES OF PARTICULATE EMISSIONS
(10⁶ metric tons per year) (EPA 1981b)

Source category	1940	1950	1960	1970	1975	1978
Stationary fuel combustion	8.7	8.1	6.7	7.2	5.1	3.8
Industrial processes	9.9	12.6	14.1	12.8	7.4	6.2
Solid waste disposal	0.5	0.7	0.9	1.1	0.5	0.5
Transportation	0.5	1.1	0.6	1.1	1.0	1.3
Miscellaneous	5.2	3.7	3.3	1.0	0.6	0.7
TOTAL	24.8	26.2	25.6	23.2	14.6	12.5

The height of release of emissions can have an important bearing on human health. For example, emissions from motor vehicles and home heating in densely populated areas may be as important as emissions from large stationary sources in remote areas. Both types of sources must be taken into account in assessing monitoring sites.

INSTRUMENTATION

Until a sufficient data base is developed for PM₁₀ measurements, most of the information that is available to indicate the nature of particulate matter concentrations will be based on TSP measurements made with high-volume (hi-vol) monitors. Therefore, it is important to understand what hi-vols measure and how this differs from what PM₁₀ monitors measure. In addition, the advantages and limitations of instruments that use optical reflectance and beta attenuation need to be understood.

Hi-Vol TSP Monitors

The hi-vol sampler collects particles on a glass-fiber filter. Air is drawn through the filter at a relatively high flow rate (approximately 1.5 m³/min). Although the collection efficiency for larger (>10 μm) particles is sensitive to wind speed, hi-vols collect essentially all particles less than 25 μm under most conditions. The AED of particles with a 50 percent collection efficiency varies from 25 to 30 μm. However, day-to-day variations in wind speed account for no more than a 10 percent variability in measured

concentrations (EPA 1981b). Under identical meteorological conditions, a typical coefficient of variation is 3 to 5 percent. A more significant problem is the formation of artifact mass caused by the reaction of acid gases with material collected on the glass-fiber filter during a 24-hour sample collection. An estimated 6 to 7 $\mu\text{g}/\text{m}^3$ can be added to a 24-hour concentration measurement by artifacts. Errors may also occur due to loss of volatile particles, deposition on filters before and after sampling, gas reactions after sampling, and filter handling.

Potential Reference Method for PM₁₀

The reference method for PM₁₀ is designed to measure that portion of suspended particulate matter in the atmosphere that is likely to be deposited in the thoracic region of the human respiratory tract. The PM₁₀ reference method has a collection efficiency of 50 percent for particles with 10 μm AED (i.e., $D_{50} = 10 \mu\text{m}$).¹ The measurement consists of drawing air at a constant rate through a specially shaped inlet that inertially separates particles larger than 10 μm from the sampling stream. The effectiveness of the size discrimination for the 10 μm separation must match the prescribed limits defined by the reference method, or not differ by more than 10 percent in the expected mass concentration measured by a sampler with the ideal size cut efficiencies. The particles contained in each sampling stream are collected on a filter that is weighed (after moisture equilibration) before and after sampling. As with hi-vol sampling, the volume of air sampled is also measured and corrected to EPA reference conditions (i.e., 25° C and 760 mm Hg).

Although the median particle size collection efficiency is the principal characteristic of a PM₁₀ reference method sampler, a sampler must also meet the following criteria to be a reference method:

- The particle size above which the collection efficiency is less than 50 percent must be within 1 μm of 10 μm .
- The concentration measurements must be reproducible with 15 percent precision.
- The flow rate must be stable to within 10 percent of the initial flow rate over a 24-hour period.

The specific requirements of a PM₁₀ reference method are given in Appendix J of 40 CFR 50.

¹ The particle size cut, D_{50} , of a PM sampler is defined as the particle diameter at which the collection efficiency is less than 50 percent for all larger particles.

PM₁₀ samplers are subject to errors due to loss of volatile particles, artifact PM, nonsampled PM deposition, humidity, filter handling, flow rate variations, and air volume determinations. However, the uncertainties associated with gravimetric measures of particulate matter are less than those associated with particulate measurements based on other principles.

Other Particulate Matter Measurements

The gravimetric method of measuring PM is limited by the need to (1) accumulate an adequate mass for detection by use of an analytical balance, (2) condition the filter for moisture content, (3) separate the collection time from the mass assessment time, and (4) handle the sample between collection and assessment. To eliminate these disadvantages, optical sensing and beta attenuation measurement principles can be used. However, measurements based on these principles do not measure mass directly and may produce variable concentration estimates when certain properties of the particles vary (e.g., particle size distribution or carbon content).

A commonly used instrument based on optical sensing is the tape sampler. Particles are collected to form a stain on a paper tape filter, which is periodically advanced. The transmittance of light through the stain is measured to determine the optical density or coefficient of haze (COHS). The COHS units at a given site may be calibrated to mass measurements made with a colocated gravimetric device. The tape sampler is capable of finer time resolution and faster readout time than gravimetric sensing methods. For certain purposes, including response to severe pollution buildups that require a rapid update of information, optical sensing may be a necessary alternative to gravimetric sensing.

It is also possible to measure specific properties of collected samples. Such properties may include sulfate and nitrate components, visibility reduction, and specific elemental components. The need for information other than mass concentration of PM should be defined when monitoring operations are planned and factored into siting considerations. Samples taken for mass concentration measurements usually can be used for other purposes, because the mass measurement techniques preserve the samples.

USE OF AVAILABLE DATA TO DRAW INFERENCES ABOUT PM₁₀ LEVELS

Because of the abundance of TSP data and the limited quantity of PM₁₀ data available, it may be necessary to use TSP or other available measures of PM to determine expected patterns of PM₁₀. EPA has published a document examining relations of PM₁₀ to other particulate matter (Procedure for Estimating Probability of Nonattainment of PM₁₀ NAAQS Using TSP or PM₁₀ Data). The details of this procedure are beyond the scope of this document; however, a few conclusions from this report are provided.

The ratio of PM₁₀/TSP was examined at sites consisting of colocated PM₁₀/TSP sites operating in 1982 and 1983 for the purpose of establishing a simple ratio which would permit the direct adjustment of TSP to PM₁₀. However, upon scrutinizing the data base, it was clear that a substantial degree of variability existed amongst individual ratios. (The IP/TSP ratios were also examined, only to

establish that they confirmed the PM₁₀/TSP analyses.) This variability includes inter- as well as intrasite differences in the ratios. As described elsewhere in the document, the PM₁₀/TSP ratio was also found to be somewhat sensitive to TSP concentrations. This sensitivity is diminished by focusing on site-days observing TSP > 100 ug/m³ or, in the case of annual analyses, site-years with TSP > 55 ug/m³.

Several attempts were also made to find an explanatory site descriptor which could account for the disparity in the ratios among sites (i.e., inter-site variability). In the first attempt, such site descriptors as urban versus suburban were compared; however, no statistically significant difference was found. Geographic area (East, Southwest, West Coast, etc.) and site type (industrial, commercial or residential) likewise revealed insignificant differences in the ratios. In a more recent and more extensive investigation of geographic differences performed on the entire 1982 and 1983 data base, statistically significant differences were found among individual sites as well as among larger groupings of sites. However, the differences among larger groupings of sites are smaller and are difficult to explain on a physical basis. These investigations conclude that unless sufficient data to calculate a site specific PM₁₀/TSP ratio are available, the existing data base does not justify use of different distributions of ratios for different parts of the country.


The previously described investigations of geographic, climatological, concentration range, or site type classifiers were attempts to reduce or account for part of the variability in PM₁₀ to TSP ratios. No doubt, a part of the overall variance in ratios results from intra-site variation in ratios arising from differences in the sources impacting the monitor site. As discussed in other sections of the document, there are several issues associated with the precision of the TSP and PM₁₀ measurements which affect intra-site variance. These factors include windspeed dependence, weighing problems, artifact formation and sampler wall losses. Thus, the inter-site variance can potentially be eliminated by the use of site specific data, but the intra-site variance can only be partially reduced by careful operating procedures.

The variance among PM₁₀/TSP ratios suggests the need to examine the frequency distribution of ratios rather than relying on a single value for the ratio. The cumulative frequency distribution for PM₁₀/TSP is presented in Figure 3 for site average (arithmetic mean) ratios. Figure 4 contains a similar distribution for 24-hour ratios.

SPATIAL/TEMPORAL PATTERNS

National spatial and temporal patterns of PM₁₀ have been deduced from a variety of available PM observations. Sections 3 and 4 of this document contain guidelines for estimating these patterns in local areas. Important factors that influence the patterns are the sources of emissions, topography and other physiographic factors, and meteorology. Figure 5 shows an indication of the variation in concentrations that can be expected with season of the year and with rural, suburban, and urban location. These graphs are based on monitoring data from a small number of sites.


Cumulative Percentage of Ratios Greater Than a
Given Value (Annual)



Cumulative Percentage of Ratios Less Than A Given Value (Annual)

Figure 3. Distribution of Annual PM₁₀/TSP Ratios

Cumulative Percentage of Ratios Greater than
A Given Value (24-hour)



Cumulative Percentage of Ratios Less Than A Given Value
Figure 4. Distribution of 24-hour PM_{10}/TSP Ratios




Figure 5. Seasonal variations in urban, suburban, and rural areas for four size ranges of particles.

Source: After Trijonis et al. (1980).

Influence of Sources

The highest TSP values are found in dusty arid regions and in industrialized cities. Table 2 shows a breakdown of the principal categories of sources that comprise the EPA national inventory of particulate emissions. The much larger fugitive emissions from nonindustrial anthropogenic activities, such as travel on unpaved roads and wind-eroded farmland, are not included in these figures. These indirect fugitive emissions are coarse particles, and less than 50 percent of their mass will be less than 10 μm in diameter. Furthermore, the sources are widely dispersed and not concentrated near populated areas.

Most of the interest in controlling and monitoring particulate emissions focuses on the stationary sources listed in Table 2. These emissions are believed to contain more toxic elements and to consist primarily of fine particles. Fugitive dust emissions from stationary sources are of particular concern, because they exceed stack emissions, are emitted near ground level, and contain more toxic materials than soils from farmlands and unpaved roads away from industrial sources.

Influence of Atmospheric Processes

PM emitted into the atmosphere is transported by the wind and diluted by various atmospheric turbulence and mixing processes. In addition, particles are removed by dry and wet deposition processes. Particles remaining airborne may grow by condensation, coagulation, and chemical reactions; these growth processes are enhanced by the accumulation of moisture. Figure 6 summarizes and graphically illustrates many of these various atmospheric processes.

Secondary pollutants, which form and grow due to these atmospheric processes, are a major component of PM concentrations. Sulfates, formed primarily by atmospheric reactions, often account for 40 percent of the fine particles. Because fine particles typically contribute about one-third of TSP mass and because PM_{10} is expected to equal about 50 percent of the TSP levels, it is reasonable to expect the sulfate contribution to equal about 25 percent of PM_{10} measurements. But on many occasions the total contribution of secondary PM to PM_{10} measurements may be considerably higher than 25 percent. Because the formation of secondary PM requires time, the principal sources are likely to be remote from the point where they are measured. This makes it important to measure PM_{10} concentrations upwind of urban areas, as well as within and downwind of the areas of concern. The formation of sulfates and nitrates is sufficiently active in both summer and winter to produce high contributions to PM_{10} measurements. The formation of organic aerosols is also important; observed 24-hour concentrations have reached as high as 100 $\mu\text{g}/\text{m}^3$.

TABLE 2. SUMMARY OF NATIONAL 1985 PARTICULATE
MATTER EMISSIONS BY SOURCE CATEGORY (EPA 1987)

Source Category	1985 Emissions (10 ³ tons)
Coal-fired electric utility boilers	627
Coal-fired industrial boilers	132
Integrated iron and steel plants and coke ovens*	187
Portland cement plants	286
Primary nonferrous smelters#	44
Solid waste disposal plants	110
Kraft Pulp and paper mills	110
Asphalt batching plants	132
Concrete lime and gypsum	99
Iron and steel foundries	44
Subtotal for selected source categories	1771
Stationary sources§	6600
Mobile sources	1430
All sources	8030

* Includes emissions from materials handling and storage piles.

Includes fugitive process emissions and emissions from ore crushing and materials handling.

§ By difference between all sources and mobile sources.




Figure 6. Complex processes affecting transport and transformation of airborne particulate matter.

Source: Adapted from Drake and Barrager (1979).

SECTION 3

MONITORING OBJECTIVES FOR PM₁₀

Two pressing questions arise in planning a monitoring program. How many monitors are required? And where should they be located? The answers affect the allocation of resources that, particularly in operational settings, ultimately shape the final program.

Due to a wide diversity of topography, population distribution, source locations, and climates, ambient air quality monitoring regulations and policies rarely specify the number and location of monitors. But regardless of the influence of physical factors, the specifications for a monitoring network strongly depend upon the monitoring objectives.

A monitoring objective relates the monitoring mandate to spatial/temporal variations in sources of pollution, meteorology, and receptors of pollution. The monitoring mandate arises from specific needs and uses for data. A monitoring objective is the link between the goals of the mandate and appropriate siting opportunities in the monitoring scene. Monitoring objectives relate program objectives that concentrate upon end uses for the collected data and physical objectives that concentrate on the temporal and spatial character of representative sampling.

One obvious use of PM₁₀ data lies in establishing environmental regulations and policies. Such regulatory mandates are rooted in the Clean Air Act (CAA) and other Federal, state, and local regulations that specify air quality requirements.

Other data uses satisfy research needs and support public services. A variety of data uses for the criteria pollutants have been summarized in other EPA monitoring guidelines (Ball and Anderson 1977; Ludwig and Kealoha 1975; Ludwig, Kealoha, and Shelar 1977; Ludwig and Shelar 1978) and elsewhere (e.g., EPA 1977a). Table 3 summarizes these varied data uses:

- Evaluation of ambient air quality
- Enforcement of source-specific regulations
- Evaluation/development of control plans
- Air quality maintenance planning
- Protection of public health
- Development and testing of models
- Research.

TABLE 3. PRINCIPAL DATA USES FOR PM₁₀

-
1. Evaluation of Ambient Air Quality
 - Judging Attainment of NAAQS
 - Establishing Progress in Achieving/Maintaining NAAQS
 - Establishing Long-Term Trends

 2. Enforcement of Source-Specific Regulations
 - Categorical Sources (ESECA, SCS, PSD)
 - Individual Sources
 - Enforcement Actions

 3. Evaluation/Development of Control Plans
 - SIP Provisions
 - Evaluation/Development/Revision of Local Control Strategies

 4. Air Quality Maintenance Planning
 - Establishing Baseline Conditions
 - Project Future Air Quality

 5. Protection of Public Health
 - Air Quality Indices
 - Documentation of Population Exposures
 - Response to Unique Citizen Complaints
 - Development/Revision of Standards

 6. Development and Testing of Models
 - Input for Receptor Models
 - Validation and Refinement
 - Assessing Representativeness of Monitoring Networks

 7. Research
 - Effects on Humans, Plants, Animals and Environment
 - Characterization of Source, Transport, Transformation, and Fate for Anthropogenic and Natural Emissions
 - Development/Testing of New Instrumentation
-

The order of the listed uses does not represent any sense of priority. The uses are a composite of diverse program objectives that would require extended discussion to develop in detail.

In all areas except research, a straightforward relationship exists between mandate and program objectives or data uses. Thus these representative data uses provide a range of example situations, so that physical objectives for specific cases not covered here can be developed by analogy.

EVALUATION OF AMBIENT AIR QUALITY

The National Ambient Air Quality Standard for PM_{10} stipulates acceptable air quality in terms of a 24-hour criteria level (not to be exceeded more than the specified number of times a year) and an annual criteria level (the 12-month arithmetic mean). Although the NAAQS is the principal standard that must be met, other local and state agencies may set standards that must be met.

Compliance with the NAAQS is a fundamental goal of ambient air quality control strategies (particularly for State Implementation Plans (SIPs)) and forms the basis for air quality maintenance planning, policy development, and additional regulation. Data are needed to evaluate ambient air quality and detect compliance with the NAAQS. Attainment status is conferred upon an area, based on the expectation that the NAAQS criteria levels are not violated. Therefore, the monitoring objectives are geared to acquiring measurements that represent conditions throughout the area in question, the underlying context being that air quality levels elsewhere in the area are no worse than those indicated by the measurements.

The data are also used to demonstrate reasonable progress toward attainment for areas in violation of the NAAQS, document baseline conditions for environmentally sound expansion and development, and depict long-term trends.

ENFORCEMENT OF SOURCE-SPECIFIC REGULATIONS

Under some circumstances, major air pollution sources are allowed to operate under demonstration that their emissions do not cause ground-level concentrations that exceed a specified criteria level. The criteria level is ordinarily tied to NAAQS, but may be tied to other criteria. These situations may prevail for power plants, coking facilities, and other categorical sources under a variety of regulations. Source-specific regulations may consist of tailored or negotiated agreements that are integrated to implementation plans on a source-by-source basis. Although the responsibility to monitor may fall upon a regulatory agency or upon the source management, the objective is to measure the impact of a known source.

Indications of compliance/noncompliance are often used in enforcement proceedings and frequently form the basis for litigation and negotiation. A corollary monitoring situation entails isolating an offending source or family of sources when an adverse impact is measured.

Many applications require a long-term, continuing monitoring program. However, in some enforcement situations, a relatively short sampling program or a periodic survey approach is applicable.

EVALUATION/DEVELOPMENT OF CONTROL PLANS

Government monitoring agencies and pollution source operators are actively concerned with gaining/retaining NAAQS attainment status. Procedures for pursuing this goal are stated in the SIP, which is expanded and modified as needed.

Monitoring data are needed for the following purposes:

- Define nonattainment areas
- Develop control policies and strategies
- Define nondeterioration areas
- Develop air pollution emergency episode plans.

The monitoring data are used to demonstrate and characterize the need for controls. The demonstration may identify categorical sources or specific sources. Nondeterioration areas and areas subject to growth or economic rejuvenation require monitoring to define the baseline conditions.

Monitoring data are needed in areas subject to extremely high concentrations to identify the onset and abatement of episodes. A separate guidance document on the timely reporting of PM₁₀ concentrations during emergency episodes is available (EPA 1983).

AIR QUALITY MAINTENANCE PLANNING

Planning agencies and developers from the private sector require monitoring data to determine baseline air quality levels in locations of projected growth and expansion. These data may be critical in determining whether such activity will meet Prevention of Significant Deterioration (PSD) requirements in attainment areas or interfere with progress toward attainment of NAAQS in nonattainment areas. Siting considerations need to consider whether special sites are needed to meet these data needs or whether the nearest available monitoring will be adequate.

PROTECTION OF PUBLIC HEALTH

It can be argued that all air quality monitoring is ultimately oriented to public health. Air quality indices keep the public apprised of current levels of air pollutants. The siting requirements to meet the data use need to be coordinated with needs for emergency episode data and for ambient air quality evaluations. A second category of public health oriented data use involves documentation of population exposures. This may require a specially sited network designed to estimate personal exposures in connection with epidemiological studies. Special monitoring sites may also be required to respond to unique citizen complaints. These frequently involve sources and impacts that are not part of operational coverage.

DEVELOPMENT AND TESTING OF MODELS

Monitoring requirements to support model development or testing are generally unique for each project. This is particularly true for model development support where the objective is to describe and understand the ongoing processes or to develop parameter values representative of a specific terrain, meteorological condition, or source configuration. As a general rule, monitoring for model development must be intensive and flexible to provide the maximum benefit. Measurements are desired that are as tightly spaced and as frequently recorded as are compatible with economic restraints. However, the monitoring equipment should be mobile enough so that it can be moved as conditions change or as analyzed information indicates a need for information from different locations.

The primary emphasis is on demonstrating that the model being tested adequately estimates the highest concentrations. This means that monitoring data needs to be taken at locations downwind of major sources during critical meteorological conditions. The data record needs to be sufficiently long to truly characterize the data site--usually a minimum of 1 year--if the model is to demonstrate validity at the test site. Test data, preferably from a different locality, must be independent of data used to develop the model. The placement and number of monitors will depend on meteorological conditions, topography, source characteristics, and purpose of the model. Sections 4 and 5 of this report provide further suggestions with respect to these influences.

RESEARCH

Monitoring data is needed to support research allied to PM₁₀ questions in order to improve the scientific tools for measurement, interpretation, and prediction. Monitoring sites selected to support research may coincide or

supplement other monitoring requirements. Research needs in the following areas may be considered when selecting sites:

1. Effects on humans, plants, animals, and environment
2. Characterization of source, transport, transformation, and fate for natural and anthropogenic emissions
3. Development and testing of new instrumentation.

SECTION 4

ELEMENTS OF SITE SELECTION

The site selection procedures offered in Section 5 rely primarily on inferred and demonstrated associations among PM_{10} sources, meteorology, and a number of physical factors such as topography and land use. Important outcomes (i.e., ambient concentrations) can vary tremendously from place to place within a monitoring scene and from time to time at a given place. From a useful perspective, any area to be monitored is going to be too complex to bring all structures into focus at once. The concept of representative scale is a useful way to characterize these variations on a physical basis that can be related to comprehensible patterns.

REPRESENTATIVE SCALES

The concept of representative spatial scale is used to define a characteristic distance over which pollutant concentrations are uniform or nearly so. As a corollary, we can define homogeneous areas in which measurements performed in the relatively small air volume near a sampler (nominal horizontal extent of 1 meter) can represent conditions prevailing over some much larger area.

Representative spatial scales illustrated in Figure 7 have been previously identified (EPA 1979) and are compatible with spatial scales of source areas. We shall be concerned with the following spatial scales:

- Microscale--ambient air volumes ranging in horizontal extent from a few meters to as much as 100 m. The microscale encompasses the immediate vicinity of the monitor. In the immediate presence of PM_{10} sources, exposure may in reality be only representative of the microscale. For this reason, the microscale is the final judgmental factor in site selection (see Section 5) and requires a site visit to make this appraisal, because maps rarely portray confounding influences in sufficient detail.
- Middle scale--ambient air volumes covering areas larger than microscale but generally no more than 0.5 km in extent. In settled areas, this may amount to several city blocks. As will be shown later, this is essentially the lower limit of resolution for most models.
- Neighborhood scale--ambient air volumes whose horizontal extent is generally between 0.5 and 4 km. The neighborhood scale is aptly named. It is useful in defining extended areas of homogeneous land use.




Figure 7. Illustration of various spatial scales of representativeness (Ball and Andersen 1977).

- Urban scale--ambient air volumes whose horizontal extent may range between 4 and 50 km. This is frequently the most desirable representative spatial scale, because it captures an entire urban area. However, the diversity of sources that prevail within such areas argue against homogeneity at this scale.
- Regional scale--ambient air volumes whose horizontal extent ranges from tens of kilometers to hundreds of kilometers. Monitors that are unaffected by specific sources or by localized groups of sources can be representative at this scale.
- National and global scales--seek to characterize air quality from a national perspective (thousands of kilometers) or from a global perspective (tens of thousands of kilometers).

Although all of the above scale intervals may be needed to subdivide a monitoring scene, the neighborhood scale in urban settings and the regional scale in substantially unsettled areas are particularly practical scales for spatial coverage by a single monitor. In many circumstances, the representativeness of the small scales must be estimated by networks composed of a limited number of sites.

ANALYSIS OF THE AREA TO BE MONITORED

The primary intent of the analytical process that supports site selection is to characterize pollutant levels within the area to be monitored. This requires information regarding the location of important sources of PM_{10} , a description of atmospheric trajectories to trace the movement of PM_{10} , and estimates of dispersion accompanying such movement. These reflect a complex interplay among topography and climatology that must be cast into time frames that are compatible with the NAAQS. Three components for analysis are as follows:

- Regional dispersion climatology--to assemble the basis for transport/dispersion patterns that may be applied to the area to be monitored as a whole
- Physical differentiation--to assemble the basis for identifying distortions of simple source/receptor relationships due to local alterations of trajectory and dispersion
- Emissions configuration--to assemble the basis for identifying relevant PM_{10} sources and recognizing useful patterns.

An area of interest with respect to air quality is usually defined by political boundaries, such as state, county, city, or air quality control region lines. A method of systematically characterizing the area to be monitored into homogeneous areas of air quality levels that are potential locations of air pollution monitoring sites requires that sources of particulate emissions, patterns of terrain and physiography, and climatology be taken into account. A method and data sources for performing such a classification analysis for ambient concentrations of PM have been developed in this study beginning with a description of the three categories of influencing factors. The methodology is presented in Section 5.

Emissions Configuration

The emissions configuration is simply the spatial/temporal distribution of sources throughout the monitoring scene; in concept, it will consist of one or more maps delineating areas of similar source characteristics. Depending on the mix of sources and local/regional climate, such maps will depict relevant seasonal and diurnal emissions patterns in terms of relative intensities and release heights.

In concept, the most straightforward approach to generating maps would be to selectively allocate the elements of a formal emissions inventory to a suitably detailed grid. In practice, this is not a trivial task; even an automated approach carries a substantial burden in data management and manipulation. Though difficult, this approach has merit because it develops highly usable data for subsequent computerized modeling.

An alternative approach is to proxy these source areas by patterns of land use. In most urban areas, planning agencies have compiled information that can form the basis for categories of near-surface emission. In the absence of such information, relatively unsophisticated interpretation of aerial photographs can be helpful. Table 4 offers a land use classification that is amenable to this approach. Emission factors can be assigned to each land use classification based on consideration of local heating fuels, climate, and census data in housing and population densities. In addition, large point sources (e.g., 1000 tons per year) should be separately identified.

The first use of an emissions configuration is in a semiquantitative or subjective mode. The orientation of key impact zones can be surmised with the aid of appropriate wind roses. Areas likely to be inundated by several sources can be identified.

An emissions inventory provides important information to the site selection process by identifying significant point and area sources and cataloging emissions in terms of location, source strength, operating characteristics, etc. The National Emissions Data System (NEDS), for instance, identifies individual point sources that release 100 tons per year or more

TABLE 4. IDENTIFICATION AND CLASSIFICATION OF LAND USE TYPES (AFTER AUER 1978)

Type	Use and structures	Vegetation
I1	Heavy Industrial Major chemical, steel, and fabrication industries; generally 3- to 5-story buildings, flat roofs	Grass and tree growth extremely rare; <5% vegetation
I2	Light-Moderate Industrial Rail yards, truck depots, warehouses, industrial parks, minor fabrications; generally 1- to 3-story buildings, flat roofs	Very limited grass, trees almost totally absent; <5% vegetation
C1	Commercial Office and apartment buildings, hotels; >10-story heights, flat roofs	Limited grass and trees; <15% vegetation
R1	Common Residential Single-family dwelling with normal easements; generally single-story, pitched-roof structures; frequent driveways	Abundant grass lawns and light to moderately wooded; >70% vegetation
R2	Compact Residential Single- and some multiple-family dwellings with close spacing; generally <2-story, pitched-roof structures; garages (via alley), no driveways	Limited lawn sizes and shade trees; <30% vegetation
R3	Compact Residential Old multifamily dwellings with close (<2 m) lateral separation; generally 2-story, flat-roof structures; garages (via alley) and ashpits; no driveways	Limited lawn sizes, old established shade trees; <35% vegetation
R4	Estate Residential Expansive family dwelling on multiacre tracts	Abundant grass lawns and lightly wooded; >95% vegetation
A1	Metropolitan Natural Major municipal, state, or Federal parks, golf courses, cemeteries, campuses; occasional single-story structures	Nearly total grass and lightly wooded; >95% vegetation
A2	Agricultural Rural	Local crops (e.g., corn, soybeans); >95% vegetation
A3	Undeveloped Uncultivated; wasteland	Mostly wild grasses and weeds, lightly wooded; >90% vegetation

of five criteria emissions (particulate matter, SO_x, NO_x, CO, hydrocarbons) as well as area sources aggregated at the county level (i.e., all other stationary sources that individually emit less than 100 tons per year and all mobile sources). More detailed approaches (e.g., Pace 1979) develop microinventories that add perspective and structure to the area source category.

It is beyond the intended scope of this report to promote methodologies for constructing emission inventories. For the purposes at hand, an emissions inventory for particulate matter emissions is assumed to be available and ready for use. Such an inventory may be composed of NEDS-based data (EPA 1984) or may have been specially constructed for the monitor siting analysis.

During the last few years EPA has had PM₁₀ emission factors developed for a large number of source categories. The development of PM₁₀ emission factors for additional source categories including some fugitive and open sources is still in progress at this time. The user is referred to EPA's Compilation of Air Pollution Emission Factors AP-42 for specific emissions by source category and specific methodology for their use in developing emission estimates. The compilation provides specific factors not only by general source category but also for each processing step within a category. Tables 5 and 6 present example emission factors for some selected source categories. These examples have been taken from EPA's report.

Terrain and Physiography

The patterns of ambient concentrations that occur due to the transport and diffusion of pollutants over open and flat terrain are significantly distorted by irregularities in the terrain and other features of physiography. Two major factors in this regard are as follows:


- Aerodynamic diversion--flow around and over obstacles. Distortion of the flow field may be severe during moderate to strong synoptic winds.
- Local circulations--mountain-valley winds, land-sea breezes, and the like that may prevail when synoptic influences are sufficiently weak. Under these conditions, flow patterns within the scene may "wall off" subareas. Transport and dispersion estimates at one place are unlikely to reflect air motions elsewhere.

TABLE 5. CUMULATIVE PARTICLE SIZE DISTRIBUTION AND SIZE SPECIFIC EMISSION FACTORS FOR SPREADER STOKERS BURNING BITUMINOUS COAL^a

EMISSION FACTOR RATING: C (uncontrolled and controlled for multiple cyclone without flyash reinjection, and with baghouse)
E (multiple cyclone controlled with flyash reinjection, and ESP controlled)

Particle size ^b (μ m)	Cumulative mass \leq stated size					Cumulative emission factor (kg/Mg (lb/ton) coal, as fired)				
	Uncontrolled	Controlled				Uncontrolled	Controlled			
		Multiple cyclone ^c	Multiple cyclone ^d	ESP	Baghouse		Multiple cyclone ^e	Multiple cyclone ^f	ESP	Baghouse
15	28	86	74	97	72	8.4 (16.8)	7.3 (14.6)	4.4 (8.8)	0.23 (0.46)	0.043 (0.086)
10	20	73	65	90	60	6.0 (12.0)	4.2 (8.4)	3.9 (7.8)	0.22 (0.44)	0.036 (0.072)
6	14	51	32	82	46	4.2 (8.4)	4.3 (8.6)	3.1 (6.2)	0.20 (0.40)	0.028 (0.056)
2.5	7	8	27	61	26	2.1 (4.2)	0.7 (1.4)	1.6 (3.2)	0.15 (0.30)	0.016 (0.032)
1.25	5	2	16	46	18	1.5 (3.0)	0.2 (0.4)	1.0 (2.0)	0.11 (0.22)	0.011 (0.022)
1.00	5	2	14	41	15	1.5 (3.0)	0.2 (0.4)	0.8 (1.6)	0.10 (0.20)	0.009 (0.018)
0.825	4	1	9	e	7	1.2 (2.4)	0.1 (0.2)	0.5 (1.0)	e	0.004 (0.008)
TOTAL	100	100	100	100	100	30.0 (60.0)	8.5 (17.0)	6.0 (12.0)	0.24 (0.48)	0.06 (0.12)

^aReference 61. ESP - electrostatic precipitator.
^bExpressed as aerodynamic equivalent diameter.
^cWith flyash reinjection.
^dWithout flyash reinjection.
^eInefficient data.
^fEstimated control efficiency for ESP, 99.22; baghouse, 99.81.




Cumulative size specific emission factors for spreader stokers burning bituminous coal

TABLE 5 (continued): CUMULATIVE PARTICLE SIZE DISTRIBUTION AND SIZE SPECIFIC EMISSION FACTORS FOR DRY BOTTOM BOILERS BURNING PULVERIZED BITUMINOUS COAL^a

EMISSION FACTOR RATING: C (uncontrolled)
 D (scrubber and ESP controlled)
 E (multiple cyclone and baghouse)

Particle size ^b (μ m)	Cumulative mass % \leq stated size					Cumulative emission factor ^c (kg/Mg (lb/ton) coal, as fired)				
	Uncontrolled	Controlled				Uncontrolled	Controlled ^d			
		Multiple cyclone	Scrubber	ESP	Baghouse		Multiple cyclone	Scrubber	ESP	Baghouse
15	32	54	61	79	97	1.6A (3.2A)	0.54A (1.08A)	0.24A (0.48A)	0.032A (0.064A)	0.010A (0.02A)
10	23	29	71	67	92	1.15A (2.3A)	0.29A (0.58A)	0.21A (0.42A)	0.027A (0.054A)	0.009A (0.02A)
6	17	14	62	50	77	0.85A (1.7A)	0.14A (0.28A)	0.19A (0.38A)	0.020A (0.04A)	0.008A (0.02A)
2.5	6	3	51	29	53	0.30A (0.6A)	0.03A (0.06A)	0.13A (0.26A)	0.012A (0.024A)	0.005A (0.01A)
1.25	2	1	35	17	31	0.10A (0.2A)	0.01A (0.02A)	0.11A (0.22A)	0.007A (0.014A)	0.003A (0.006A)
1.00	2	1	31	14	25	0.10A (0.2A)	0.01A (0.02A)	0.09A (0.18A)	0.006A (0.012A)	0.003A (0.006A)
0.625	1	1	20	12	14	0.05A (0.10A)	0.01A (0.02A)	0.06A (0.12A)	0.005A (0.01A)	0.001A (0.002A)
TOTAL	100	100	100	100	100	5A (10A)	1A (2A)	0.3A (0.6A)	0.04A (0.08A)	0.01A (0.02A)

^aReference 61. ESP = electrostatic precipitator.
^bExpressed as aerodynamic equivalent diameter.
^cA = coal ash weight %, as fired.
^dEstimated control efficiency for multiple cyclone, 80%; scrubber, 94%; ESP, 99.2%; baghouse, 99.8%.



Cumulative size specific emission factors for dry bottom boilers burning pulverized bituminous coal.

EMISSION FACTORS

TABLE 6. SIZE SPECIFIC EMISSION FACTORS FOR COKE MANUFACTURING

Process	Particulate emission factor rating	Particle size (µm)	Cumulative mass % < stated size	Cumulative mass emission factors			
				kg/Mg	lb/ton		
Coal preheating Uncontrolled	D	0.5	44	0.8	1.5		
		1.0	48.5	0.8	1.7		
		2.0	55	1.0	1.9		
		2.5	59.5	1.0	2.1		
		5.0	79.5	1.4	2.8		
		10.0	97.5	1.7	3.4		
		15.0	99.9	1.7	3.5		
			100	1.7	3.5		
	Controlled with venturi scrubber	D	0.5	78	0.10	0.20	
			1.0	80	0.10	0.20	
			2.0	83	0.10	0.21	
			2.5	84	0.11	0.21	
			5.0	88	0.11	0.22	
			10.0	94	0.12	0.24	
15.0			96.5	0.12	0.24		
		100	0.12	0.25			
Coal charging Sequential or stage	E	0.5	13.5	0.001	0.002		
		1.0	25.2	0.002	0.004		
		2.0	33.6	0.003	0.005		
		2.5	39.1	0.003	0.006		
		5.0	45.8	0.004	0.007		
		10.0	48.9	0.004	0.008		
		15.0	49.0	0.004	0.008		
				100	0.008	0.016	
Coke pushing Uncontrolled	D	0.5	3.1	0.02	0.04		
		1.0	7.7	0.04	0.09		
		2.0	14.8	0.09	0.17		
		2.5	16.7	0.10	0.19		
		5.0	26.6	0.15	0.30		
		10.0	43.3	0.25	0.50		
		15.0	50.0	0.29	0.58		
				100	0.58	1.15	
		Controlled with Venturi scrubber	D	0.5	24	0.02	0.04
				1.0	47	0.04	0.08
2.0	66.5			0.06	0.12		
2.5	73.5			0.07	0.13		
5.0	75			0.07	0.13		
10.0	87			0.08	0.16		
15.0	92			0.08	0.17		
		100	0.09	0.18			

(continued)
EMISSION FACTORS

TABLE 6 (Continued)

Process	Particulate emission factor rating	Particle size (um)	Cumulative mass % ≤ stated size	Cumulative mass emission factors	
				kg/Mg	lb/ton
Mobile scrubber car	D	1.0	28.0	0.010	0.020
		2.0	29.5	0.011	0.021
		2.5	30.0	0.011	0.022
		5.0	30.0	0.011	0.022
		10.0	32.0	0.012	0.024
		15.0	35.0	0.013	0.023
		100	0.036	0.072	
Quenching Uncontrolled (dirty water)	D	1.0	13.8	0.36	0.72
		2.5	19.3	0.51	1.01
		5.0	21.4	0.56	1.12
		10.0	22.8	0.60	1.19
		15.0	26.4	0.69	1.38
		100	2.62	5.24	
Uncontrolled (clean water)	B	1.0	4.0	0.02	0.05
		2.5	11.1	0.06	0.13
		5.0	19.1	0.11	0.22
		10.0	30.1	0.17	0.34
		15.0	37.4	0.21	0.42
		100	0.57	1.13	
With baffles (dirty water)	D	1.0	8.5	0.06	0.11
		2.5	20.4	0.13	0.27
		5.0	24.8	0.16	0.32
		10.0	32.3	0.21	0.42
		15.0	49.8	0.32	0.65
		100	0.65	1.30	
With baffles (clean water)	D	1.0	1.2	0.003	0.006
		2.5	6.0	0.02	0.03
		5.0	7.0	0.02	0.04
		10.0	9.8	0.03	0.05
		15.0	15.1	0.04	0.08
		100	0.27	0.54	
Combustion stack Uncontrolled	D	1.0	77.4	0.18	0.36
		2.0	85.7	0.20	0.40
		2.5	93.5	0.22	0.44
		5.0	95.8	0.22	0.45
		10.0	95.9	0.22	0.45
		15.0	96	0.22	0.45
		100	0.23	0.47	

In many instances these factors are of minor influence to site selection, particularly when viewed from the perspective of the 24-hour averaging period that defines most operational PM₁₀ monitoring. More often, however, these influences are severe enough to warrant attention, particularly in source-oriented applications. There are many circumstances where an area may experience aerodynamic diversion problems under moderate to strong synoptic influences while exhibiting local circulations when synoptic conditions are weak. Because of this, discussion of these two factors is structured around the physical aspects of the monitoring scene that should alert the monitoring designer to the situation. Four primary areas for discussion have been identified: topographic influences, coastal settings, small-scale obstacles, and urban effects.

These factors are expressed in varying intensity from area to area. A detailed discussion of resulting patterns is clearly beyond the intended scope of this document. Therefore, each topical area will be treated in summary fashion, and the description will rely heavily upon illustrations.


Topographic Influences--

Topographic elements become a factor when their influences extend into the neighborhood scale (horizontal size order of kilometers). Because the ratio of downstream aerodynamic effect to obstacle height is on the size order of 10 to 1, obstacles on the order of 100 m will influence horizontal sizes of the order of 1 km. The central problem that terrain introduces is the added detail impressed upon the advection/dispersion field. That is, a simple pattern that may be replicated consistently throughout a scene of level terrain becomes an inconstant three-dimensional perturbation in the presence of substantial terrain relief. The principal types of flow distortion that occur include separation flow on the downwind side of ridges when the flow is perpendicular to the ridge, channeling of air flow by valleys, and local circulations caused by differential heating of adjacent terrain slopes.


Coastal Settings--

In coastal settings, during periods of light synoptic winds accompanied by a sufficiently strong thermal contrast between water temperatures and land temperatures, a land/sea breeze circulation (or conversely, land/lake breeze) will control air motions in the vicinity of the shoreline.

Figure 8 displays the characteristic circulation patterns associated with a lake (or sea) breeze (8a) and a land breeze (8b). This circulation system is not static. As shown in Figure 9, the convergence zone migrates inland as the land surface heats up. The intensity of the sea breeze may increase through midafternoon, but dies out after sunset as the land surface rapidly cools. At night, the land breeze sets up, but is generally less vigorous because thermal contrasts are smaller.



A. Lake Breeze



B. Land Breeze

Figure 8. Characteristics of lake coast air flow.




Figure 9. Hourly positions of lake breeze front of August 13, 1967, with the ground track of the NACR Queen air plotted. Hygrothermograph traces at several distances from the shoreline are included. Surface water temperature is 67° F. One full wind barb equals 5 knots. From Lyons and Olsson 1972.

The primary impact of this system is to recompose a coastal monitoring scene into at least two siting domains: one area subject to the land/sea breeze effects, another outside of this influence. The size and extent of the land/sea breeze-affected subarea can be assessed in a number of ways. An obvious factor of contrast is the horizontal distribution of wind directions on appropriate days; however, few areas have sufficiently detailed meteorological networks to define the horizontal extent of the area and the change in size of the affected area with time. A more reasonable approach is to use air temperature and relative humidity patterns to characterize this effect. Figure 9 displays distinctive signatures in hygrothermograph recordings and suggests a method of analysis that may be helpful.

Small Scale Obstacles--

Wind deflection around and over obstacles is a concern in selecting specific sites in an urban area, because the effects occur on the microscale. As shown in Figure 10, air does not simply slip past an isolated structure. There are three distinguishable zones of air around a building:

1. Displacement zone--where streamlines are deflected upwind and outward, remaining so for some distance
2. Wake zone--where streamlines gradually recover original configuration
3. Cavity zone--return flow in the immediate vicinity of the downwind side.




Figure 10. Flow zones around a building

In terms of site selection, this effect is of obvious importance if an intervening obstacle contains a strong enough source to generate a ground-level impact that would be assigned to a source further upstream--particularly if monitoring were to unwittingly take place in the cavity zone. This effect is further complicated when many such obstacles are placed together, as shown in Figure 11.




Figure 11. Flow characteristics among multiple buildings.

Urban Effects--

In addition to the effects of individual buildings, a city induces large-scale modifications to the local wind field. These modifications have a bearing on site selection, due to the heat island circulation.

When a heat island circulation exists, there is a convergence zone over the center of the city and a return flow into outlying areas, as illustrated in Figure 12. This circulation pattern is most pronounced at night when differential radiative cooling rates favor higher temperatures in the urban center. The circulation pattern is generally weaker during the day when urban/rural thermal contrasts are not as strong. Table 7 summarizes the general magnitude of key heat island circulation elements.




Figure 12. Idealized urban heat island air flow (After Landsberg 1975).

TABLE 7. ESTIMATES OF THE ST. LOUIS, MISSOURI, HEAT ISLAND CIRCULATION

Element	General magnitude
Urban/rural temperature difference	>2°C
Gradient wind (900 mb)	>5 m/sec
Average surface wind	2 m/sec
Average vertical velocity	0.3 m/sec
Diameter of surface inflow	30 km
Diameter of updraft	7 km
Depth of circulation	1 km

Source: Landsberg.

Under sufficiently strong winds, the heat island circulation is overwhelmed. Oke and Hannel (1970) have developed a simple relationship between the threshold wind speed to prohibit the circulation and relative city size. Oke and Hannel's empirical formulation is as follows:

$$U_{lim} = 3.4 \text{ Log}P - 11.6$$

where P is the population number. Thus, a large urban area whose population is counted in the millions can exhibit a heat island circulation even if regional winds are quite strong. Although this relationship showed a high correlation (94 percent variance explained) for the cities studied, it should not be treated as an absolute measure. Each urban setting will have its own idiosyncracies due to local terrain, presence of water bodies, or other factors.

Climatology

Regional dispersion climatology encompasses those atmospheric parameters of regional scale influence that affect the distribution of ambient concentration. The parameters of primary concern are advection, dispersion, and vertical mixing. With the exception of advection (i.e., surface winds), the instrumentation to acquire direct measures of these parameters are generally not found in most settings. Even when relevant measurements are available, the important fine structure needed to characterize significant air pollution

transport is generally not observed (e.g, Hewson 1976; Holzworth 1974; and McCormick and Holzworth 1976). Nevertheless, it is important to consider what regular data are available to estimate advection, dispersion, and vertical mixing. Additional parameters needed for air quality simulations are also considered.

Advection--

For most monitoring objectives, advection is adequately defined by the near-surface wind (speed and direction) measured at (or adjusted to) a reference height of 10 meters above the ground. Useful observations may consist of short-term averages taken hourly or every 3 hours, as well as true algebraic or vectorial averages over these time intervals. Nearly continuous recordings are sometimes available.

Directional air flow is an intuitively appealing siting tool. One of the most useful summary depictions is the wind rose that expresses advection in terms of relative frequency of occurrence by direction, usually with a breakdown of wind speed by classes within each directional interval. By convention, a wind direction denotes the sector from which wind is blowing. Wind roses may be compared on an 8-point basis, a 16-point basis, or a 36-point basis.

The most common summary wind roses are compared for annual, seasonal, or monthly distributions (see Figure 13). Under some circumstances, wind roses are devised to study winds under critical conditions. For example, STAR¹ summaries offer a joint frequency distribution of winds and atmospheric stability. These are available from the National Climatic Center and may be compared for various time periods. Additional categories of wind roses include winds under important pollutant index levels, distribution of persistent 24-hour winds, and distributions within key parts of the day (i.e., morning versus afternoon).

Dispersion--

Dispersion is the summary effect of atmospheric turbulence in actively diluting source material. Direct measurements of the three-dimensional wind fluctuations that manifest turbulence are rarely made. Instead, various methods of characterizing turbulence based on theoretical and empirical relationships are employed. The most common system is based upon associations among wind speed, solar insolation, and cloud cover, as shown in Table 8. Many operational models accept this type of data directly, and manual techniques have evolved to treat these as well (see Turner 1970).

¹ STability ARray, a broad-based algorithm for determining stability in the lower atmosphere using estimates based on winds and cloudiness. See Doty, Wallace, and Holzworth 1976.




Figure 13. Annual wind roses for U. S. locations.

TABLE 8. DISPERSION CLASSIFICATIONS (PASQUILL 1961)

Surface wind speed at 10 m (m sec ⁻¹)	Night				
	Insolation			Thinly overcast or >4/8 low cloud	
	Strong	Moderate	Slight	<3/8 cloud	>3/8 cloud
2	A	A-B	B	-	-
2-3	A-B	B	C	E	F
3-5	B	B-C	C	D	E
5-6	C	C-D	D	D	D
>6	C	C	D	D	D

Mixing Height--

Mixing height defines the vertical extent of mixing. Ground-based and low-level inversions are the principal limiting factors. Mixing height is determined from a thermodynamic analysis of vertical temperature soundings. These soundings are routinely performed at 0000 GMT and 1200 GMT each day at a number of stations. Contact National Climatic Center (see Appendix A) for a list. Additionally, climatological summaries are also available (see Holzworth 1972).

Other Parameters--

Additional parameters that may be useful are listed below. Routine data sources are summarized in Appendix B.

- Solar radiation--for estimates of formation rates of secondary aerosols
- Visibility--as a proxy for regional scale impacts
- Precipitation--to relate to scavenging processes
- Air temperature--to be applied to plume rise estimates, or as a fine adjustment to residential space heating demand as a proxy for some combustion sources.

TAXONOMY OF REPRESENTATIVE SITES

By classifying monitoring objectives and monitoring sites, it is possible to categorize all monitoring requirements into discrete groupings. Siting methods that are appropriate to each group or to several groups can be more easily identified. Furthermore, some groupings may be of little interest and need not receive further attention.

In the preceding section, spatial scales of areas were defined within which air quality levels are reasonably homogeneous for typical organizations of human structures and activities that characterize each scale. These definitions were very general. The physical characteristics that primarily contribute to variations in air quality include sources of emissions, types of terrain, and types of meteorological influences. Each of these characteristics and the nature of the variations that affect air quality levels have been previously discussed.

For the purpose of classifying representative siting situations with respect to PM₁₀, the following three categories of sources of emissions are of interest:

- Background or general region
- General urban or industrial area
 - Homogeneous
 - Complex
- Major source within an urban area
- Isolated source.

With respect to terrain influences the following categories of topographical features are of interest:

- Plains
- Coast
- Ridge and valley
- Irregular terrain
 - Extremely rough
 - Moderately rough
- Urban.

Although mixtures of the above terrain influences are possible, it is unrealistic to attempt to characterize such complex influences within the scope of present modeling and analysis methods. For monitoring planning purposes, it may be best to incorporate the single most important influence into the analysis.

With respect to meteorological influences on air quality levels, there are two important categories of features that have been frequently cited as being important in creating poor air quality levels. These categories are (1) stagnation situations with limited vertical mixing and little advection for prolonged periods and (2) persistent winds in which pollution from a source is consistently transported to the same location for a prolonged period. The following categories of meteorological influences are of interest:

- Frequent air stagnation conditions
- Frequent persistent winds
- Normally variable meteorological conditions.

For PM_{10} air quality levels, there are two averaging times of interest: 24-hour and 1-year. The pattern of effects associated with these two averaging periods may differ, in that shorter term effects usually occur closer to the source than do longer term effects.

Based on the above factors, there are 120 possible representative siting situations consisting of all the following combinations:

- 4 classes of sources
- 5 classes of terrain
- 3 classes of meteorology
- 2 classes of averaging times.

However, for the purpose of identifying methodologies to use in determining siting needs, the same approach is applicable to many of the combinations. One need not use different approaches to treat different averaging times. Also, the meteorological influences are associated with the influences due to terrain and need not be treated as independent factors. Eliminating time and meteorology reduces the number of combinations to 20. With regard to air quality levels associated with background or distance sources that affect a general region as a whole, variations in terrain are not important. The concentrations of PM_{10} will be homogeneous over large areas and not affected by terrain variations. Siting methodologies are limited to simple situations in which a single dominant terrain is identified. At the present time, practical methodologies have not been developed for treating multiple sources in other than simple terrain situations. Practical models for treating coastal, ridge/valley, and irregular terrain for general urban sources or a major source in conjunction with general urban sources are not presented here. These two source categories are not applicable to the terrain type, leaving only the urban terrain situation. This leaves the terrain variation being treated only with respect to isolated sources.

There are only two terrain situations applicable to isolated sources since the isolated source with urban terrain is the same case as a major source within an urban area. This results in four categories of sites. Because of the range of alternative configurations of sources in urban areas, two categories are included, which may be designated complex and uniform.

As a result of these considerations, we have defined the following six representative siting situations for which specific guidelines are presented in the next section:

- o Regional scale (1)
- o General urban area
 - Complex (2)
 - Uniform (3)
- o Major source within urban area (4)
- o Isolated source
 - Plains (5)
 - Irregular terrain (6)

SECTION 5

SITE SELECTION METHODOLOGY

The general procedure recommended for selecting sites for monitoring PM_{10} is similar to that followed for monitoring any pollutant. Variations are recommended primarily with regard to specific methodologies or data that are needed for different topographical situations or different configurations of emissions. Procedures are discussed and recommendations are given for treating the six representative siting situations identified for PM_{10} in Section 4.

OVERVIEW OF METHODOLOGY

The siting of monitors is part of a continuing planning cycle for monitoring, which goes on in all air pollution control agencies and operating facilities. The three basic elements of the cycle, as shown in Figure 14, include defining the objective of monitoring, collecting monitoring data, and making judgments about air quality levels. The methodology for selecting monitoring sites is designed with the idea that this is part of an iterative process that has been performed before and will be repeated again in the future. The need for flexibility in the use of monitoring resources was clearly recognized by the Standing Air Monitoring Working Group (EPA 1977). This need has resulted in the development of three types of monitoring activities by state and local agencies, including National Air Monitoring Stations (NAMS), State and Local Air Monitoring Stations (SLAMS), and Special Purpose Monitoring (SPM). The locations of NAMS and SLAMS must be coordinated with EPA regional offices because these must be designed to meet EPA needs in addition to state and local needs. The siting methodology is applicable to all three types of monitoring stations and will be useful to industrial operating facilities as well as air pollution control agencies.

The general site selection process is illustrated in Figure 15. The procedure is applicable to all PM_{10} siting requirements, although the indicated steps may be considerably simpler for some types of monitoring requirements than for others. Each box shown in the diagram defines a data review and analysis step. The diamonds define decisions, and the rounded boxes define data needs. The process is divided into the following six steps, which are performed in sequence:

1. Analyze existing PM monitoring data
2. Review local situation to determine adequacy of mapping analysis and/or to select a modeling procedure
3. Model air quality scene (if necessary)
4. Determine network requirements




Figure 14. Planning cycle for monitoring.




Figure 15. Procedure for selecting PM₁₀ monitoring sites.

5. Determine monitoring sites and placement
6. Document and update site exposure experience.

Site planning may vary in scope of responsibility and may include any of the following:

- Design multipurpose network
- Supplement existing network for specific purpose
- Design single-source impact or compliance monitoring network
- Monitor a designated area or location.

Guidelines for performing each step in the site selection process and variations that deal specifically with each of the six types of siting situations are described in the subsequent subsections.

ANALYZE EXISTING AMBIENT PM MONITORING DATA

In order to devise a monitoring strategy and select monitoring sites, the monitoring planner must hypothesize the historical spatial distribution of PM_{10} concentrations over the area of concern. An adequate data base of related measurements, such as for TSP matter, may be available to meet this need. If not, the distribution must be estimated by mathematical simulation modeling or by a reasonable, physically based qualitative analysis. The best method of estimating the distribution of air quality levels will depend on the amount, type, and quality of available information. The information of interest includes the following categories:

- Suspended particulate matter measurements
- Locations and amounts of particulate emissions
- Air pollution climatology and meteorology data
- Maps of topographical features.

As a general rule, the amount of monitoring data available to help design a monitoring network or site new monitors is either nonexistent or very incomplete. However, with regard to siting new PM_{10} monitors, there is likely to be a wealth of hi-vol monitoring data for TSP concentrations that can be very helpful. Other relevant ambient PM measurements include IP measurements, tape sampler measurements, and various types of direct and

indirect PM measurements. The EPA SAROAD data base, available from EPA regional offices, is a convenient source of much of the available data. State and local air pollution control offices are also important sources of additional data and information about other data that may have been collected by nongovernment parties or in special studies.

After assembly of all available data and elimination of data that are suspect because of poor quality control, a decision is made as to whether the available data is sufficiently dense to justify mapping analysis, or whether single-station analysis is more valuable. Generally, unless measurements are available from at least six sites concurrently, mapping analysis is not practical.

Mapping Analysis

When performing mapping analyses, different types of measurement data should not be mixed on the same map unless an adequate calibration correction is made for different types of data. If corrections are to be made, it would be convenient if the different types of measurements were corrected to estimates of PM₁₀ concentrations. As a minimum, two types of maps should be constructed, including one for annual means and one for peak 24-hour concentrations (not concurrent) for each year of data, particularly the most recent years. In addition, it will be useful to plot concurrent 24-hour data for a few days that are distinguished by having one or more high values. The maps may be constructed by locating the observing sites on a convenient mapping display. The appropriate values may be entered at each site to provide a guide for drawing a set of representative contours of concentrations. The number and value of contours to be drawn will depend on the range of values observed and the nature of their spatial distribution. Computer graphics packages are available to perform the contouring analysis if manual analysis is not practical. Generally, about six contours will provide a useful display. However, as few as one or as many as 10 may be appropriate, depending on the magnitude of the range relative to the mean of the values observed. The maps will be used to identify representative spatial scales and preliminary siting selections.

While the mapping and station analysis data may be helpful in identifying the spatial distribution of PM₁₀, they may be inadequate. Having analyzed the available data, the monitoring planner must consider whether modeling is needed to supplement the available monitoring data. Consideration should be given to gradients evident in the observations, locations of major sources, terrain, and meteorology. In most cases the available PM observations will not be adequate for planning a new monitoring network.

Single-Station Analysis

When single-station analyses are performed, it is desirable to identify the significant influencing factors that affect the PM₁₀ air quality levels observed. This identification process will help determine how wide an area

the station represents. Conclusions drawn from one station should be compared with results from other stations in the area of interest. Trends and frequency distributions help in analyzing single-station data. Case study analyses of peak values will also be helpful. Figure 16 shows an example of 12-month running means for three sites in Youngstown, Ohio. When significant trends exist, they may indicate the influence of a nearby source. This would be especially true if trends at one site are more pronounced than at other sites. The down trends at the three Youngstown stations might be attributed to decreasing steel production in the local area. The differences among the stations might be attributed to the locations of sites relative to steel production areas and the prevailing wind directions. Shorter averaging periods, such as 3-month averages, would be helpful in identifying seasonal variations that might be associated with specific sources or meteorological conditions.

An example of statistical analysis of single-station data is presented in Table 9. Locations that have similar frequency distributions, particularly over a period of several years, can be considered to be in homogeneous areas. To further support the identification of homogeneous areas, it is useful to review meteorological conditions associated with a selected range of high values. Because TSP measurements represent 24-hour values, a good deal of care is required in selecting meaningful meteorological values. The prevailing (most frequent) and the range of wind directions corresponding to the measurement period are useful. Wind persistence (ratio of vector mean to scalar mean wind speed), height and magnitude of nocturnal temperature inversion, scalar average wind speed, and range of Pasquill stability categories (see definition in Turner 1970) are other meteorological parameters that may show consistent values with the high TSP measurements. If the meteorological conditions associated with high measurements differ significantly between monitoring sites, this result indicates that the sites represent different zones of air quality and has an important bearing in planning a monitoring network.

Another useful single-station analysis is the pollution rose. Figure 17 shows pollution roses constructed for four sites near a coking plant. The pollution rose is constructed by computing the average measured concentration for all values when the prevailing wind was in a given direction. The values may be limited to days when the wind persistence index (ratios of vector to scalar wind speed) exceeds a certain value. In Figure 17, the data include only days with a wind persistence index equal to or greater than 0.85.

REVIEW OF LOCAL SITUATION

An important step in the process of selecting monitoring sites is to identify the unique local influences that are affecting air quality. The types of topographical features, the magnitudes of PM emissions, and the locations of both with respect to one another have a major impact on where the worst air quality levels will occur. In assessing the value of available monitoring data and in selecting an air quality simulation model, it is necessary to take these local influences into account. After a brief




Figure 16. Twelve-month running geometric means (Pickering, Villardo, and Rector 1981).

TABLE 9. TSP DATA SUMMARY FOR SAROAD STATION #391720001
 (Units in micrograms/m³) (Pickering, Vilardo, and Rector 1981)

YEAR	1973	1974	1975	1976	1977	1978	1979	1980
# OF READINGS :	59	81	95	109	113	110	113	79
GEOMETRIC MEAN:	122.5	114.2	109.2	90.2	99.2	95.9	95.0	93.1
GEOMETRIC S.D.:	1.8	1.6	1.6	1.5	1.7	1.7	1.5	1.5
HIGHEST BY LARSEV EXTRP:	635.4	460.4	406.4	326.1	440.3	431.4	233.5	319.5
1ST HIGHEST: DATE :	486.0 730416	296.0 740117	314.0 750419	259.0 750915	275.0 770310	368.0 780426	273.0 790322	355.0 900530
2ND HIGHEST: DATE :	339.0 730426	281.0 740906	277.0 750924	204.0 750924	231.0 771106	237.0 781122	226.0 791123	194.0 900807
# OF READINGS EXCEEDING 250 :	4	4	3	0	1	1	1	1
# OF READINGS EXCEEDING 150 :	24	20	22	17	27	19	3	10
RANGE								
0-55:	9	11	15	29	25	27	36	15
56-130:	20	37	48	54	49	48	52	46
131-195:	20	22	20	23	32	27	11	16
196-250:	6	7	9	3	5	7	3	0
251-325:	2	4	3	0	1	0	1	0
326-390:	1	0	0	0	0	1	0	1
391-455:	0	0	0	0	0	0	0	0
>455:	1	0	0	0	0	0	0	0




Figure 17. TSP roses for four sites near a coking plant (Pickering, Vilardo, and Rector 1981).

description of the information needed, suggestions are given for steps to take in evaluating available air quality and for estimating PM₁₀ air quality levels by the use of mathematical models.

Emission Data

Information on the locations and magnitudes of sources of particulate matter emissions is needed. The influence of PM₁₀ sources can be determined by the use of air quality dispersion models and graphical aides that treat the contributions of sources to receptor locations, and by qualitative interpretation of the model results in the light of known topographic influences and monitoring data. Available sources of data and how they may be used in monitor siting analysis is provided here.

Two useful items of information are a detailed and accurate land use map and an accurate point source emission inventory. Large-area, statewide, or multistate maps are needed to show the locations of major population and industrial areas. Smaller area maps that show the size and location of different types of urban development within a single city are also needed for most monitoring objectives. There are many sources for the large-area maps. City-size land use maps are usually available from city and county planning offices. U.S. Geological Survey maps or Sanborn maps may be useful if other sources of land use maps are not available. Another very useful source of data on land use is the U.S. Geological Survey's records of aerial photographic coverage and space imagery. Reference files of data available on microfilm are maintained at the EROS Data Center of the U.S. Geological Survey in Sioux Falls, South Dakota. (See Appendix B for recommended contacts.)

Detailed information on specific sources of particulate emissions is available in state and local emission inventories. Both area and point source emission data are needed. Area source emissions are typically estimated on a countywide basis. However, estimates are frequently allocated to a fine grid in order to provide inputs to dispersion models or for other purposes. Gridded area source data that include location, emission rate, and stack parameters (e.g., temperature and volume flow rate) are needed. When accurate and complete, the NEDS data available from EPA include peak and average emission rates and seasonal variations in addition to the minimum information on location and emissions.

In addition to the emission inventory, census data and traffic data may be used to help define the spatial distribution of particulate emissions, particularly emissions associated with fuel combustion for space heating and emissions from vehicle kickup and tailpipe exhaust. If seasonal variations of emissions due to space heating are not available, they can be estimated on a seasonal or daily basis by use of degree days.¹

¹ A degree day is the amount that the average of the daily maximum and minimum temperatures is less than 65° F. Days on which the average is 65° F or greater are not counted.

Emission data for particulate matter are most complete and most accurate for stack emissions from large point sources. However, the principal sources of PM₁₀ concentrations are fugitive emissions, secondary particles, and emissions from automobile exhaust (Watson, Chow, and Shah 1981). Special attention is needed to ensure that the emission inventory is reasonably accurate with respect to industrial material handling operations, fumes from uncontained processes, mechanically reentrained road dust (both paved and unpaved roads), and windblown dust from disturbed soil, or a variety of industrial sources (Pace 1980).

Topography

The topography of an area will affect the transport and dispersion of pollutants released to the atmosphere. It is important to take note of topographical features in evaluating how adequately monitoring data represent the expected air quality levels and in selecting a modeling approach for simulating air quality levels. The following topographical features are of interest:

- Shorelines of major bodies of water
- Boundaries of significant urban areas (primarily covered by buildings and pavement)
- Significant terrain elevation features, including ridges, valleys, and areas of complex terrain.

The influence of topography on atmospheric transport is discussed in Section 4. The location of air monitoring sites in relation to sources of PM emissions must be reviewed in the light of these influences. An air pollution meteorologist may be consulted regarding the significance of topographical effects, if there is a doubt about the effect.

The locations of these features are easily identified on topographical maps available from the U.S. Geological Survey.

Reviewing Local Effects

Having assembled data that describe the local situation with regard to measurements of air quality, sources of emissions, meteorology, and terrain, the monitoring site planner is ready to assess the nature of these influences and determine whether to use modeling or qualitative analysis for assistance in selecting monitoring sites.

With regard to sources of particulate emissions, it is necessary to identify the locations of major sources and the quantity of emissions emanating both from stacks and as fugitive dust. Smaller sources of particulate emissions may be represented as area sources, e.g., as emission densities over 1 km squares. The area source emission densities should include particulate emissions from fuel combustion by smaller commercial and industrial sources, by residences, and by all types of mobile sources; also, process and fugitive dust emissions from industrial, waste disposal, and construction operations should be included. Guidelines on how to conduct an emission inventory and to allocate emission data to a gridwork are available from EPA (1973) and are not documented here. Both annual mean and seasonal, monthly, or daily maximum (if they are significantly different from the annual) emission rates should be determined. When plotted on maps, the area emission densities (both mean and maximum) will indicate areas of relative maximum and minimum emission levels and the degree of homogeneity in the area source emissions over the monitoring area of interest.

The nature of major topographical features and their locations relative to the sources of particulate emissions need to be identified. Major topographical features include coastlines, ridge lines, valley walls, and hilltops. In addition to specific topographical features, the area may be generally characterized by its roughness, e.g., built-up urban area, moderately rough rolling hills or river valley, or extremely rough valleys and ridges of a mountainous area. The treatment of terrain roughness is further complicated by the need to deal with terrain transitions. Cities and other areas of interest are frequently located near the base of a mountainous area or on a coastline where major terrain transitions exist.

While the location and nature of terrain features help to identify their influence, meteorological data are the demonstrated evidence of the effect. All of the air quality models recommended in the EPA Guideline on Air Quality Models (Revised) (1986) assume that meteorological conditions are homogeneous between all combinations of sources and receptors. Therefore, the available meteorological data should be reviewed to delineate areas and time for which the homogeneity assumption and the recommended models are applicable.

The single most significant meteorological parameter that must be homogeneous is wind direction. Since wind direction at a single site is generally accurate within 10° azimuth,² the variance in wind direction differences between sites should not exceed the sum of that variance due to measurement errors at the two sites. A useful rule of thumb is that the standard deviation of the differences in wind direction at two sites should not exceed $\sqrt{2}$ times 10°, or be less 15°, if the two sites are assumed to be measuring the same wind direction.

²This is related to the spatial representativeness of the observations and not the accuracy of the wind vane.

If meteorological data are not available to demonstrate the homogeneity of meteorological conditions, one can require that there be no major topographical features between sources of pollution and potential receptor monitoring sites in areas selected for modeling analysis. While this may be helpful in the immediate area, it does not treat indirect effects in nearby areas due to wind flow away from major topographical features. Lake breeze fronts and valley drainage flow fronts are examples of air boundaries that lie away from the topographical features that generate them. Winds on opposite sides of these air boundaries may differ by 90° or more, and the boundary may lie several miles away from the terrain feature. Air quality models that treat the effects of these terrain-generated air boundaries are under development and evaluation. One important effect of these boundaries, namely limited vertical mixing, can be treated by the available models.

Is the Analysis of Monitoring Data Sufficient?

The patterns and directions of maximum levels may differ for long- and short-term PM₁₀ concentrations. Both types of patterns should be reviewed separately. The important judgment to be made is whether the effects shown by the monitoring data are reasonable in the light of other available information, or whether modeling is needed to better define the spatial pattern of PM₁₀ concentrations.

In order to be useful for siting purposes, the monitoring data should define the shape and magnitude of the air quality pattern. Based on the distribution of sources, topography, and meteorology, the pattern should reflect these influences or at least not be inconsistent with respect to them. If these expectations are met, one may accept the pattern shown by the monitoring data as adequate. If the expectations are not met, a more detailed analysis based on results from air quality simulation models or from supplementary mobile monitoring may be required. There are two types of comparisons that can be made to help judge whether the air quality patterns are acceptable. One comparison examines the time history of the pattern. The other comparison examines the shape of the air quality pattern with respect to the shape of the pattern of emission densities and topographical features.

If the patterns of annual means or maximum 24-hour concentrations for several years show the same shape and same locations of peaks when superimposed on each other, the pattern is consistent with time. This consistency is evidence of a stable pattern, which is a reasonable guide for planning monitoring sites. If the pattern is changing with time, the analysis may be adequate, but the reasons for the changing pattern should make sense in terms of changes in sources or in meteorological conditions. If there are no apparent reasons for the changes, modeling results should be obtained and reviewed.

Emission densities that are chronologically consistent with the air quality data should be plotted and used to generate contour patterns. Topographical features may also be located on these patterns. When the emission density contours are superimposed on the air quality patterns, there

should be a reasonable relationship. One possible cause of deviations might be due to significant amounts of emissions from stacks. The heights of the stacks should be noted as an aid in identifying this influence. As a general rule, most IP and TSP emissions are from ground-level sources; however, uncontrolled or undercontrolled emissions from stacks can be major sources of pollution, which significantly alters the pattern of air quality from what would be observed from ground-level sources. A reasonably consistent pattern would be one in which the air quality pattern is offset from the emission pattern in the direction of prevailing wind flow. If the influence of major peaks in emission density are not evident in the air quality pattern, a modeling analysis may be helpful in identifying the magnitude of the pattern deformation that can be expected.

Selecting a Model

Major unsolved problems are associated with modeling PM concentrations. When using the results of model simulations to select monitoring sites, one should keep the following uncertainties in mind:

- Most of the IP matter that makes up the concentrations occurring in urban locations may not originate from local sources.
- Air quality simulation models recommended in the Guideline (EPA 1986) do not treat the physical and chemical processes that alter the size of airborne particles and may not adequately treat their removal by wet and/or dry deposition.
- Emission factors and emission data that are available to estimate emissions of particulate matter do not identify IP emissions as a portion of total PM emissions.
- Most IP emissions originate from fugitive sources rather than stacks. The uncertainty associated with available fugitive emission estimates is very high.
- Air quality simulation models recommended in the Guideline (EPA 1986) very simplistically treat the topographical influences on atmospheric transport and dispersion of pollutants.

In spite of these uncertainties it is still useful to use modeling to identify areas of relatively good and poor air quality and to select sites for a monitoring network. Models that may be useful in each of the six monitoring situations described at the end of Section 4 are listed in Table 10. No modeling results are needed to site a regional scale monitoring station, because this type of site is representative of a large, relatively homogeneous area of air quality in which influences from nearby sources are

TABLE 10. AVAILABLE EPA MODELS FOR SIX MONITORING SITUATIONS*

Monitoring Situation	Recommended model	
	Annual Mean	Maximum 24-hour
Regional scale	None**	None**
General urban area		
-- uniform	CDM-2.0	RAM
-- for complex sources in urban areas	ISC	ISC
Urban area with single or multiple major IP source(s)	CDM-2.0	RAM
Single source with terrain height below stack top# (complex source)	CRSTER	CRSTER (ISC)
Single source near terrain above stack top§	COMPLEX I*** or VALLEY	VALLEY or COMPLEX I***

* Available on EPA's UNAMAP Version 6.

For multiple sources where it is not appropriate to consider the emissions as located at a single point, the MPTER model is appropriate.

§ COMPLEX I and VALLEY are considered screening techniques. For regulatory purposes, COMPLEX I should be used only with onsite meteorological data as input.

** Selection of model is a case-by-case decision.

*** The SHORTZ model is an appropriate screening technique for use in urbanized valleys with onsite meteorological data as input.

negligible. With regard to selecting a model, a distinction is made between monitoring situations with a single source in a rural setting and monitoring situations with multiple sources in an urban setting. A distinction is also made between rural monitoring situations with and without complex terrain. For modeling purposes, complex terrain is usually defined as terrain that exceeds the stack top of the source.

For estimating annual means, the CDM model is appropriate for multiple source urban situations, and the CRSTER model is recommended for single-source rural situations in the absence of complex terrain. In the presence of complex terrain, the COMPLEX I screening model for rural areas and the SHORTZ screening model for urban areas (available in the EPA UNAMAP Program System, Version 6) are more appropriate than VALLEY, if at least 1 year of onsite meteorological data are available. These models are relatively easy and inexpensive to use. For estimating maximum 24-hour concentrations, the RAM model is recommended for urban situations and CRSTER for single-source, rural situations. When the single source or multiple major IP sources are complex (as is frequently the case when treating fugitive emissions from large industrial sources), the ISC model is recommended in place of RAM or CRSTER.

Procedures for using these models and for compiling data for them are discussed in detail in the Guideline on Air Quality Models (Revised) (EPA 1986), and the PM₁₀ SIP Guideline. In addition, Appendix A contains a list of cities for which STAR data have been compiled. These data should be helpful to modelers who wish to execute CDM or ISCLT. Appendix B contains a list of information sources that should also prove helpful.

Selecting Representative Sites Without Monitoring or Modeling Data

There may be situations in which it is not possible to use monitoring data or the results of a modeling analysis to define the pattern of air quality levels in an area that is to be monitored. In this case, the monitoring network can be planned by identifying representative sites on the basis of available information on sources of emissions, climatological data, and topographical considerations. Section 4 presents a discussion of how these physical characteristics of the area to be monitored influence the air quality with respect to PM₁₀. On the basis of these considerations, six representative monitoring situations were identified. Observations from other locations and previous modeling analyses of general classes of source influences may be used to select PM₁₀ monitoring sites for these situations.

Figures 18 through 21 summarize the steps that need to be followed in selecting sites for the six types of representative monitoring situations. Figure 18 treats regional scale siting. Figure 19 treats siting neighborhood-scale sites in urban areas, and Figure 20 treats siting middle scale sites with and without the presence of major point sources. These two figures cover the three urban representative siting situations identified in Section 4. Figure 21 treats siting around an isolated major point source in flat or




Figure 18. Steps for locating regional scale monitoring site.




Figure 19. Steps for locating a neighborhood scale monitoring site in an urban area.




Figure 20. Steps for locating micro-/middle scale monitoring sites in urban areas.




Figure 21. Steps for locating monitoring sites near isolated major sources.

complex terrain. This includes two of the representative siting situations. These three figures deal with all six representative siting situations. Specific guidelines that may be used in performing these steps are discussed below.

Regional Scale Monitoring Sites

Regional scale monitoring sites are needed to measure background levels of PM₁₀ that are transported into the area being monitored. It is important that regional scale monitoring sites not be affected by nearby sources, which would significantly alter their scales of representativeness, for large periods of time. It may be necessary to use two or more sites to measure background concentrations when a single site cannot be found that is never influenced by nearby sources. Figure 18 suggests four steps to follow in selecting the site(s).

The first step is to identify all major urban areas and all major operating facilities that may have an effect on PM₁₀ air quality levels in the area of concern. Locations and populations of nearby urban areas are readily determined from maps and standard library references. Large cities as far away as 100 km are of concern. This is based on the use of models to estimate the distance to which emissions of 1.0 $\mu\text{g}/\text{m}^2/\text{sec}$ from a metropolitan area 40 km in diameter will extend before the peak concentration is less than 20 $\mu\text{g}/\text{m}^3$ under neutral atmospheric stability conditions and a light wind speed of 2 m/sec. Distances from smaller cities are less critical; e.g., a concentration of 20 $\mu\text{g}/\text{m}^3$ will extend 60 km downwind of a city that is 20 km in diameter and 15 km downwind of a city that is 10 km in diameter. These estimates were derived using the methodology for Estimation of Concentration of Area Sources proposed by D.B. Turner (1974). A concentration of 20 $\mu\text{g}/\text{m}^3$ is significant because this is the 1-hour concentration that is likely to be associated with an observed 24-hour concentration of 5 $\mu\text{g}/\text{m}^3$, and because 24-hour concentrations as low as 5 $\mu\text{g}/\text{m}^3$ are small in comparison to observed variations in regional scale IP concentrations. Annual mean concentrations of IP at 17 monitoring sites in nonurban areas (Watson, Chow, and Shah 1981) showed a mean of 30 $\mu\text{g}/\text{m}^3$ and a standard deviation of 9 $\mu\text{g}/\text{m}^3$. A concentration of 5 $\mu\text{g}/\text{m}^3$ is about half of the standard deviation of regional scale or background level concentrations of IP.

Major operating facilities can be identified from state emission inventories that are available from state and Federal offices listed in Appendix B. Estimates of significant impact distances are listed in Table 11 for various emission rates and effective source heights. Effective source height refers to the height above the ground at which the center of the plume of emissions from a plant is transported. This includes the height of release from a stack or vent plus the rise that may occur due to momentum and/or heat in the exhaust stream. For fugitive emissions blown from the ground or vented from open windows and doors, the effective height may be essentially zero or ground level. All areas affected by major sources can be circled on


a map by a radius scaled to the significant impact distance. The circles should include the urban area and major sources in the area being monitored as well as nearby sources outside of the area. Any areas not covered by circles are suitable for regional-scale monitoring sites. Sites within 40 m of major highways (see Figure 22) or unpaved roads are also not suitable. This is because emissions from motor vehicles in heavy traffic and the reentrainment of dust from unpaved roads are also significant sources of particulate matter. If there are no uncovered areas or if the uncovered areas are unsuitable because of accessibility or other considerations, it is necessary to use more than one site to monitor the regional scale. Operations from different sites would be applicable to background levels on different days.

TABLE 11. DISTANCES FROM MAJOR POINT THAT AFFECT REGIONAL SCALE MONITORS

Emissions rate (g/sec)	Effective source height (m)	Downwind distance (km) beyond which the product of concentrations and wind speed does not exceed $40 \mu\text{g}/\text{m}^3 \times \text{m}/\text{sec}$ for four Pasquill stability classes			
		B	C	D	E
400	all	14	30	>100	>100
100	300	7	14	33	--*
	<150	7	14	50	>100
40	300	4.5	7	--	--
	100	4.5	8	25	50
	<70	4.5	8	27	57
10	>300	--	--	--	--
	100	2.1	4	8	11
	<30	2.1	4	10	19
4	100	1.2	2.0	--	--
	<30	1.4	2.4	5	9

* Dashes indicate values as high as $40 \mu\text{g}/\text{m}^2/\text{sec}$ do not occur.

NOTE: $40 \mu\text{g}/\text{m}^2/\text{sec}$ represents the lowest value that is expected to produce a 24-hour concentration contribution of at least $5 \mu\text{g}/\text{m}^3$. This is based on the assumptions that a 24-hour value will be about 25 percent of the 1-hour peak concentration and that wind speed will be 2 m/sec. A concentration contribution of $5 \mu\text{g}/\text{m}^3$ is small in comparison to variations in regional scale IP concentrations (see text). Tabulated values are based on curves from the EPA Workbook of Atmospheric Dispersion Estimates (Turner 1970).



LEGEND: SIZE x-x-x COARSE ♦-♦-♦ FINE □-□-□ TOTAL

Figure 22. Average measured PM concentrations (downwind less upwind) from a major Philadelphia highway (Burton and Suggs 1982).

When two sites are needed to monitor background concentrations, one station should be selected that is upwind of the area of concern most frequently or downwind least frequently. If this site cannot be clear of contributions from nearby sources for all wind directions, a second site is required. This site should be selected to supplement information obtained from the first site to the maximum extent possible, so that one site or the other is measuring the background level at all times. One strategy is to place the second site in the direction that is upwind of the area of concern second most frequently. If the first and second most frequent wind directions are more than 120° apart, this may be a good plan. If they are less than 90° apart, both sites may be downwind of the primary area of concern or of the same large source on the same day. This risk can be minimized by selecting a second site that has bearing from the primary area of concern that is 180° from the bearing to the first site. A climatological wind rose showing the frequency with which the wind blows in each direction is useful for selecting sites. The map of circled major sources may be used to show areas that are not affected by major sources for specific wind directions. Figure 23 shows an example. In this case the monitoring agency must select a site within 24 km (15 miles) of its offices. However, the impact zone of the city (City A) extends out 90 km, so the agency must monitor on both sides of the city. The most frequent and second most frequent wind directions, shown in the lower right-hand corner of the figure, are about 120° apart. However, a site directly south of the city is not desirable because of interference from City D. An alternative site slightly to the east of south would still be representative for south winds and less affected by City D. Another alternative site is 180° from the direction for which the first site was selected. Selected regional scale monitoring sites should not be influenced by topographical features. Sites along shorelines, in or at the base of pronounced valleys, near sharp bluffs; or in low-lying areas should be avoided. The topography around the most suitable sites is uniform.

Urban Areas with No Major Point Sources

Some urban areas will have no major sources of PM_{10} emissions. Because most of the measured IP concentrations come from geological materials, from motor vehicle traffic, or from secondary aerosols formed in the atmosphere (EPA 1981; Watson, Chow, and Shah 1981), this may be the situation in a number of areas for which monitoring is planned. Figures 19 and 20 describe steps that may be used to select monitoring sites in such situations.

The first step is to obtain and analyze traffic and urban development data that can be used to identify potential variations in otherwise homogeneous neighborhood scale patterns of PM_{10} concentrations. Areas of high traffic density, such as major highways, shopping centers, sports areas, amusement parks, airports, and parking facilities, need to be identified and analyzed. Also, areas that are concentrated sources of particulate matter emissions, such as solid waste handling facilities, unpaved roadways, central business districts, and construction operations, need to be analyzed.




Figure 23. Example of background site selection within 24 km (15 mi) of City A.

Figures 24 through 26 show the model peak concentrations downwind of highways that occur within 15 m of the roadway. Data in Table 12 show the peak concentrations expected downwind of other sources that are centers of intensive traffic-generated emissions. These guides can be used to estimate where the pollution increases above general neighborhood levels will occur, which can be expected in the vicinity of these sources.

On the basis of the magnitudes of the PM₁₀ enhancement predicted for all the traffic-concentrated areas and the locations of the source areas relative to the downwind edge of the city for the most prevalent wind direction, a decision must be made on how many monitors will be used to measure the maximum PM₁₀ concentration. Unless a single source or source area is clearly more significant than any other, a number of sites should be selected as potential peak concentration monitoring sites. These sites will be representative of micro- or possibly middle scale areas. The monitoring site should be located as close to the source as possible without infringement or interference from the source. The most suitable sites are within 5 to 15 m of the sources on the downwind side of the prevailing wind direction. It is usually not practical to locate a site less than 5 m from a source. Generally, one site is sufficient for each source area.

Neighborhood sites are needed to represent the areas that encompass or surround the peak concentration sites. Due to variations in the type and intensity of land uses throughout an urban area, a large metropolitan area may be characterized by well over 1000 different neighborhoods. The process of identifying and classifying all neighborhoods in a metropolitan area in terms of their potential PM₁₀ air quality levels is a worthwhile effort for air pollution control planning purposes. The use of monitoring or modeling data is the most satisfactory way to making such classifications. However, it is also possible to characterize neighborhoods in a qualitative fashion by preparing a detailed emission inventory that identifies the spatial distribution of emissions from the many indirect and fugitive sources of PM₁₀.

By examining the locations and magnitudes of these sources in relation to the climatology of wind direction frequencies, one can rank neighborhoods in terms of their expected levels of high PM₁₀ concentrations. Neighborhoods that encompass the middle or microscale areas that are expected to contain high concentrations are clearly high priority neighborhoods for monitoring sites. One or two neighborhoods adjacent to the maximum concentration neighborhoods are desirable secondary sites. A third category of monitoring sites includes neighborhoods that are of special interest because of large population density; because of rapid growth expectations; or because of a highly sensitive population such as elderly (e.g., nursing home), ill (e.g., hospital), or young (e.g., day care center).

Sites in the third category of interest may also meet the second category of interest. There are no firm rules to determine how many sites to monitor. Each monitoring jurisdiction must determine what its priorities are and how far down the priority list of potential sites it is able and willing to go.




Figure 24. Concentration as a function of wind speed, computed using HIGHWAY2 model.





Figure 25. Concentration as a function of wind direction, computed using HIGHWAY2 model.

Highway Data:
 4-lane, 12-m wide highway
 Traffic = 3000 vehicles/h
 Emissions = 0.28 g/vehicle/km.

Winds:
 Perpendicular to highway
 Wind speed = 4 m/sec.



LEGEND: PASQUILL STABILITY +---+ C △---△ E □---□ I

Figure 26. Concentration as a function of stability class, computed using HIRWAY2 model.

TABLE 12. MAXIMUM CONCENTRATIONS NEAR DOWNWIND
EDGE OF TYPICAL URBAN AREA SOURCES

Type Source	Typical Maximum 24-hour Concentration ($\mu\text{g}/\text{m}^3$)	References
Urban Expressway (1)	85	Burton and Suggs 1982
Street Canyon (2)	45	Ingalls 1981
Parking Garage* (3)	45	Ingalls 1981
Roadway Tunnel (2)	650	Ingalls 1981
Shopping Mall (4)	80	Ingalls 1981
Sports Stadium* (4)	10	Ingalls 1981

* Very high short term concentrations may occur near this source.

- (1) Based on observed upwind-downwind differences in IP over 14 hours, corrected to 24 hours and PM_{10} .
- (2) Based on a 24-hour average to peak ratio of 0.5, a vehicle emission rate of 0.28 g/km, and a peak traffic flow of 3000 vehicles/hour.
- (3) Based on model estimates and an emission rate of 0.085 g/min.
- (4) Based on CO observations of 2.5 ppm (24 h) for shopping centers, and 22 ppm (15 min) for sports stadiums, and ratio of PM_{10} to CO emissions of 0.0286.

Table 13 illustrates a rationale for selecting 15 sites. In this example, four neighborhoods are identified that potentially have high micro- and middle scale PM₁₀ levels. The neighborhoods that border on a neighborhood containing high concentrations are also expected to have a chance of exceeding the NAAQS for PM₁₀. As a result, two sites in adjacent neighborhoods will be selected. There are also three neighborhoods that contain health care treatment facilities with persons who are highly sensitive to air quality. After discussions with various officials responsible for providing funds for air monitoring operations, a decision is made to put monitors at 15 sites.

TABLE 13. EXAMPLE DETERMINATION OF THE NUMBER OF MONITORING SITES IN A METROPOLITAN AREA*

Priority	Type of scale for PM ₁₀	Recommended number of sites	(X) Number of areas	(=) Number of sites	
1	Includes selected micro- or middle scale site	1	4	4	
2	Adjacent to major source area	2			
3	Special interest	1	3	<u>3</u>	
				Total	15

* This case was selected to be representative of a city with a population of 500,000 and four major source areas. Smaller cities and cities with fewer source areas may require fewer monitoring sites.

Each neighborhood selected for monitoring must be reviewed carefully to identify areas containing micro- or middle scale PM₁₀ effects. Neighborhood scale sites must be selected to avoid these areas. The data presented in Tables 14 through 16 identify the distances to which middle scale effects extend from the types of sources associated with PM emissions. These distances should be shown as circles around sources in neighborhoods selected for monitoring.

TABLE 14. SIGNIFICANT IMPACT DISTANCES OF
SMALL GROUND-LEVEL AREA SOURCES

Area (m x m)	Emission rate (kg/km ² /day)	Maximum downwind distance (km) with significant impact*
250 x 250	10	0.25
	10 ²	1.0
	10 ³	5
500 x 500	10	0.6
	10 ²	2.5
	10 ³	14
10 ³ x 10 ³	10	1.4
	10 ²	7
	10 ³	45

* Based on 24 $\mu\text{g}/\text{m}^3$, F stability class and 2 m/sec wind speed. Estimated using Workbook of Atmospheric Dispersion Estimates (Turner 1970) by treating source as a point. This worst case situation is expected to produce a 24-hour concentration of 6 $\mu\text{g}/\text{m}^3$.

TABLE 15. SIGNIFICANT IMPACT DISTANCES OF HIGHWAYS

Average daily traffic (veh/day)	Maximum downwind distance (km) with significant impact*
100,000	0.22
50,000	0.11
25,000	0.05
15,000	0.02
12,000	0

* Based on 6 $\mu\text{g}/\text{m}^3$, Pasquill stability class D, and wind speed of 2 m/sec at 45 degree angle with highway. Estimated using EPA HIWAY2 model and vehicle emission rate of 0.28 g/km. Because concentrations downwind of highways are not sensitive to variations in wind direction, the worst case 24-hour concentration is based on a persistent worst case 1-hour concentration. This allows the effect to be comparable with worst case effects from elevated points (Table 16) and small areas (Table 14).

TABLE 16. SIGNIFICANT IMPACT DISTANCES OF ELEVATED SOURCES

Effective plume height (m)	Emission rate (kg/hr)	Critical Pasquill stability class	Maximum downwind distance (km) with significant impact*
30	30	C	3.3
	10		1.7
	3		0.9
100	100	A	1.2
	30		0.8
	10		0.5
300	100	A	1.2

* Based on $24 \mu\text{g}/\text{m}^3$ and 2 m/sec wind speed. Estimated using Workbook of Atmospheric Dispersion Estimates (Turner 1970). This worst case situation is expected to produce a 24-hour concentration of $6 \mu\text{g}/\text{m}^3$.

Monitoring Isolated Major Sources in Flat Terrain

Figure 20 suggested steps to be followed in selecting monitoring sites near an isolated major source. A distinction must be made between sources with the principal emissions from a tall stack and sources with the principal emissions from ground level. For ground-level sources, the maximum concentrations will occur immediately adjacent to the source in the most prevalent downwind directions from the source. Wind observations will easily identify the most suitable siting areas. Additional monitors may be used to help define the extent of the area near the source that has high concentrations and the neighborhood scale level of PM_{10} in the vicinity of the source. Two types of information can be helpful in determining the extent of the high impact area: (1) the relative concentration isopleths from the EPA (1970) Workbook of Atmospheric Dispersion Estimates and (2) annual wind direction frequency statistics published by the National Climatic Center (see Appendix A).

It is easily seen from the Workbook data that the peak concentration falls off rapidly with distance for ground-level sources. The peak concentration 100 m from the source drops by a factor of 10 at a distance of 40 km from the source for all stability conditions. The more stable the atmosphere, the more slowly the peak concentration drops with increasing distance from the source. The Workbook curves show that even for very stable conditions (Pasquill Class F), the peak concentration drops by a second factor of 10 within 1600 m from the source. These data show the microscale influences within 100 m of the source are at least 10 times greater than the middle scale influences from 100 to 500 m from the source. If there is public exposure within 100 m, it is important to locate a monitor there. Middle scale monitoring sites within 500 m of the source are desirable in each prevailing wind direction. One of the middle scale sites should be downwind for the wind direction that occurs most frequently with stable conditions and low wind speeds. A Star climatology analysis for the closest weather observing station maybe used to determine this direction (see Appendix A).

If the primary emissions are from a tall stack, the highest ground-level concentrations will be away from the source. Detailed manual computational procedures for estimating the magnitude and location of the maximum impact of tall stack emissions are given in Volume 10 of the EPA Guidelines for Air Quality Maintenance Planning and Analysis (Budney 1977). Figures 27 and 28 (taken from Budney 1977) show how the distance to the maximum short-term concentration varies with the effective height of the exhaust gas plume and atmospheric stability. Figure 27 treats sources in rural terrain, and Figure 28 treats sources in urban terrain. Budney's Guideline describes a method of estimating the effective height of the source. Because the PM₁₀ monitors will observe 24-hour and annual mean concentrations, the large variation in distance to the maximum concentration with variations in atmospheric stability class must be taken into account in selecting a site. It may be noted in Figure 27 that the maximum concentrations occur with the greatest instability (i.e., Class A). Therefore, it is important to site a monitor close to the source where the maximum contributions will occur under unstable conditions. As shown by Figure 27, this will be as close as 100 m to a source with a 20 m effective height and as far as 800 m downwind of a source with a 300 m effective height.

Another important factor in selecting a site is the persistence of the wind direction over the observation period. Because the wind direction is highly variable under unstable conditions and because persistent wind directions are generally associated with neutral (Class D) stability conditions, a good strategy is to select a second monitoring site at a distance associated with the peak for neutral stability. The distance downwind to the peak concentration will vary from about 350 m for an effective height of 20 m to between 15 and 20 km for an effective height of 300 m.




Figure 27. Downwind distance to maximum concentration and maximum relative concentration (x_w/Q) as a function of Pasquill stability class and effective plume height in rural terrain (Turner 1970).




Figure 28. Downwind distance to maximum concentration and maximum $\chi u/Q$ as a function of stability class and effective plume height in urban terrain (Budney 1977).

The peak concentration will be sharp, with high concentrations falling off rapidly with distance from the peak, when the peak is close to the source. This is a middle-scale effect, and the maximum impacts will be observed over an area within 200 to 300 m of the peak. The frequency of wind directions associated with only unstable conditions should be taken into account in selecting sites for observing the middle-scale peak.

When selecting a site to observe concentrations from a tall stack (effective height of 100 m or more) during persistent wind conditions (and neutral stability), the concentrations will fall off gradually with distance from the peak. The impacted area will be on a neighborhood scale, with high concentrations (within 25 percent of the peak) occurring at distances of 2 km from the peak when the effective height is 100 m and to distances of 10 km when the effective height is 300 m. Wind direction frequencies associated with neutral conditions should be used to site monitors. It may be noted that there is a large area within which to select a site.

Wind observations from remote sites (e.g., a regional airport) are very useful for selecting neighborhood-scale sites. When selecting a middle-scale site, it is necessary that the wind observations be representative of the very small scale area in the vicinity of the site. In the next section, topographical influences are discussed that may make wind observations unrepresentative. Suggestions are made for taking the local influences into account in selecting monitoring sites.

Monitoring Isolated Major Sources in Complex Terrain

There are a number of situations in which the complexity of the terrain in the vicinity of a major source will influence how pollutants are distributed in the nearby vicinity. These influences must be taken into account in siting monitors if the observations are going to achieve their objectives. Available meteorological observations may not be adequate to describe the effects, especially if they are taken from a single site. In particular, the effects of elevated terrain, coast lines, and urban structures need to be taken into account. The air flow characteristics in the vicinity of these types of terrain were discussed in Section 4. Suggestions are given here for using the topographical characteristics of an area to select monitoring sites and to modify the site selection guidelines for flat terrain.

Typical influences due to elevated terrain include two-sided boundaries such as a valley and one-sided boundaries such as a mountain range or a pronounced bluff. Air flow in a valley is subject to nighttime drainage down the slopes and along the valley floor, to upslope convection and fumigation during the day, and to channeled flow when strong winds blow diagonally across the valley. Near one-sided boundaries, emissions on the downwind side of a ridge or hill may become entrapped in the turbulent wake flow downwind of the ridge, or separated from ground-level when overshoot separation flow occurs over the ridge. Emissions near either one-sided or two-sided terrain boundaries may impact the terrain under very stable conditions with the flow

directed towards the elevated terrain. Each of these effects produces a pollution impact zone, which is associated with the terrain configuration. Monitoring sites are needed that measure the results of these effects. The following terrain-oriented sites are needed to supplement or replace sites that conform to flat terrain siting selections:

- Down- and up-valley in place of or in addition to downwind of the most prevalent wind directions
- Terrain elevation at the effective height of the source plume or at maximum elevation (if less than effective height) in prevailing downwind directions
- Nearest terrain elevation at effective height of source plume.

Near a lake or ocean coast, there will be an invisible boundary between the air influenced by the temperature of the underlying water surface and the air influenced by the temperature of the underlying land surface. A great difference in the two surface temperatures can significantly alter air flow in the vicinity of the coast line. The two effects that are of interest in selecting sites for monitors are (1) the tendency for the air flow to be perpendicular to the coast and (2) the formation of a vertical circulation with its axis centered on the coast line. The first effect indicates the need for a monitoring site directly inland from a source near the coast. The second effect indicates the need to have sites along the coast on both sides of the source. These sites are to catch the impact of air that initially moves inland, but that subsequently rises, moves back over the water, sinks, and blows back inland at low levels. Under these conditions, pollution moves perpendicular to the apparent ground-level wind observations. The magnitude of the air pollution effect from this recirculation of air over the coast line is difficult to anticipate. It could be an important, controversial contribution to establish. These siting considerations should be taken as supplements to the guidelines given for more uniform terrain situations.

Urban Areas with Major Point Sources

When major point sources of PM emissions are present in an urban area, there is a need to consider the impacts of the point and the urban area sources individually and of their joint overlapped effects. Siting considerations relating to both urban areas and points as individual sources were previously discussed. The overlapped effects can be best identified by considering lines connecting pairs of nearly individual sources. When the connecting lines parallel one of the prevailing wind directions, locations that are downwind of both sources and near the maximum of the second downwind source are likely locations of maximum 24-hour PM₁₀ concentrations. However, the maximum annual mean concentration is likely to be in a location that is central to the individual sources. Such a location will be affected

by different sources at different times, rather than by the simultaneous overlapping of the effects of two or more sources. These two qualitative criteria regarding the impact of overlapping effects can be used to help identify locations that are probably sites of maximum concentrations. These criteria are helpful when a modeling analysis is not available to evaluate the joint effects of multiple sources.

Simple calculations and graphical analysis may be used to apply the above siting criteria for multiple sources. For instance, in deciding which pairs of overlapped source contributions are most significant, the relative emission sites and distances between sources should be taken into account. The contribution of a source to the PM₁₀ concentration at any location is directly proportional to the emission rate and inversely proportional to the distance from the source. Although the distance relationship is a complex function of atmospheric stability conditions and the effective height of the emissions, the distance effect is most frequently very nearly proportional to the inverse square of the distance. For the purpose of evaluating the importance of overlaps from the sources, the following relationship can be used:

$$A = \frac{E}{D^2}$$

where A = Relative contribution from second source
E = Emission rate (second source)
D = Distance to second source.

To illustrate the use of this relationship, consider a major urban freeway with a nearby source only 0.5 km away that emits 10 lb/hr. The overlap contribution from the source will be more important than any other source emitting 100 lb/hr or less at a distance of 1.6 km or more away, since

$$A_1 = \frac{10}{(0.5)^2} = 40$$

$$A_2 = \frac{100}{(1.6)^2} = 39$$

A good way to define the scale and locations of the effect of overlapped sources is to construct a representative graph of peak concentrations versus distance downwind of the second source. This can be done quite easily by the use of the EPA Workbook of Atmospheric Dispersion Estimates (Turner 1970) or

Volume 10 of the EPA Guidelines for Air Quality Maintenance Planning and Analysis (Budney 1977). The following steps may be used:

1. Pick a representative stability condition (e.g., C stability) and find the appropriate xu/Q versus distance graph.
2. For the larger of two overlapping sources, use the selected graph to find a dozen pairs of xu/Q and distance values that straddle the peak xu/Q value, and multiply the xu/Q values by the emission rate to get $(xu)_1$ values.
3. Add the distance (D) between the two sources to the distances read in step 2 and read a new x/Q value from the graph for each new distance.
4. Multiply the second set of xu/Q values by the second source emission rate to get $(xu)_2$ values.
5. Add the two sets of xu values together and plot the sum as a function of the initial distance (without D added).
6. Repeat steps 2 through 5 for additional distances to make the curve complete.

Table 17 shows a sample work table for use with the above steps. The procedure may be repeated for more than one stability class to help identify a range of distances from the source within which the maximum concentrations will occur. The buildup and fall off of concentration with distance will help identify the distance scale that the combined concentrations will affect.

TABLE 17. SAMPLE WORK TABLE FOR OVERLAP EFFORTS

Distance from larger source (x)	$(xu/Q)_1$	$(xu)_1$	Distance from smaller source (x+D)	$(xu/Q)_2$	$(xu)_2$	$(xu)_1$ + $(xu)_2$

This procedure is expected to be adequate for most monitor siting purposes. However, the graphs referenced above do not include any effects of particle removal due to fallout or other atmospheric processes. Actual concentrations may decrease more rapidly with downwind distance than is represented by these curves. More accurate graphical representations of the relationship may become available in the future and should be used when appropriate.

When considering sites to measure long-term concentrations that include contributions from many sources, a simple numerical evaluation procedure may be used to help select the best sites. Over a long-term period, both the distance from the source and the frequency with which the wind blows from each source to the potential monitoring site must be taken into account. The following simple source weighting function takes these two effects into account:

$$B = \sum_{i=1}^N \frac{E_i f_i}{(D_i)^2}$$

where B = Monitoring site pollution index

E_i = Source i emission rate

f_i = Relative frequency with which wind blows from source i to the monitoring site

D_i = Distance from source i to monitoring site

N = Number of urban area and major point sources.

This site evaluation equation may be used to rank alternative monitoring sites. The best way to perform the site evaluation process is to plot the major urban area and major point sources on a map. A number of locations in the middle of the sources and close to or downwind of the larger sources may be selected as potential monitoring sites. The evaluation equation may then be used to score the relative pollution levels expected at each potential site. The highest score would indicate the site most likely to measure the highest PM₁₀ concentration.

SELECTION OF MONITORING SITES

Number and Locations of Monitors

The preceding steps have been concerned with developing a pattern of PM₁₀ air quality that occurs in an area of concern for which monitoring is planned. This may be an area administered by an air pollution control agency or an area impacted by a particular source. In either case, there are

three types of information regarding the patterns which are of interest, including:

- Maximum PM₁₀ concentration
- Background PM₁₀ concentration
- Area impacted by significant PM₁₀ concentrations.

Significant PM₁₀ concentrations may be levels associated with air quality standards, PSD increments, specific increments above background levels, or other criteria of interest. There is another type of site that does not involve a selection process (i.e., sensitive sites of special interest). In a simple pattern, there will be one maximum and a single regularly shaped contour that defines the area impacted by significant concentrations. Complex patterns have two or more peaks that may or may not lie within a single closed contour of impacted areas of interest. Unless one peak is much higher than the others, two or more peak areas will need to be monitored.

The number of monitors needed to define impacted areas will include a minimum of two and may include six or more depending on how large, how complex and how definitive the impacted area is. A single, well-sited monitor, located well away from any nearby sources or source areas, may be adequate for determining background concentrations. If it is impractical to locate a monitor far away from nearby sources, it may be desirable to select two nearby monitors, one or more of which is measuring background concentrations on any given day, depending on wind direction. Because PM₁₀ concentrations are measured over 24-hour periods and because the wind direction is frequently variable over a 24-hour period, this is a less desirable option than a single, well-sited monitor.

In planning and revising air monitoring plans, it is important to bear in mind that the need for monitoring data is dynamic and will change from year to year. Once the nature of the air quality pattern for PM₁₀ concentrations has been established or verified, fewer stations are needed to evaluate general ambient conditions and trends. This is especially true for areas where the ambient levels are well within acceptable limits and there is no significant impact area. Reducing the amount of resources allocated to fixed monitoring stations will allow resources to be reallocated to meet other special purpose monitoring needs.

Previous monitoring and modeling provide a first estimate of the PM₁₀ air quality patterns, but a large amount of uncertainty may still exist regarding both the shape and the magnitude of the pattern. Therefore, some monitoring resources should be allocated to verifying the assumptions made regarding the pattern. Two forms of monitoring are recommended for this purpose, including temporary sites and mobile monitoring. This type of monitoring is most effective when it is used in conjunction with modeling results to confirm or deny the influence of specific sources on air quality levels. An example of appropriate use of this type of monitoring is to

establish the validity of a kink or a bulge in the air quality pattern due to the influence of a specific nearby source or source area. Modeling results could be obtained to show the expected contribution of specific sources to the bulge. Air monitoring results along with appropriate meteorological data could be used to establish the validity of the influence. A temporary monitor could be moved from one location to another to investigate the validity of a number of these influences. The monitoring results would increase confidence in the modeling results or provide the basis for either model improvements or selection of a more accurate model.

Mobile monitoring can also be used to help establish the influence of specific sources. Mobile monitoring is effective when it is used to identify peaks in concentrations during crosswind sampling traverses downwind of large elevated point sources. Another effective use of mobile monitoring is to encircle area sources in order to establish concentrations upwind and downwind of suspected significant sources of ground-level fugitive emissions. A limitation in mobile monitoring is the need to use a continuous type of analyzer. Continuous measurements of PM will necessarily be based on physical measurement other than the weight of size-selected particulate matter collected on a filter. As a result, it will be necessary to correlate the mobile measurements with fixed station measurements before interpreting the mobile measurement data. Some guidelines on ways of making these correlations are provided in the Guidelines for PM-10 Episode Monitoring Methods (Pelton 1982).

Specific Site Selection

Once a general area for a monitoring site has been selected, it is necessary to select a specific location for the sampling operation. The intake for the monitor must be representative of the siting area, as close to the breathing zone as possible, and not biased abnormally high or low by influences which are only representative of the probe intake. The nature of biasing influences is documented in CFR 40 Part 58 and includes the following:

- Chemical reactions due to the air stream passing near reacting surfaces
- Unusual micrometeorological conditions
- Vegetation that serves as a pollutant sink
- Undue influence from nearby small sources (e.g., incinerator or furnace flue)
- Shielding influences from nearby obstructions.

Based on the consideration of these factors, the following guidelines for siting problems were promulgated in CFR 40, Part 58:

- 2-15 m above ground, as near to breathing height as possible, but high enough not to be an obstruction and to avoid vandalism
- At least 2 m away horizontally from supporting structures or walls
- Should be 20 m from dripline of trees
- Should not be near furnace or incinerator flues
- No nearby obstructions to air flow due to buildings, structures or terrain, at least in directions of frequent wind.

These guidelines were provided for TSP but are equally applicable to PM₁₀.

INSTALLATION AND FOLLOWUP

Each time a monitoring site is established, a documented description of the site is established. This record will help in the interpretation of results obtained from the site and in the evaluation of the need for changes. The following information is useful in documenting a site with regard to effects on measured PM₁₀ concentrations:

- Exposure diagram
 - Horizontal depiction showing location relative to nearby streets, buildings, and other significant structures, terrain features, or vegetation
 - Vertical depiction showing location relative to supporting structures, including buildings, walls, etc.
- Height of sampling intake above ground level
- Microinventory map showing locations of roads (with traffic counts), open fields, storage piles, and any visible emissions within 500 m of sampler
- List of all inventoried point and area sources within 1.5 km of sampler and all major point sources within 8 km of sampler

- Make and model of PM₁₀ monitor
- Types of meteorological and other air monitoring equipment operated at the site.

Once a monitoring site is selected and approved, the above site information should be compiled. As soon as it is practical, data collected from the site should be reviewed and scrutinized to determine that they do not contain undue influences from nearby sources. The suggestions for analyzing single-station air quality records, presented earlier in this report, should be used to evaluate the observations.

SECTION 6

EXAMPLE STUDY

To illustrate and test the ideas for selecting monitoring sites that were described in Section 5, TSP data for the City of Baltimore and surrounding areas for 1980 and 1981 are listed in Table 18. Figure 29 shows the locations of monitoring sites within the city limits; Figure 30 shows monitoring site locations outside the city limits.

For the purposes of this example, it is assumed that the State of Maryland and the City of Baltimore will cooperatively operate monitoring stations in the city for the following objectives:

- Evaluate progress in meeting and judge the attainment or nonattainment of NAAQS
- Develop and revise as necessary the Maryland Implementation Plan for controlling PM_{10}
- Provide data to EPA to meet national monitoring needs and to evaluate the State's management of air quality
- Provide data for model research and development
- Support enforcement activities
- Provide the public with information on air quality exposure and trends
- Provide data to identify and document episode exposure situations.

The annual mean concentrations for 1980 and 1981 are plotted in Figures 31 and 32. Isopleths are also shown to help interpret the patterns indicated by these data. The locations of the eight major point sources with particulate matter emissions in excess of 100 tons/yr are also shown and identified by number. The estimated emission rates for these sources are listed in Table 19. Fugitive emissions shown by squares in the air quality maps are listed in Table 20.

The maximum 24-hour concentration of TSP that were measured during 1980 and 1981 are shown in Figures 33 and 34. The 1981 pattern is based on 15 observations, while the 1980 pattern is based on 10 observations. The patterns of maximum concentration are quite different between the 2 years. The tongue of

TABLE 18. HI-VOL MEASUREMENTS OF TSP IN THE VICINITY OF BALTIMORE
(MARYLAND AIR MANAGEMENT ADMINISTRATION 1980, 1981)

Site, county	Geometric mean		Maximum (6-day cycle)	
	1980	1981	1980	1981
35. Fire Department Headquarters, City	82	70	284	203
38. NE Police Station, City*	54	48	138	129
39. NW Police Station, City*	69	56	275	122
40. SE Police Station, City*	81	68	269	166
41. SW Police Station, City*	65	55	201	135
42. Fire Department #10, City	--	88	--	325
44. Fairfield, City	89	89	206	310
47. Canton Pier #4, City**	--	(141) ²	--	(575) ²
48. AIRMON-02, City	--	67	--	146
49. Fire Department #22, City**	82	(85) ²	222	(165) ²
50. Ft. McHenry, City	103	89	195	231
51. Holabird Elementary School, City**	(72) ²	71	(175) ²	161
52. Westport, City	93	71	178	140
53. Canton Recreational Center, City**	--	(75) ²	--	(176) ²
54. I-95, City**	(73) ³	73	(133) ³	155
23. Garrison, County	49	47	94	93
26. Catonsville, County	47	46	86	112
28. Essex, County	64	61	134	136
29. Padonia, County	67	60	183	114
33. Chesapeake Terrace Elementary School, County	66	60	147	140
34. Sollers Point	79	80	145	176
18. Linthicum, Anne Arundel County**	(56) ²	--	(81) ²	--
20. Glen Burnie, Anne Arundel County	68	61	132	125
23. Riviera Beach, Anne Arundel County	60	58	85	137

* Operated on a 3-day cycle, rather than a 6-day cycle.

** Values in parentheses represent only two or three quarters.




Figure 29. TSP monitoring sites in Baltimore City.




Figure 30. TSP monitoring sites in the Baltimore AOCR, excluding Baltimore City.




Figure 32. Annual mean TSP concentration for 1981.

TABLE 19. TSP EMISSIONS BY EIGHT LARGEST POINT SOURCES IN BALTIMORE CITY

Number	Name	Emissions (tons/year)	Type
1	BG&E	181	Fuel burning
2	Davison Chemical	133	Process
3	General Refractory	116	Process
4	Carton Elevator	1,475	Process
5	Allied Chemical	145	Process
6	National Gypsum	126	Process
7	Louis Dreyfus	2,193	Process
8	U.S. Gypsum	1,612	Process

TABLE 20. FUGITIVE EMISSIONS BASED ON 1977 SURVEY
(Schakenbach and Koch 1978)

Area identification	Emission rate (tons/day)	Principal sources
1	11.7	Dirt roads
2	8.0	Dirt roads, construction sites
3	2.2	Dirt and gravel roads
4	4.1	Dirt and gravel roads
5	2.2	Dirt and gravel roads
6	7.3	Dirt roads
7	2.4	Dirt roads, construction sites
8	2.6	Dirt and gravel roads
9	10.9	Dirt and gravel roads
10	2.7	Dirt and gravel roads
11	1.8	Gravel roads
12	1.7	Construction sites
13	3.8	Storage piles, gravel roads
14	4.1	Gravel roads
15	2.1	Gravel roads




Figure 33. Maximum 24-hour TSP concentration for 1980.




Figure 34. Maximum 24-hour TSP concentration for 1981.

high concentrations shown for the 1980 data is not confirmed in 1981. It is possible that the two high observations to the east and northwest ends of the tongue were not properly sited and showed unrepresentative local influences. The 1981 pattern for maximum 24-hour concentrations is more compatible with the two annual mean patterns, showing a primary peak around the open harbor area and a secondary peak over the primary central city area just west of site 35.

The TSP monitoring data indicate a core area of high concentrations centered on the Baltimore harbor region. The highest point and area source emissions of particulate matter also form a ring around the harbor zone.

Figure 35 is a wind rose showing the frequency of 24-hour mean wind directions with a wind persistence index of 0.85 or greater. (An index of 1.0 indicates a continuous wind direction without variation.) The wind directions with the most frequent occurrence of a persistent wind are west-northwest, west, and northwest. The persistent wind directions closely parallel the orientation of the harbor along the Patapsco River. Therefore, the persistent winds also favor a core of high particulate matter concentrations around the harbor zone. The tongue of high values north of the principal sources shown in the peak 1980 concentrations is not well supported and is not evident in the 1981 data.

PM₁₀ concentrations may be expected to show a flatter pattern with less pronounced peaks than the TSP data. This is because there will be lower contributions from the larger particles released close to local sources. Monitoring sites farther from the local sources will be less affected by the deletion of larger particles and will show smaller reductions. This will result in a smoother pattern.

At least one site in the harbor area is needed to measure the peak PM₁₀ concentrations. Since the area is presently out of compliance with NAAQS for particulates, there will need to be sufficient monitors in the area surrounding the harbor to delineate the general shape of a potential noncompliance area for the new PM₁₀ standards. One strategy would be to select locations northwest, northeast, and south or southwest of the harbor area. In view of the potential for high levels of PM₁₀ concentrations, there is a need to inform the public of PM₁₀ exposure levels and trends, to document episode situations, and to support enforcement activities. For these reasons, it is desirable to site at least one and ideally two additional PM₁₀ monitors in the harbor area. Once the magnitude of PM₁₀ concentrations relative to PM₁₀ standards has been established, the siting requirements need to be reevaluated. There is also a need for a background monitoring site. There are many suitable sites that are presently monitoring TSP concentrations. Baltimore County Site 23, about 15 km northwest of Baltimore City, is upwind of the persistent prevailing wind directions. Furthermore, TSP measurements made at this site are indistinguishable from TSP measurements made at a site 35 km to the northwest (site 53) in very rural Carroll County (see Figure 31).




Figure 35. Wind persistence rose for Baltimore-Washington International Airport for 1973-1977 (wind persistence index greater than 0.85) (Pickering et al. 1979).

The preceding discussion describes the development of PM₁₀ monitoring network requirements where there is adequate TSP monitoring data to define the shape of the expected pattern of PM₁₀ concentrations. In this situation, modeling is not necessary. The subsequent selection of specific monitoring placements require onsite inspection of potential sites and the criteria described in Section 5.

SECTION 7

REFERENCES

- Auer, A.H., Jr. Correlations of Land Use and Cover with Meteorological Anomalies. *J. Appl. Meteorol.* 17:636-43, 1978.
- Ball, R.J., and G.E. Anderson. Optimum Site Exposure Criteria for SO₂ Monitoring. EPA-450/3-77-013, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1977.
- Budney, L.J. Guidelines for Air Quality Maintenance Planning and Analysis, Vol. 10 (Rev.): Procedures for Evaluating Air Quality Impact of New Stationary Sources. EPA-450/4-77-001, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1977.
- Barton, R.M., and J.C. Suggs. Philadelphia Roadway Study. Draft Report. U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1982.
- Changery, M.J., W.T. Hodge, and J.V. Ramsdell. Index--Summarized Wind Data. BNWL-2220 WIND-11 UC-60, U.S. Department of Commerce, National Climatic Center, Asheville, North Carolina, 1977.
- Corn, M. Aerosols and the Primary Air Pollutants--Nonviable Particles. In: *Air Pollution (3rd edition)*, Volume I, A.C. Stern, ed. Academic Press, Inc., New York, New York, 1976.
- Doty, S.R., B.L. Wallace, and G.C. Holzworth. A Climatological Analysis of Pasquill Stability Categories Based on STAR Summaries. National Oceanic and Atmospheric Administration, Asheville, North Carolina, 1976.
- Drake, R.L., and S.M. Barrager. Mathematical Models for Atmospheric Pollutants. EA-1131, Electric Power Research Institute, Palo Alto, California, 1979.
- Fujita, T.T. Tornadoes and Downbursts in the Context of Generalized Planetary Scales. *J. Atmos. Sci.* 38:1511-34, 1981.
- Hewson, E.W. Meteorological Measurements. In: *Air Pollution (3rd edition)*, Volume I, A.C. Stern, ed. Academic Press, New York, New York, 1976.
- Holzworth, G.C. Mixing Heights, Wind Speeds, and Potential for Urban Air Pollution Throughout the Contiguous United States. AP-104, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1972.

Holzworth, G.C. Climatological Aspects of the Composition and Pollution of the Atmosphere. Tech. Note No. 139. Secretariat of the World Meteorological Organization, Geneva, Switzerland, 1974.

Ingalls, M.N. Estimating Mobile Source Pollutants in Microscale Exposure Situations. EPA-460/3-81-021, U.S. Environmental Protection Agency, Ann Arbor, Michigan, 1981.

Jutze, C.E., et al. Technical Guidance for Control of Industrial Process Fugitive Particulate Emissions. EPA-450/3-77-010, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1977.

Landsberg, H.H. Atmospheric Changes in a Growing Community. Tech. Note No. BN 823. University of Maryland, College Park, Maryland, 1975.

Landsberg, H.H. The Urban Climate. Academic Press, New York, New York, 1981.

Ludwig, F.L., and J.H.S. Kealoha. Selecting Sites for Carbon Monoxide Monitoring. EPA-450/3-75-077, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1975.

Ludwig, F.L., J.H.S. Kealoha, and E. Shelar. Selecting Sites for Monitoring Total Suspended Particulates. EPA-450/3-77-018, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1977.

Ludwig, F.L., and E. Shelar. Site Selection for the Monitoring of Photochemical Air Pollutants. EPA-450/3-78-013, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1978.

Lyons, W.A., and L.E. Olsson. Mesoscale Air Pollution Transport in the Chicago Lake Breeze. J. Air Poll. Contr. Asso. 22:876-81, 1972.

Maryland Air Management Administration. Maryland Air Quality Data Report. Maryland Department of Health and Mental Hygiene, Baltimore, Maryland, 1980 and 1981.

Massoglia, M.F., J.P. Wood, and K.H. Babb. Emission Reductions Study, Stationary Sources of Air Pollution (1970-1979). EPA-340/1-81-001a, U.S. Environmental Protection Agency, Washington, D.C., 1981.

McCormick, R.A., and G.C. Holzworth. Air Pollution Climatology. In: Air Pollution (3rd edition), Volume I, A.C. Stern, ed. Academic Press, New York, New York, 1976.

Oke, T.R., and F.G. Hannel. The Form of the Urban Heat Island in Hamilton, Canada. In: Proceedings of the WHO/WMO Symposium on Urban Climates and Building Climatology. WMO Tech. Note No. 168. Secretariat of the World Meteorological Organization, Geneva, Switzerland, 1970.

- Pace, T.G. An Empirical Approach for Relating Annual TSP Concentrations to Particulate Microinventory Emissions Data and Monitor Siting Characteristics. EPA-450/4-79-012, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1979.
- Pace, T.G. Ambient Particulate Baseline Conditions--Sources and Concentrations. In: Proceedings of the Technical Basis for a Size Specific Particulate Standard, Specialty Conference, Air Pollution Control Association, 1980.
- Pasquill, F. The Estimation of the Dispersion of Windborne Material. Meteorol. Mag. 90:33-49, 1961.
- Pickering, K.E., et al. A Study of Ambient Air Quality in the Vicinity of Major Steel Facilities. GEOMET Report ES-793, EPA Contract No. 68-01-4144, Task 8. GEOMET Technologies, Inc., Rockville, Maryland, 1979.
- Pickering, K.E., J.M. Vilaro, and H.E. Rector. A Study of Ambient TSP Levels Near Major Steel Facilities (1978-1980 Update), Volume II. Draft Report ESF-955, EPA Contract No. 68-01-6311, Tasks 6 and 10. GEOMET Technologies, Inc., Rockville, Maryland, 1981.
- Schakenback, J.S., and R.C. Koch. A Particulate Matter Study for the Metropolitan Baltimore Intrastate Air Quality Control Region. GEOMET Report No. EF-710. GEOMET, Incorporated, Gaithersburg, Maryland, 1978.
- Shanon, L.J., J.P. Reider, and C. Cowherd. Emission Factors for Inhalable and Fine Particulates. In: Proceedings of the Technical Basis for a Size Specific Particulate Standard, Speciality Conference, Air Pollution Control Association, 1980.
- Suprenant, N., et al. Emissions Assessment of Conventional Stationary Source Combustion Systems, Volumes I and II. EPA-600/7-79-029, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1979.
- Taback, H.J., et al. Fine Particulate Emissions from Stationary and Miscellaneous Sources in the South Coast Air Basin. Final Report to California Air Resources Board, Sacramento, California, by KVB, Inc., 1979.
- Trijonis, J., et al. Analysis of the St. Louis RAPS Ambient Particulate Data. EPA-450/4-80-006a, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1980.
- Turner, D. B. Workbook of Atmospheric Dispersion Estimates. Report No. AP-26, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1970.

- Turner, D. B. Dispersion Estimate Suggestion No. 4. EPA National Environmental Research Center, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1974.
- U.S. Environmental Protection Agency. Guide for Compiling a Comprehensive Emission Inventory (Revised). No. APTD-1135. Research Triangle Park, North Carolina, 1973.
- U.S. Environmental Protection Agency. Air Monitoring Strategy for State Implementation Plans. Standing Air Monitoring Working Group. EPA-450/2-77-010. Research Triangle Park, North Carolina, 1977a.
- U.S. Environmental Protection Agency. Guideline on Air Quality Models (Revised). EPA-450/2-78-027R. Research Triangle Park, North Carolina, 1986.
- U.S. Environmental Protection Agency. Ambient Air Quality Monitoring, Data Reporting, and Surveillance Provisions for Particulate Matter. Federal Register, Part III, 52:24736-750. 1987.
- U.S. Environmental Protection Agency. NEDS National Emissions Data System Information. EPA-450/4-80-013a. Research Triangle Park, North Carolina, 1984.
- U.S. Environmental Protection Agency. Review of the National Ambient Air Quality Standards for Particulate Matter: Revised Draft Staff Paper. Research Triangle Park, North Carolina, 1981a.
- U.S. Environmental Protection Agency. Air Quality Criteria for Particulate Matter and Sulfur Oxides. Volumes I and II. External Review Draft No. 2, Research Triangle Park, North Carolina, 1981b.
- U.S. Environmental Protection Agency. Compilation of Air Pollutant Emission Factors. Volume 1: Stationary and Area Sources. Fourth Edition. AP-42, Research Triangle Park, North Carolina, 1985.
- U.S. Environmental Protection Agency. Supplement A to Compilation of Air Pollutant Emission Factors, 1986.
- U.S. Environmental Protection Agency. An Examination of 1982-1983 Particulate Matter Ratios and Their Use in the Estimation of PM₁₀ NAAQS Attainment Status. EPA-450/4-85-010. Research Triangle Park, North Carolina, 1985.
- U.S. Environmental Protection Agency. Guideline for PM₁₀ Episode Monitoring Methods (Revised). EPA-450/4-83-005. Research Triangle Park, North Carolina 1983.
- Watson, J.G., J.C. Chow, and J.J. Shah. Analysis of Inhalable and Fine Particulate Matter Measurements. EPA-450/4-81-035, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1981.

Whitby, K.T. Aerosol Formation in Urban Plumes. In: Aerosols, Anthropogenic and Natural Sources and Transport, T.J. Kneip and P.J. Lioy, eds. Ann. N.Y. Acad. Sci. 338:258-75, 1980.

Zoller, J., T. Bertke, and J. Janzen. Assessment of Fugitive Particulate Emission Factors for Industrial Processes. EPA-450-/3-78-107, U.S. Environmental Protection Agency, Research Triangle Park, North Carolina, 1978.

APPENDIX A

METEOROLOGICAL DATA TABULATIONS FOR CDM PROGRAM

Cities for which Stability Array (STAR) data tabulations are available are listed alphabetically by date and by city within a state. This list was compiled by Changery, Hodge, and Ramsdell (1977). Additional tabulations may be available since this compilation, and others may be ordered. For assistance on orders contact:

Director
National Climatic Center
Federal Building
Asheville, North Carolina 28801

A-1. EXPLANATION OF ENTRIES

CITY is the city or town name for the location at which the original observations were taken. It may also be the name of a military installation.

NAME-TYPE is usually the airport or field name and/or service which operated the station. If these had changed during the period summarized, the name and/or service valid for the longest portion of the summary is used. A few stations may have no identifying information.

Under NAME, commonly used abbreviations are:

APT	-	Airport
ATL	-	Air Terminal
BD	-	Building
CAP	-	County Airport
CO	-	County
FLD	-	Field
GEN	-	General
GTR	-	Greater
INL	-	International
MAP	-	Municipal Airport
MEM	-	Memorial
METRO-	-	Metropolitan
MN	-	Municipal
RGL	-	Regional
TERM	-	Terminal

Under TYPE, commonly used abbreviations are:

AAB	-	Army Air Base
AAF	-	Army Air Field
AAFB	-	Auxiliary Air Force Base
AEPG	-	Army Energy Proving Ground
AF	-	Air Force
AFB	-	Air Force Base
AFS	-	Air Force Station
ANGB	-	Air National Guard Base
ASC	-	Army Signal Corp
CAA	-	Civil Aeronautics Administration
FAA	-	Federal Aviation Administration
FSS	-	Flight Service Station
LAWR	-	Limited Airways Weather Reporting (Station)
MCAF	-	Marine Corps Air Facility
MCAS	-	Marine Corps Air Station
NAAF	-	Naval Auxiliary Air Facility
NAAS	-	Naval Auxiliary Air Station
NAF	-	Naval Air Facility
NAS	-	Naval Air Station
NAU	-	Naval Air Unit
NF	-	Naval Facility
NS	-	Naval Station
PG	-	Proving Ground
SAWR	-	Supplementary Airways Weather Reporting (Station)
WBAS	-	Weather Bureau Airport Station
WBO	-	Weather Bureau Office

ST is a two-letter code identifying each of the fifty states.

WBAN # refers to the five-digit number identifying stations operated by United States Weather Services (civilian and military) currently or in the past. A few stations have had no number assigned.

WMO # refers to the five-digit block and station numbers assigned to U. S. stations as authorized by the World Meteorological Organization. Many stations with a WBAN # will have no corresponding WMO number.

LAT, LONG are the latitude and longitude of the station in degrees and minutes. If the station changed coordinates during the period summarized, the location reflects the site with the longest record.

ELEV is the elevation (above sea level) of the station in meters. Reported station elevation was used if the barometric height above sea level was not available. If an elevation change occurred during the period summarized, the elevation reflects the station height for the longest period of record.

PERIOD OF RECORD is the first and last month-year of the summarized period. As an example, 01 38 - 12 44 is read as January 1938 through December 1944.

SUMMARY TYPE identifies each summary according to its format. Each format is similar to one of the 16 types presented in detail beginning on page I-13.

SUMM FREQ is the summary frequency or the time period in which the summarized data are presented. Abbreviations used are:

M - Monthly. Data for each calendar month combined and presented on a monthly basis.

S - Seasonal. Data for the months December through February of the period of record are combined into a winter season, summarized and presented on a seasonal basis. The months March-May, June-August, and September-November are similarly summarized.

A - Annual. All data for the period summarized together.

MA - Monthly and Annual.

SA - Seasonal and Annual.

MS - Monthly and Seasonal.

MSA - Monthly, Seasonal, and Annual.

IYM - Individual Year-Month. Data are presented for individual months of record.

SP - Special Period. The special period presented is described further in the given summary's Tab #/Remarks column.

TAB #/REMARKS column contains additional identifying or explanatory information. Many of the summaries produced by the Climatic Center and Air Weather Service for a specific project are identified by a tabulation number. A "T" followed by a 4 or 5 digit number identifies a summary produced by the NCC. Similarly, a "TCL" with a number indicates an AWS summary. Not all summaries can be so identified. This number is provided as an aid in requesting a specific tabulation.

Numbers following or in place of a tabulation number refer to remarks listed beginning on page I-9. These remarks are provided if additional information describing a summary is necessary. Examples are summaries with data for hourly or 3-hour periods, specified hours only, combined stations, etc.

A-2. REMARKS

This is a list of descriptive remarks coded by number in the Tab #/Remarks column of the index. Numbers missing were not used.

1. Broken period
2. 3-hourly groups
3. Day-night
4. 0600-1800 LST only
5. 10-12 observations per day, all daylight hours
6. By hours 00, 03, 06, 09, 12, 15, 18, 21 LST
7. See microfilm for broken periods and format
8. Includes flying weather conditions
9. Part "C" only
10. Hours 0600-1200 LST only
11. May-November only
12. Broken period - pre-11/45 data from Point Hope (Stn #26601)
13. Broken period by hourly groups
14. Less 12/59
15. Pre-1939 data from Tin City (Stn #26634)
16. Less 12/70
17. 0500-1600 LST only
18. 2-13 observations daily
19. 0700-1900 LST only
20. Combined data for Douglas AAF (Stn #23001) for 11/42-11/45 and Douglas Apt (Stn #93026) for 11/48-12/54
21. Part "A" only by hourly groups - combined data for Kingman CAA (Stn #93167) for 01/34-12/41 and Kingman AAF (Stn #23108) for 03/43-06/45
22. For hours 0800, 1400, 1700 LST only
23. Direction and speed by visibility, relative humidity \geq 90% and/or precipitation, and relative humidity \geq 90% and no precipitation - August, October, and December only
24. Part "A" only
25. By 2-hourly groups
26. Daylight hours only
27. September-December only
28. By hourly groups
29. For 0900-1600 and 1700-0800 LST
30. Period 01/37-03/38 for Indio (Stn #03105)
31. Precipitation-wind tabulation for April-October
32. By day and night hours on microfilm
33. Periods: July 15-31, August 1-15 for 1000 and 1400 LST
34. No data for 27 months
35. See Edwards AFB
36. Some data from Paso Robles (Stn #23231)
37. All observations by various stability classes
38. See Moffett Field
39. Also contains a contact wind rose
40. Eight directions and calm
41. Includes a percentage graph

42. 1200 LST observations only
43. Some missing data
44. Contains all weather, precipitation, and visibility \leq 6 miles
wind tabulations for day and night hours
45. Also called 94A
46. See Farallon Island SE
- 47A. 0100-0400 LST
- 47B. 0700-1000 LST
- 47C. 1300-1600 LST
- 47D. 1900-2200 LST
- 47E. 0600-2200 LST
- 47F. 0700 LST
- 47G. 1600 LST
- 47H. 0600-0900 LST
- 47I. 1600-1800 LST
- 47J. 0700-0900 LST
- 47K. 1900-0600 LST
- 47L. 1000-1500 LST
- 47M. 1200-2000 LST
- 47N. 0800-2100 LST
- 47P. 1100-1300 LST
48. Also contains bimonthly summaries
49. Located in city file
50. Three speed groups
51. June, July, August - daylight hours only
52. Special tables
53. Pre-1944 data from Bolling AAF (Stn #13710)
54. Also known as Chantilly, VA, FAA (pre-Dulles)
55. See Andrews AFB, MD
56. Data for 01/74 from Herndon Apt (Stn #12841)
57. See also Cape Kennedy AFB
58. Tower data - 8 levels (3-150 m)
59. June-August only
60. Data for 09/42-09/45 from Carlsbad AAF (Stn #23006)
61. Data after 07/53 from Key West NAS (Stn #12850)
62. Data thru 1945 from Marianna AAF (Stn #13851)
63. Contains 14 months of data from Morrison Field (Stn #12865)
64. Contains graphical wind rose
65. Tabulated by temperature and relative humidity intervals
66. Seasonal by day and night hours
67. Closed and instrument weather conditions only
68. Less 01/49
69. 24 observations daily
70. 8 observations daily
71. 1 of 3 parts
72. Tabulation by day and night hours for May 1 - September 30 and
October 1 - April 30
73. Tabulated for December-March and April-November
74. Data prior to 10/42 and after 10/45 from Sioux City Apt (Stn #14943)

- 75. For day - clear and cloudy and night - clear and cloudy conditions
- 76. Also contains a ceiling-visibility tabulation
- 77. 0700-1900 LST only
- 78. All weather and 2 relative humidity classes
- 79. Summer season only - 1957 missing
- 80. May, August-November only
- 81. Includes separate wind rose for WSO
- 82. Four speed categories
- 83. Monthly tabulation for 0400 and 1400 LST, seasonal tabulation for all observations
- 84. Some data from Presque Isle AFB (Stn #14604)
- 85. Four observations per day
- 86. Semi-monthly periods
- 87. 1935 data from Boston WBAS (Stn #14739)
- 88. VFR, IFR, closed conditions
- 89. Pre-03/1952 data from Paso Robles (Stn #23231)
- 90. August 1-15 only for hours 1000 and 1400 LST
- 91. Partial SMOS
- 92. June, July only for hours 2200L - 0200L
- 93. April thru December only
- 94. Less April 1958 and 1960
- 95. January, April, July, and October only
- 96. Winter season only
- 97. Part "C" and "E" only
- 98. 36 compass points
- 99. Less October-December 1945 for a 2-hour period after sunrise
- 100. November 1951 substituted for November 1955
- 102. For hour groups 07-09, 10-15, 16-18, and 19-06 LST and all hours combined
- 103. For hours 0100, 0700, 1300, and 1900 LST (individual and all hours combined)
- 104. Day and night hours, clear and cloudy conditions
- 106. Pre-02/33 data from Albuquerque WBO (Stn #23073)
- 108. Precipitation wind rose tabulation
- 109. All observations by 6 hourly groups
- 110. For ceiling less than 600 feet and/or visibility less than 1-1/2 miles - also an annual hourly summary
- 111. Also summarized by month-hour for hours 0200 and 1400 LST
- 112. Summarized by days 1-15 and 16 to end of month for day and night hours
- 115A. 1300 LST
- 115B. 0400 LST
- 115C. 1000 LST
- 115D. 1600 LST
- 115E. 2200 LST
- 115F. 0700 LST
- 115G. 0100 LST
- 115H. 1900 LST
- 117. See Covington, Kentucky
- 118. Pre-04/32 data from Oklahoma City WBO (Stn #93954)
- 119. May to October only

- 120. Monthly for 1961-63, individual months 1-4/64
- 121. Also contains day and night summaries
- 124. Summary titled Scranton
- 125. See Wilkes-Barre
- 126. December-February for 0730 and 1930 LST only
- 128. Pre-12/44 data from Galveston AAF (Stn #12905)
- 129. Data for 10/62-12/63 for Greenville-Spartanburg Apt (Stn #03870)
- 132. February-April and June-September only
- 133. Pre-03/43 data from English Field (Stn #23047)
- 134. Post-10/66 data from Fort Wolters
- 135. Less 6/68
- 136. For hours 00-23 and 07-22 LST
- 140. Also contains annual ceiling/visibility tabulation
- 141. Less 0000 and 0300 LST
- 142. See Killeen
- 143. See Dugway PG
- 144. Data for 1943-49 for Wendover AFB (Stn #24111)
- 145. 0400-1800 LST
- 146. See Washington, DC - Dulles International Apt WBAS
- 147. See Washington, DC - National Apt WBAS
- 149. 0700-1200 LST
- 150. Tower data, year-month-level, month-level, and month-level-hour
- 151. Pre-11/41 data from Paine Field CAA (Stn #24222)
- 152. 10 observations per day - closed on weekends
- 153. 10 observations per day - wind speed estimated
- 155. By 5°F temperature intervals - with and without thunderstorms
- 157. One speed group - greater than 14 knots
- 158. Speed classes in Beaufort Force - mean speed by direction in mph
- 159. Hourly groups for 0600-1600 LST
- 160. Post-05/55 data from Forest Sherman (Stn #03855)
- 161. By speed classes and 5°F temperature classes
- 162. For all hours combined and for hours 0030 and 1230 individually

CITY	NAME - TYPE	ST	LEAS #	LEAS #	LAT	LONG	ELEV	PERIOD OF RECORD	SUMMARY TYPE	SUMM FREQ	TAB#/REMARKS
ANNISTON	CALHOUN CO APT CAR	AL	13871		33 25N	085 51W	0183	01 46 - 12 54	STAR	SA	T13272
BIRMINGHAM	MUNICIPAL APT LEAS	AL	13875	72228	33 34N	088 49W	0182	01 50 - 12 54	STAR	MA	T12741
BIRMINGHAM	MUNICIPAL APT LEAS	AL	13875	72228	33 34N	088 49W	0182	01 71 - 12 71	STAR	SA	T13618
BIRMINGHAM	MUNICIPAL APT LEAS	AL	13875	72228	33 34N	088 49W	0182	01 72 - 12 72	STAR	SA	T50879
FOOT BUCKER	CRIMES APT	AL	03850		31 15N	085 43W	0091	01 85 - 12 59	STAR	SA	T12791
HUNTSVILLE	HUNTSVL-MADISON CAR LEAS	AL	03856	72223	34 42N	086 35W	0185	01 80 - 12 54	STAR	SA	T14718
HUNTSVILLE	HUNTSVL-MADISON CAR LEAS	AL	03856	72223	34 38N	086 48W	0188	01 72 - 12 72	STAR	SA	T50879
MOBILE	BATES FLD LEAS	AL	13894	72223	30 41N	088 15W	0089	01 68 - 12 70	STAR	SA	T12825
MOBILE	BATES FLD LEAS	AL	13894	72223	30 41N	088 15W	0089	01 70 - 12 74	STAR	SA	T52078
MOBILE	BATES FLD LEAS	AL	13894	72223	30 41N	088 15W	0089	01 70 - 12 70	STAR	SA	T12925
MOBILE	BATES FLD LEAS	AL	13894	72223	30 41N	088 15W	0089	01 71 - 12 71	STAR	A	T01772
MOBILE	BATES FLD LEAS	AL	13894	72223	30 41N	088 15W	0089	01 72 - 12 72	STAR	SA	T50879
MONTGOMERY	JANNELLY FLD LEAS	AL	13895	72228	32 18N	086 24W	0081	01 70 - 12 70	STAR	A	T12867
MONTGOMERY	JANNELLY FLD LEAS	AL	13895	72228	32 18N	086 24W	0081	01 72 - 12 72	STAR	SA	T50879
SELMA	CRAIG AFB	AL	12850		32 21N	086 50W	0053	01 54 - 12 58	STAR	SA	T12867
TUSCALOOSA	VAN DE GRAFF APT CAR	AL	93806		33 14N	087 37W	0097	01 49 - 12 54	STAR	A	T51862.3
ANCHORAGE	ELMENDORF AFB	AK	26401	70272	61 15N	149 48W	0054	01 51 - 12 70	STAR	MA	T15332.3
ANCHORAGE	INTERNATIONAL APT LEAS	AK	26451	70273	61 10N	150 01W	0048	01 69 - 12 69	STAR	MA	T15853
BIG DELTA	FAA	AK	26415	70267	64 00N	146 44W	0389	01 80 - 12 64	STAR	MA	T14063
BIG DELTA	FAA	AK	26415	70267	64 00N	146 44W	0389	01 67 - 12 71	STAR	SA	T14063
CORDOVA	FILE 13 APT CAR	AK	26410	70296	50 30N	146 30W	0013	01 58 - 12 62	STAR	SA	T50320
FAIRBANKS	EIELSON AFB	AK	26407	70265	64 39N	147 04W	0186	01 81 - 12 70	STAR	SA	T14703
FAIRBANKS	INTERNATIONAL APT LEAS	AK	26411	70261	64 49N	147 52W	0134	01 81 - 12 70	STAR	SA	T14703
GULKANA	INTERMEDIATE FIELD	AK	26425	70271	62 08N	146 27W	0481	01 87 - 12 71	STAR	SA	T14063
KENAI	MUNICIPAL APT CAR	AK	26523	70256	60 34N	151 15W	0027	01 49 - 12 58	STAR	MA	T15332.3
KENAI	MUNICIPAL APT CAR	AK	26523	70256	60 34N	151 15W	0027	01 68 - 12 70	STAR	SA	T13873
MIDDLETON ISL	AFS	AK	26403	70343	60 28N	146 19W	0013	01 58 - 12 62	STAR	SA	T50320
DOUGLAS	BISBEE-DOGLS INL APT LEAS	AZ	93026		31 37N	108 36W	1262	01 50 - 12 54	STAR	SA	T50672.3
DOUGLAS	BISBEE-DOGLS INL APT CAR	AZ	93026		31 37N	108 36W	1262	01 50 - 12 54	STAR	SA	T13385
PHOENIX	SKY HARBOR MAP LEAS	AZ	23183	72278	33 28N	112 01W	0339	01 56 - 12 64	STAR	MA	T14324
PHOENIX	SKY HARBOR MAP LEAS	AZ	23183	72278	33 28N	112 01W	0339	01 87 - 12 71	STAR	MA	T13781
PHOENIX	SKY HARBOR MAP LEAS	AZ	23183	72278	33 28N	112 01W	0339	01 68 - 12 73	STAR	SA	T50584.22
PHOENIX	SKY HARBOR MAP LEAS	AZ	23183	72278	33 28N	112 01W	0339	01 73 - 12 75	STAR	SA	T52279.3
PHOENIX	SKY HARBOR MAP LEAS	AZ	23183	72278	33 28N	112 01W	0339	01 73 - 12 75	STAR	MA	T52279.3
PHOENIX	SKY HARBOR MAP LEAS	AZ	23183	72278	33 28N	112 01W	0339	01 75 - 12 75	STAR	MA	T52362.3
PHOENIX	SKY HARBOR MAP LEAS	AZ	23183	72278	33 28N	112 01W	0339	01 75 - 12 75	STAR	MA	T52362.3
PRESCOTT	MUNICIPAL APT LEAS	AZ	23164	72272	34 39N	112 28W	1530	01 67 - 12 71	STAR	SA	T01772
TUCSON	MUNICIPAL APT LEAS	AZ	23160	72274	32 08N	110 57W	0779	01 55 - 12 64	STAR	MA	T14324
TUCSON	MUNICIPAL APT LEAS	AZ	23160	72274	32 08N	110 57W	0779	01 58 - 12 63	STAR	SA	T13111
TUCSON	INL APT LEAS	AZ	23160	72274	32 07N	110 56W	0789	01 67 - 12 71	STAR	MA	T14388
TUCSON	INL APT LEAS	AZ	23160	72274	32 07N	110 56W	0789	01 67 - 12 71	STAR	MA	T14316
TUCSON	INTERNATIONAL APT LEAS	AZ	23185	72280	32 40N	114 38W	0062	01 67 - 12 71	STAR	SA	T13385
EL DORADO	GOODWIN FIELD CAR	AR	93882		33 13N	092 48W	0082	01 50 - 12 54	STAR	SA	T50055
FORT SMITH	MUNICIPAL APT LEAS	AR	13864	72344	35 20N	094 22W	0141	01 55 - 12 74	STAR	MA	T51827.3
FORT SMITH	MUNICIPAL APT LEAS	AR	13864	72344	35 20N	094 22W	0141	01 68 - 12 72	STAR	MA	T14655
LITTLE ROCK	ADAMS FIELD MAP LEAS	AR	13863	72340	34 44N	092 14W	0084	01 55 - 12 64	STAR	SA	T14644
LITTLE ROCK	ADAMS FIELD MAP LEAS	AR	13863	72340	34 44N	092 14W	0084	01 68 - 12 70	STAR	SA	T13028
LITTLE ROCK	ADAMS FIELD MAP LEAS	AR	13863	72340	34 44N	092 14W	0084	01 68 - 12 73	STAR	SA	T51048.3
LITTLE ROCK	ADAMS FIELD MAP LEAS	AR	13863	72340	34 44N	092 14W	0084	08 71 - 07 72	STAR	SA	T11153
LITTLE ROCK	ADAMS FIELD MAP LEAS	AR	13863	72340	34 44N	092 14W	0084	02 72 - 02 73	STAR	SA	T01772
ALAMEDA	MRS	CA	23238	72406	37 47N	122 19W	0009	01 60 - 12 64	STAR	MA	T14288
ARCATA	FAA	CA	24283		40 59N	124 06W	0089	01 68 - 12 72	STAR	A	T14360
BAKERSFIELD	MEADOWS FIELD LEAS	CA	23155	72384	35 25N	119 03W	0151	01 60 - 12 64	STAR	A	T52295
BAKERSFIELD	MEADOWS FIELD LEAS	CA	23155	72384	35 25N	119 03W	0151	01 64 - 12 73	STAR	MA	T50715.3
BAKERSFIELD	MEADOWS FIELD LEAS	CA	23155	72384	35 25N	119 03W	0151	01 67 - 12 71	STAR	MA	T14331
BISHOP	LEAS	CA	23157	72480	37 22N	118 23W	1253	01 60 - 12 64	STAR	MA	T52558.47W
BLYTHE	RIVERSIDE COUNTY APT CAR	CA	23158		33 37N	114 43W	0120	01 40 - 12 64	STAR	SA	T14358
BLYTHE	RIVERSIDE COUNTY APT CAR	CA	23158		33 37N	114 43W	0119	09 68 - 08 74	STAR	SA	T15211
SUBURBAN	HOLLYWO-SUBURBAN APT LEAS	CA	23152	72288	34 12N	118 23W	0231	01 50 - 12 64	STAR	MA	T13257
CHINA LAKE	MRS	CA	93104		35 41N	117 41W	0680	01 54 - 12 58	STAR	LYN	T15276
CHINA LAKE	MRS	CA	93104		35 41N	117 41W	0682	01 58 - 12 63	STAR	LYN	T15276
DAGGERTT	SAN BERNARDINO CAR CAR	CA	23181		34 52N	116 47W	0588	01 58 - 12 64	STAR	SA	T13284
DAGGERTT	SAN BERNARDINO CAR CAR	CA	23181		34 52N	116 47W	0588	01 58 - 12 64	STAR	MA	T13284
EDWARDS	AFB MURCO	CA	23114	72381	34 55N	117 54W	0708	01 58 - 12 70	STAR	MA	T51145
FAIRFIELD	TRAVIS AFB	CA	23202	72415	38 16N	121 58W	0018	01 60 - 12 64	STAR	MA	T14239
FRESNO	AIR TERMINAL LEAS	CA	23183	72389	36 47N	119 42W	0103	01 60 - 12 64	STAR	A	T52385
FRESNO	AIR TERMINAL LEAS	CA	93183	72388	36 47N	119 42W	0103	01 60 - 12 64	STAR	MA	T52358.3
LONG BEACH	MUNICIPAL APT LEAS	CA	23128	72287	33 49N	118 09W	0021	01 48 - 12 64	STAR	MA	T15332.3
LONG BEACH	MUNICIPAL APT LEAS	CA	23128	72287	33 49N	118 09W	0021	01 60 - 12 64	STAR	MA	T12257
LONG BEACH	MUNICIPAL APT LEAS	CA	23128	72287	33 49N	118 09W	0017	01 65 - 12 74	STAR	MA	T15332.3
LONG BEACH	MUNICIPAL APT LEAS	CA	23128	72287	33 49N	118 09W	0008	01 68 - 12 73	STAR	A	T50819.3
LOS ALAMITOS	MRS	CA	93108		33 48N	118 03W	0008	01 69 - 12 69	STAR	MA	T12267
LOS ANGELES	INTERNATIONAL APT LEAS	CA	23174	72295	33 56N	118 23W	0037	01 55 - 12 64	STAR	MA	T50246
LOS ANGELES	INTERNATIONAL APT LEAS	CA	23174	72295	33 56N	118 23W	0037	01 60 - 12 61	STAR	MA	T14068
LOS ANGELES	INTERNATIONAL APT LEAS	CA	23174	72295	33 56N	118 23W	0037	05 64 - 04 68	STAR	MA	T12267
LOS ANGELES	INTERNATIONAL APT LEAS	CA	23174	72295	33 56N	118 23W	0037	01 55 - 12 66	STAR	SA	T14068
LOS ANGELES	INTERNATIONAL APT LEAS	CA	23174	72295	33 56N	118 23W	0037	01 70 - 12 71	STAR	SA	T14068
ROFFETT FIELD	MRS SUNNYVALE	CA	23244	72509	37 25N	122 03W	0012	01 50 - 12 64	STAR	MA	T14289
NEEDLES	MUNICIPAL APT CAR	CA	23179	72380	34 48N	114 37W	0280	01 48 - 12 64	STAR	SA	T13790
NEEDLES	MUNICIPAL APT CAR	CA	23179	72380	34 48N	114 37W	0280	01 55 - 12 64	STAR	SA	T13790
NEEDLES	MUNICIPAL APT CAR	CA	23179	72380	34 48N	114 37W	0280	09 58 - 08 74	STAR	SA	T15211
OAKLAND	INTERNATIONAL APT LEAS	CA	23230	72493	37 44N	122 22W	0005	01 50 - 12 64	STAR	MA	T14289
OXNARD	AFB	CA	23136		34 13N	119 04W	0025	01 60 - 12 64	STAR	MA	T50818
POINT MUGO	AF	CA	93111	72391	34 37N	119 07W	0004	03 52 - 02 72	STAR	MA	T15332.3
POINT MUGO	AF	CA	93111	72391	34 37N	119 07W	0008	01 50 - 12 64	STAR	MA	T50616
RIVERSIDE	MARCH AFB	CA	23119	72285	33 53N	117 15W	0461	01 56 - 12 70	STAR	A	T50819.3
RIVERSIDE	MARCH AFB	CA	23119	72285	33 53N	117 15W	0461	01 66 - 12 70	STAR	MA	T14331
SACRAMENTO	MUNICIPAL APT LEAS	CA	23232	72483	38 31N	121 00W	0013	01 56 - 12 70	STAR	SA	T01772

CITY	NAME - TYPE	ST	LEAS	WFO	LAT	LONG	ELEV	PERIOD OF RECORD	SUMMARY TYPE	SUM FREQ	TAGS/RE MARKS
SACRAMENTO	EXECUTIVE ART WARS	CA	23232	72483	38 31N	121 30W	3008	01 58 - 12 73	STAR	SA	750504.47F
SACRAMENTO	EXECUTIVE ART WARS	CA	23232	72483	38 31N	121 30W	3008	01 58 - 12 73	STAR	SA	750504.47F
SAN DIEGO	LINDBERGH INT ART WARS	CA	23188	72290	32 44N	117 10W	3011	01 55 - 12 54	STAR	MA	750248
SAN DIEGO	LINDBERGH INT ART WARS	CA	23188	72290	32 44N	117 10W	3011	01 55 - 12 54	STAR	MA	750889
SAN DIEGO	LINDBERGH INT ART WARS	CA	23188	72290	32 44N	117 10W	3011	01 58 - 12 73	STAR	MA	701772
SAN DIEGO	NAS NORTH ISLAND	CA	23112		32 43N	117 13W	3015	01 57 - 12 71	STAR	MA	775000
SAN FRANCISCO	INTERNATIONAL ART WARS	CA	23234	72484	37 37N	122 23W	3007	01 58 - 12 64	STAR	MA	714289
SAN FRANCISCO	INTERNATIONAL ART WARS	CA	23234	72484	37 37N	122 23W	3007	01 58 - 12 73	STAR	SA	750878.47C
SAN FRANCISCO	INTERNATIONAL ART WARS	CA	23234	72484	37 37N	122 23W	3007	01 58 - 12 73	STAR	SA	750878.47B
SAN FRANCISCO	INTERNATIONAL ART WARS	CA	23234	72484	37 37N	122 23W	3007	01 58 - 12 73	STAR	SA	750878.47A
SAN FRANCISCO	INTERNATIONAL ART WARS	CA	23234	72484	37 37N	122 23W	3007	01 58 - 12 73	STAR	SA	750878.47D
SAN RAFAEL	HAMILTON AFB	CA	23211		38 04N	122 31W	3004	01 56 - 12 64	STAR	MA	714289
SAN RAFAEL	HAMILTON AFB	CA	23211		38 04N	122 31W	3004	01 56 - 12 70	STAR	SA	714158
SANTA BARBARA	MUNICIPAL ART WAR	CA	23180		34 28N	119 50W	3004	01 50 - 12 54	STAR	MA	712329
SANTA MARIA	WARS	CA	23275	72384	34 58N	120 35W	3071	01 49 - 12 53	STAR	MA	750740
SANTA MARIA	WARS	CA	23275	72384	34 58N	120 37W	3073	01 49 - 12 74	STAR	MA	752110.3
UKIAH	MUNICIPAL ART WAR	CA	23275		30 08N	123 12W	3182	01 55 - 12 84	STAR	MA	750175
VANDENBERG	CAMP COCKE AFB	CA	93214	72383	34 43N	120 34W	0118	01 58 - 12 72	STAR	MA	715332.3
VANDENBERG	CAMP COCKE AFB	CA	93214	72383	34 43N	120 34W	0118	01 51 - 12 70	STAR	MA	715020
VANDENBERG	CAMP COCKE AFB	CA	93214	72383	34 43N	120 34W	0118	01 58 - 12 70	STAR	MA	750908.47E
VANDENBERG	CAMP COCKE AFB SUB	CA	93214	72383	34 43N	120 34W	0118	01 70 - 12 70	STAR	SA	701772
VICTORVILLE	GEORGE AFB	CA	23131		34 35N	117 23W	0880	01 58 - 12 87	STAR	MA	710284
VICTORVILLE	GEORGE AFB	CA	23131		34 35N	117 23W	0880	01 58 - 12 87	STAR	SA	710284
AKRON	WASHINGTON COUNTY ART CAM	CO	24015		40 07N	103 10W	1388	01 50 - 12 54	STAR	MA	715038
COLORADO SPGS	PETERSON FIELD WARS	CO	93037	72466	38 46N	104 43W	1857	01 58 - 12 73	STAR	MA	750235
COLORADO SPGS	PETERSON FIELD WARS	CO	93037	72466	38 46N	104 43W	1857	01 74 - 12 74	STAR	A	751847.3
DENVER	STAPLETON INT ART WARS	CO	23082	72468	38 46N	104 53W	1615	01 60 - 12 84	STAR	MA	750313
DENVER	STAPLETON INT ART WARS	CO	23082	72468	38 46N	104 53W	1615	07 58 - 02 58	STAR	A	712311
DENVER	STAPLETON INT ART WARS	CO	23082	72468	38 46N	104 53W	1615	01 74 - 12 74	STAR	MA	751859.3
GRAND JUNCTION	MUNICIPAL ART WARS	CO	23066	72476	39 07N	108 32W	1474	01 50 - 12 64	STAR	SA	714518
PUEBLO	MEMORIAL ART WARS	CO	93058	72464	38 17N	104 31W	1415	01 50 - 12 64	STAR	MA	750807
PUEBLO	MEMORIAL ART WARS	CO	93058	72464	38 17N	104 31W	1415	01 58 - 12 70	STAR	SA	750098
PUEBLO	MEMORIAL ART WARS	CO	93058	72464	38 17N	104 31W	1438	01 73 - 12 74	STAR	A	715405
PUEBLO	MEMORIAL ART WARS	CO	93058	72464	38 17N	104 31W	1438	01 74 - 12 74	STAR	A	751847.3
BRIDGEPORT	MUNICIPAL ART WARS	CT	94702	72504	41 10N	073 08W	0009	01 54 - 12 84	STAR	A	712243
BRIDGEPORT	MUNICIPAL ART WARS	CT	94702	72504	41 10N	073 08W	0009	01 58 - 12 88	STAR	SA	714783
HARTFORD	BRAINARD FIELD WARS	CT	14793		41 46N	072 38W	0006	01 48 - 12 52	STAR	MA	714204
WINDSOR LOCKS	BRADLEY FIELD WARS	CT	14740	72508	41 56N	072 41W	0081	01 58 - 12 72	STAR	SA	714793
WINDSOR LOCKS	BRADLEY FIELD WARS	CT	14740	72508	41 56N	072 41W	0081	05 73 - 04 74	STAR	A	750465
WINDSOR LOCKS	BRADLEY FIELD WARS	CT	14740	72508	41 56N	072 41W	0081	01 74 - 04 75	STAR	MA	711793
WINDSOR LOCKS	BRADLEY FIELD WARS	CT	14740	72508	41 56N	072 41W	0081	05 74 - 10 74	STAR	A	752448.52
DOVER	AFB	DE	13707		39 08N	075 28W	3011	01 53 - 12 57	STAR	A	711749
DOVER	AFB	DE	13707		39 08N	075 28W	3011	01 58 - 12 70	STAR	MA	750465.3
DOVER	AFB	DE	13707		39 08N	075 28W	3011	07 74 - 08 75	STAR	A	752267
WILMINGTON	GTR MIL NEW CAS ART WARS	DE	13781		39 40N	075 36W	0028	01 50 - 12 54	STAR	MA	713167
WILMINGTON	GTR MIL NEW CAS ART WARS	DE	13781		39 40N	075 36W	0024	01 50 - 12 54	STAR	SA	715634
WILMINGTON	GTR MIL NEW CAS ART WARS	DE	13781		39 40N	075 36W	0028	01 57 - 12 57	STAR	SA	701778
WILMINGTON	GTR MIL NEW CAS ART WARS	DE	13781		39 40N	075 36W	0024	01 58 - 12 73	STAR	MA	750466
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 50 - 12 54	STAR	A	714151.47K
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 50 - 12 54	STAR	A	714151.47I
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 50 - 12 54	STAR	A	714151.47L
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 50 - 12 54	STAR	A	713371
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 50 - 12 54	STAR	A	714151.47J
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 58 - 12 72	STAR	MA	750766.47J
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 58 - 12 72	STAR	MA	714737
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 58 - 12 73	STAR	A	751800.3
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 58 - 12 58	STAR	MA	713770
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 70 - 12 70	STAR	MA	713770
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	05 70 - 12 70	STAR	MA	701772
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 71 - 12 71	STAR	MA	713770
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 72 - 12 72	STAR	MA	714175
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	11 72 - 12 72	STAR	MA	701772
WASHINGTON	NATIONAL ART WARS	DC	13743	72405	38 51N	077 02W	3023	01 73 - 12 73	STAR	A	751800.3
WASHINGTON	DULLES INT ART WARS	DC	93738	72403	38 57N	077 27W	3084	01 58 - 12 70	STAR	SA	713303
WASHINGTON	DULLES INT ART WARS	DC	93738	72403	38 57N	077 27W	3084	01 57 - 12 71	STAR	SA	713872
WASHINGTON	DULLES INT ART WARS	DC	93738	72403	38 57N	077 27W	3084	01 70 - 12 71	STAR	SA	714565
WASHINGTON	DULLES INT ART WARS	DC	93738	72403	38 57N	077 27W	3084	01 71 - 12 71	STAR	MA	714175
WASHINGTON	DULLES INT ART WARS	DC	93738	72403	38 57N	077 27W	3084	01 72 - 12 72	STAR	MA	714175
JAYTONA BEACH	MUNICIPAL ART WARS	FL	12834		29 11N	081 33W	3015	01 57 - 12 71	STAR	SA	750035
FORT MEYERS	PAGE FIELD WARS	FL	12835	72210	28 39N	081 53W	3004	01 58 - 12 73	STAR	A	750878
JACKSONVILLE	JESSON ART WARS	FL	12889	72208	30 25N	081 39W	3012	01 58 - 12 58	STAR	SA	712856
JACKSONVILLE	JESSON ART WARS	FL	12889	72208	30 25N	081 39W	3012	01 70 - 12 70	STAR	SA	712856
JACKSONVILLE	JESSON ART WARS	FL	12889	72208	30 25N	081 39W	3012	01 72 - 12 72	STAR	SA	701772
JACKSONVILLE	JESSON ART WARS	FL	12889	72208	30 25N	081 39W	3012	01 73 - 12 73	STAR	SA	760163
JACKSONVILLE	JESSON ART WARS	FL	12889	72208	30 25N	081 39W	3009	01 75 - 12 75	STAR	A	752247
MIAMI	INTERNATIONAL ART W	FL	12838	72202	25 48N	080 16W	3004	01 57 - 12 71	STAR	MA	713861
MIAMI	INTERNATIONAL ART	FL	12838	72202	25 48N	080 16W	3004	01 70 - 12 74	STAR	A	752115.3
MIAMI	INTERNATIONAL AP	FL	12838	72202	25 48N	080 16W	3004	01 71 - 12 71	STAR	MA	713861
MIAMI	INTERNATIONAL AP	FL	12838	72202	25 48N	080 16W	3004	01 72 - 12 72	STAR	MA	701772
MIAMI	INTERNATIONAL AP	FL	12838	72202	25 48N	080 16W	3004	01 73 - 12 73	STAR	MA	750183
MIAMI	INTERNATIONAL	FL	12838	72202	25 48N	080 16W	3017	01 74 - 12 74	STAR	A	752115.3
MIAMI	INTERNATIONAL	FL	12838	72202	25 48N	080 16W	3017	08 74 - 08 75	STAR	MA	751924.3
MIAMI	INTERNAT	FL	12838	72202	25 48N	080 16W	3017	03 75 - 03 75	STAR	A	751924.3
MILTON	WHITING F	FL	93841		30 43N	087 01W	3054	01 52 - 12 71	STAR	SA	714567
JALANOO	"CCOY"	FL	12815		28 27N	081 18W	3032	01 56 - 12 57	STAR	SA	701772
JALANOO	"CCOY"	FL	12815		28 27N	081 18W	3032	01 70 - 12 70	STAR	SA	701772
JALANOO	"CCOY"	FL	12815		28 27N	081 18W	3032	01 74 - 12 74	STAR	A	751046.56

CITY	NAME - TYPE	ST	WGS	WGS	LAT	LONG	ELEV	PERIOD OF RECORD	SUMMARY TYPE	SUM FREQ	TAB#/REMARKS
ORLANDO	HERNOON APT WGRS	FL	12841	72205	28 33N	081 20W	0037	01 50 - 12 54	STAR	A	T11740
ORLANDO	HERNOON APT WGRS	FL	12841	72205	28 33N	081 20W	0037	01 50 - 12 54	STAR	NR	T50580
ORLANDO	HERNOON APT WGRS	FL	12841	72205	28 33N	081 20W	0037	01 50 - 12 54	STAR	NR	T14855
ORLANDO	HERNOON APT WGRS	FL	12841	72205	28 33N	081 20W	0037	01 71 - 12 71	STAR	SA	T01772
PANAMA CITY	TYNDALL AFB	FL	12846	74775	30 04N	089 35W	0007	01 73 - 12 73	STAR	NR	T50241
PENSACOLA	FOREST SHERMAN NAS	FL	02855	72222	30 21N	087 18W	0010	01 66 - 12 70	STAR	SA	T14171
PENSACOLA	FOREST SHERMAN NAS	FL	02855	72222	30 21N	087 18W	0010	01 67 - 12 71	STAR	T14	087
TALLAHASSEE	MUNICIPAL APT WGRS	FL	02805	72214	30 23N	084 22W	0021	01 50 - 12 64	STAR	A	T52115.3
TALLAHASSEE	MUNICIPAL APT WGRS	FL	02805	72214	30 23N	084 22W	0021	01 50 - 12 64	STAR	NR	T50580
TALLAHASSEE	MUNICIPAL APT WGRS	FL	02805	72214	30 23N	084 22W	0021	01 50 - 12 73	STAR	NR	T50415
TALLAHASSEE	MUNICIPAL APT WGRS	FL	02805	72214	30 23N	084 22W	0021	01 72 - 12 72	STAR	NR	T50014
TAMPA	MACDILL AFB	FL	12810	74788	27 51N	082 30W	0008	01 72 - 12 72	STAR	NR	T50838
TAMPA	MACDILL AFB	FL	12810	74788	27 51N	082 30W	0008	01 68 - 12 68	STAR	SA	T12957
TAMPA	INTERNATIONAL APT WGRS	FL	12842	72211	27 58N	082 32W	0010	01 50 - 12 70	STAR	SA	T12957
TAMPA	INTERNATIONAL APT WGRS	FL	12842	72211	27 58N	082 32W	0010	01 50 - 12 84	STAR	NR	T50500
TAMPA	INTERNATIONAL APT WGRS	FL	12842	72211	27 58N	082 32W	0010	01 55 - 12 80	STAR	SA	T12928
TAMPA	INTERNATIONAL APT WGRS	FL	12842	72211	27 58N	082 32W	0010	01 69 - 12 73	STAR	A	T15377
TAMPA	INTERNATIONAL APT WGRS	FL	12842	72211	27 58N	082 32W	0010	01 71 - 12 71	STAR	SA	T14113
TAMPA	INTERNATIONAL APT WGRS	FL	12842	72211	27 58N	082 32W	0010	01 72 - 12 72	STAR	SA	T14346
TAMPA	INTERNATIONAL APT WGRS	FL	12842	72211	27 58N	082 32W	0010	01 72 - 12 72	STAR	NR	T13267
TAMPA	INTERNATIONAL APT WGRS	FL	12842	72211	27 58N	082 32W	0010	01 72 - 12 72	STAR	NR	T50838
TAMPA	INTERNATIONAL APT WGRS	FL	12842	72211	27 58N	082 32W	0010	01 73 - 12 73	STAR	A	T50487.3
TAMPA	INTERNATIONAL APT WGRS	FL	12842	72211	27 58N	082 32W	0010	01 73 - 12 73	STAR	SA	T50413
TAMPA	INTERNATIONAL APT WGRS	FL	12842	72211	27 58N	082 32W	0003	01 74 - 12 74	STAR	A	T51046
TAMPA	INTERNATIONAL APT WGRS	FL	12842	72211	27 58N	082 32W	0003	01 74 - 12 74	STAR	A	T51184
WEST PALM BEACH	INTERNATIONAL APT WGRS	FL	12844	72203	28 41N	080 08W	0009	01 70 - 12 70	STAR	SA	T01772
ALBANY	TURNER AFB	GA	13815		31 35N	084 05W	0068	01 62 - 12 68	STAR	SA	T14372
ALBANY	NAS	GA	13815		31 35N	084 05W	0065	01 68 - 12 73	STAR	SA	T15175.3
ALBANY	NAS	GA	13815		31 35N	084 05W	0065	01 68 - 12 68	STAR	NR	T50600.3
ALBANY	NAS	GA	13815		31 35N	084 05W	0065	01 68 - 04 74	STAR	NR	T50880.3
ALBANY	NAS	GA	13815		31 35N	084 05W	0065	01 70 - 12 70	STAR	NR	T50680.3
ALBANY	NAS	GA	13815		31 35N	084 05W	0065	01 70 - 12 70	STAR	SA	T13252
ALBANY	NAS	GA	13815		31 35N	084 05W	0065	01 71 - 12 71	STAR	NR	T50680.3
ALBANY	NAS	GA	13815		31 35N	084 05W	0065	01 72 - 12 72	STAR	NR	T50880.3
ALBANY	NAS	GA	13815		31 35N	081 12W	0065	01 73 - 12 73	STAR	NR	T50880.3
ALMA	BACON COUNTY APT CAR	GA	13815		31 35N	081 12W	0065	01 74 - 04 74	STAR	NR	T50880.3
ATHENS	SEN EPPS FIELD WGRS	GA	13870		31 32N	082 31W	0082	01 54 - 12 58	STAR	SA	T15175.3
ATHENS	SEN EPPS FIELD WGRS	GA	13873	72311	33 57N	083 19W	0247	01 69 - 12 73	STAR	SA	T15175.3
ATLANTA	WGRS	GA	13873	72311	33 57N	083 19W	0245	01 70 - 12 70	STAR	SA	T13252
ATLANTA	WGRS	GA	13874	72319	33 39N	084 25W	0302	01 58 - 12 63	STAR	SA	T12888
ATLANTA	WGRS	GA	13874	72319	33 39N	084 25W	0311	01 67 - 12 71	STAR	SA	T01772
ATLANTA	WGRS	GA	13874	72319	33 39N	084 25W	0315	01 68 - 12 73	STAR	SA	T15175.3
ATLANTA	WGRS	GA	13874	72319	33 39N	084 25W	0311	01 70 - 12 70	STAR	SA	T01772
ATLANTA	WGRS	GA	13874	72319	33 39N	084 25W	0311	01 72 - 12 72	STAR	NR	T13404
ATLANTA	WGRS	GA	13874	72319	33 39N	084 25W	0315	01 73 - 12 73	STAR	NR	T14388
AUGUSTA	BUSH FIELD WGRS	GA	03820	72318	33 22N	081 58W	0046	01 55 - 12 55	STAR	A	T51126
AUGUSTA	BUSH FIELD WGRS	GA	03820	72318	33 22N	081 58W	0046	01 67 - 12 55	STAR	SA	T01371
AUGUSTA	BUSH FIELD WGRS	GA	03820	72318	33 22N	081 58W	0046	01 68 - 12 73	STAR	SA	T14010
AUGUSTA	BUSH FIELD WGRS	GA	03820	72318	33 22N	081 58W	0046	01 70 - 12 70	STAR	SA	T15175.3
AUGUSTA	BUSH FIELD WGRS	GA	03820	72318	33 22N	081 58W	0046	01 72 - 12 72	STAR	NR	T13252
AUGUSTA	BUSH FIELD WGRS	GA	03820	72318	33 22N	081 58W	0046	01 75 - 12 75	STAR	NR	T14399
AUGUSTA	BUSH FIELD WGRS	GA	03820	72318	33 22N	081 58W	0046	01 76 - 03 78	STAR	NR	T14873.52
BRUNSWICK	GLYNCO NAS	GA	03826		31 15N	081 28W	0010	01 57 - 12 71	STAR	NR	T14372
BRUNSWICK	GLYNCO NAS	GA	03826		31 15N	081 28W	0010	01 59 - 12 73	STAR	SA	T15175.3
BRUNSWICK	GLYNCO NAS	GA	03826		31 15N	081 28W	0010	01 70 - 12 70	STAR	SA	T13252
COLUMBUS	METROPOLITAN APT WGRS	GA	03842		32 31N	084 56W	0123	01 67 - 12 71	STAR	SA	T14066
COLUMBUS	METROPOLITAN APT WGRS	GA	03842		32 31N	084 56W	0118	01 69 - 12 73	STAR	SA	T15175.3
COLUMBUS	METROPOLITAN APT WGRS	GA	03842		32 31N	084 56W	0123	01 70 - 12 70	STAR	A	T14041
MCDON	LEWIS & WILSON APT WGRS	GA	03813	72317	32 42N	083 39W	0110	01 67 - 12 71	STAR	SA	T14372
MCDON	LEWIS & WILSON APT WGRS	GA	03813	72317	32 42N	083 39W	0110	01 68 - 12 73	STAR	SA	T15175.3
MCDON	LEWIS & WILSON APT WGRS	GA	03813	72317	32 42N	083 39W	0110	01 70 - 12 70	STAR	SA	T13252
SAVANNAH	TRAVIS FLD MGR WGRS	GA	03822	72207	32 08N	081 12W	0018	01 68 - 12 70	STAR	SA	T13050
SAVANNAH	TRAVIS FLD MGR WGRS	GA	03822	72207	32 08N	081 12W	0018	01 67 - 12 71	STAR	SA	T14065
SAVANNAH	TRAVIS FLD MGR WGRS	GA	03822	72207	32 08N	081 12W	0018	01 68 - 12 73	STAR	SA	T15175.3
SAVANNAH	TRAVIS FLD MGR WGRS	GA	03822	72207	32 08N	081 12W	0018	01 70 - 12 70	STAR	SA	T01772
SAVANNAH	TRAVIS FLD MGR WGRS	GA	03822	72207	32 08N	081 12W	0018	01 70 - 12 70	STAR	SA	T01772
SAVANNAH	TRAVIS FLD MGR WGRS	GA	03822	72207	32 08N	081 12W	0018	01 73 - 12 72	STAR	NR	T14398
SAVANNAH	TRAVIS FLD MGR WGRS	GA	03822	72207	32 08N	081 12W	0018	01 73 - 06 74	STAR	SA	T50649
SAVANNAH	TRAVIS FLD MGR WGRS	GA	03822	72207	32 08N	081 12W	0018	01 75 - 12 75	STAR	A	T52184
SAVANNAH	HUNTER AFB	GA	13824		32 01N	081 02W	0018	01 68 - 12 70	STAR	SA	T15175.3
BARBERS POINT	NAS	HI	22914	91178	21 19N	158 04W	0015	01 52 - 12 72	STAR	NR	T50709
BARBERS POINT	NAS	HI	22914	91178	21 19N	158 04W	0015	01 57 - 12 71	STAR	NR	T50121
HILO	LITMAN FIELD WGRS	HI	21904	91285	19 43N	155 04W	0010	08 52 - 07 57	STAR	NR	T13223
HONOLULU	JOHN ROGERS INTL APT WGRS	HI	22921	91182	21 21N	157 56W	0012	01 60 - 12 64	STAR	NR	T5C121
KAHULUI	NAS	HI	22918	91190	20 54N	156 26W	0015	01 56 - 12 70	STAR	SA	T13225
PUUHAE	CAR	HI	22925		20 50N	156 28W	0040	01 53 - 12 57	STAR	SA	T13204
BOISE	MUNICIPAL APT WGRS	ID	24131	72581	43 34N	116 13W	0870	01 60 - 12 64	STAR	NR	T50544
BOISE	FANNING FIELD FRA CAR	ID	24145		43 31N	112 04W	1449	01 55 - 12 64	STAR	NR	T51224.3
BOISE	MOUNTAIN HOPE AFB	ID	24151		42 10N	112 19W	1368	01 48 - 12 54	STAR	NR	T51224.3
BOISE	MUNICIPAL APT WGRS	ID	24156	72578	43 03N	115 52W	0812	01 55 - 12 58	STAR	NR	T50544
BOISE	MUNICIPAL APT WGRS	ID	24156	72578	42 55N	112 36W	1356	01 55 - 12 54	STAR	NR	T51224.3.60
BOISE	MUNICIPAL APT WGRS	ID	24156	72578	42 55N	112 36W	1356	01 58 - 12 62	STAR	SA	T10870
BOISE	MUNICIPAL APT WGRS	ID	24156	72578	42 55N	112 36W	1265	01 65 - 12 74	STAR	NR	T51224.3.70
BELLEVILLE	SCOTT AFB	IL	14812		38 33N	089 51W	0135	01 51 - 12 70	STAR	SA	T51003.3
CHICAGO	MIDWAY APT WGRS	IL	14819	72534	41 47N	087 45W	0187	01 54 - 12 73	STAR	SA	T50468
CHICAGO	MIDWAY APT WGRS	IL	14819	72534	41 47N	087 45W	0187	01 54 - 12 70	STAR	SA	T50404
CHICAGO	MIDWAY APT WGRS	IL	14819	72534	41 47N	087 45W	0187	01 57 - 12 57	STAR	SA	T11920

CITY	NAME - TYPE	ST	LEAS #	SPD #	LAT	LONG	ELEV	PERIOD OF RECORD	SUMMARY TYPE	SUMM PREC	TABL/RECORDS
CHICAGO	MIDWAY ART WARS	IL	14819	72534	41 47N	087 45W	2187	01 80 - 12 58	STAR	A	T14843
CHICAGO	MIDWAY ART WARS	IL	14819	72534	41 47N	087 45W	2187	01 70 - 12 70	STAR	SA	T01772
CHICAGO	MIDWAY ART WARS	IL	14819	72534	41 47N	087 45W	2187	01 71 - 12 73	STAR	A	T51304
CHICAGO	MIDWAY ART WARS	IL	14819	72534	41 47N	087 45W	2187	01 71 - 12 71	STAR	SA	T01772
CHICAGO	MIDWAY ART WARS	IL	14819	72534	41 47N	087 45W	2187	01 72 - 12 72	STAR	A	T14843
CHICAGO	MIDWAY ART WARS	IL	14819	72534	41 47N	087 45W	2187	12 72 - 11 73	STAR	SA	T50404
CHICAGO	MIDWAY ART WARS	IL	14819	72534	41 47N	087 45W	2187	12 72 - 11 73	STAR	SA	T50466
CHICAGO	MIDWAY ART WARS	IL	14819	72534	41 47N	087 45W	2187	01 73 - 12 73	STAR	A	T50549.3
CHICAGO	MIDWAY ART WARS	IL	14819	72534	41 47N	087 45W	2187	01 74 - 12 74	STAR	SA	T51207.3
CHICAGO	MIDWAY ART WARS	IL	14819	72534	41 47N	087 45W	2187	01 75 - 12 75	STAR	A	T52403.3
CHICAGO	MIDWAY ART WARS	IL	14819	72534	41 47N	087 45W	2187	01 75 - 12 75	STAR	A	T52344.3
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 83 - 12 83	STAR	A	T11860
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 85 - 12 85	STAR	A	T11860
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 86 - 12 86	STAR	A	T11860
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 87 - 12 87	STAR	A	T11860
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 88 - 12 88	STAR	SA	T51855.3
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 89 - 12 89	STAR	A	T11860
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	06 71 - 11 71	STAR	MA	T13303
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 88 - 12 88	STAR	MA	T14801
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 74 - 12 74	STAR	MA	T50259
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 80 - 12 80	STAR	A	T51888.3
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 87 - 12 71	STAR	SA	T13593
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 85 - 12 73	STAR	SA	T51153.3
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 85 - 12 88	STAR	SA	T12088
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 85 - 12 89	STAR	SA	T50860.3
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 85 - 12 89	STAR	SA	T51308.3
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 70 - 12 70	STAR	SA	T12787
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 72 - 12 72	STAR	MA	T50443
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 73 - 12 73	STAR	MA	T14842
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 73 - 12 73	STAR	MA	T50443
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 50 - 12 54	STAR	A	T13700
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 58 - 12 52	STAR	MA	T14844
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 63 - 12 57	STAR	MA	T01772
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 66 - 12 70	STAR	MA	T13357
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 70 - 12 70	STAR	MA	T14823
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 70 - 12 74	STAR	SA	T51153.3
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 67 - 12 71	STAR	SA	T13344
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 67 - 12 71	STAR	MA	T13563
CHICAGO	0 WARE INL ART WARS	IL	94846	72530	41 50N	087 54W	0211	01 70 - 12 74	STAR	MA	T51153.3
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 50 - 12 64	STAR	SA	T11868
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 54 - 12 64	STAR	A	T50423
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 66 - 12 70	STAR	SA	T12881
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 66 - 12 70	STAR	SA	T50020
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 72 - 12 72	STAR	SA	T15277
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 72 - 12 72	STAR	SA	T50220
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 68 - 12 64	STAR	SA	T52126.3
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 70 - 12 74	STAR	SA	T15875.3
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 75 - 12 75	STAR	SA	T52409.3
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 55 - 12 74	STAR	MA	T51827
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 66 - 12 71	STAR	SA	T50282
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 67 - 12 71	STAR	A	T13709
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 70 - 12 70	STAR	A	T13534
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 71 - 12 71	STAR	A	T13534
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 50 - 12 54	STAR	A	T13709
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 72 - 12 71	STAR	A	T15186
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 70 - 12 74	STAR	A	T51799
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 70 - 12 74	STAR	A	T51799
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 60 - 12 64	STAR	SA	T50708.3
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 62 - 12 70	STAR	MA	T50127
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 50 - 12 54	STAR	MA	T50974.3
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 54 - 12 58	STAR	MA	T15008
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 50 - 12 70	STAR	SA	T15169
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 53 - 12 72	STAR	MA	T14650
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 72 - 12 72	STAR	MA	T01772
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 63 - 12 72	STAR	MA	T50300
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 70 - 12 74	STAR	MA	T51200.3
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 73 - 12 73	STAR	MA	T50300
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 50 - 12 54	STAR	SA	T11898
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	10 48 - 09 54	STAR	SA	T11898
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 58 - 12 52	STAR	SA	T11898
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 64 - 12 54	STAR	A	T50064
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 69 - 12 73	STAR	SA	T15172
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 70 - 12 74	STAR	SA	T15675.3
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 70 - 12 74	STAR	SA	T15675.3
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 72 - 12 72	STAR	SA	T15207
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 73 - 12 73	STAR	SA	T51144.3
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	04 74 - 07 74	STAR	A	T50329
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 75 - 12 75	STAR	SA	T52408.3
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 58 - 12 52	STAR	SA	T11898
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 54 - 12 58	STAR	SA	T11898
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 50 - 12 54	STAR	SA	T11898
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 54 - 12 54	STAR	A	T52099
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 56 - 12 70	STAR	SA	T12881
EVANSVILLE	ORESS MEMORIAL ART WARS	IN	93817	72432	38 03N	087 32W	0122	01 67 - 12 71	STAR	MA	T14818

CITY	NAME - TYPE	ST	LEAS #	LONG #	LAT	LONG	ELEV	PERIOD RECORD	3F	SUMMARY TYPE	SUM FREQ	TRAIL/REMARKS
LOUISVILLE	STANHOFFORD FIELD WARS	KY	33821	72423	38 11A	085 44W	0149	01 70 - 12 70		STAR	SA	T12274
LOUISVILLE	STANHOFFORD FIELD WARS	KY	33821	72423	38 11A	085 44W	0149	01 72 - 12 72		STAR	SA	T15172
LOUISVILLE	STANHOFFORD FIELD WARS	KY	33821	72423	38 11A	085 44W	0149	01 73 - 12 73		STAR	SA	T30328
PROUDMAN	BARKLEY ART CAR	KY	33818		37 04N	088 46W	0121	01 50 - 12 54		STAR	SA	T11858
PROUDMAN	BARKLEY ART FSS	KY	33818		37 04N	088 46W	0121	01 55 - 12 54		STAR	FM	T13034
PROUDMAN	BARKLEY ART FSS	KY	33818		37 04N	088 46W	0121	01 50 - 12 54		STAR	FM	T14528
ALEXANDRIA	ESLER FIELD	LA	13935		31 23N	092 18W	0036	01 70 - 12 73		STAR	SA	T50568
ALEXANDRIA	ESLER FIELD	LA	13935		31 23N	092 18W	0036	01 70 - 12 74		STAR	SA	T51266.3
BATON ROUGE	RYAN FIELD MPO WARS	LA	13970		30 32N	091 09W	0024	01 56 - 12 54		STAR	FM	T14291
BATON ROUGE	RYAN FIELD MPO WARS	LA	13970		30 32N	091 09W	0024	01 56 - 12 70		STAR	A	T13080
BATON ROUGE	RYAN FIELD MPO WARS	LA	13970		30 32N	091 09W	0024	01 70 - 12 74		STAR	SA	T51258.3
BATON ROUGE	RYAN FIELD MPO WARS	LA	13970		30 32N	091 09W	0024	01 70 - 12 70		STAR	A	T13080
BATON ROUGE	RYAN FIELD MPO WARS	LA	13970		30 32N	091 09W	0024	01 72 - 12 72		STAR	FM	T14338
BATON ROUGE	RYAN FIELD MPO WARS	LA	13970		30 32N	091 09W	0024	01 72 - 12 72		STAR	A	T51096.3
LA FAYETTE	MUNICIPAL ART CAR	LA	13876		30 12N	091 59W	0013	01 54 - 12 58		STAR	SA	T50753
LAKE CHARLES	MUNICIPAL ART WARS	LA	03837	72240	30 07N	093 13W	0005	01 58 - 12 70		STAR	A	T50886
LAKE CHARLES	MUNICIPAL ART WARS	LA	03837	72240	30 07N	093 13W	0005	01 58 - 12 70		STAR	A	T13060
LAKE CHARLES	MUNICIPAL ART WARS	LA	03837	72240	30 07N	093 13W	0005	01 70 - 12 70		STAR	A	T13060
LAKE CHARLES	MUNICIPAL ART WARS	LA	03837	72240	30 07N	093 13W	0005	01 70 - 12 74		STAR	SA	T51268.3
LAKE CHARLES	WARS	LA	13841	72240	30 13N	093 09W	0005	01 58 - 12 62		STAR	FM	T50748
LAKE CHARLES	WARS	LA	13841	72240	30 13N	093 09W	0005	01 58 - 12 62		STAR	SA	T51002.3
MONROE	SELMAH FIELD CAR	LA	13842		32 31N	092 03W	0028	01 54 - 12 58		STAR	SA	T51285.3
MONROE	SELMAH FIELD CAR	LA	13842		32 31N	092 03W	0028	01 54 - 12 58		STAR	SA	T50555
NEW ORLEANS	MOISANT INL ART WARS	LA	12918	72231	29 59N	090 15W	0006	01 60 - 12 54		STAR	FM	T13287
NEW ORLEANS	MOISANT INL ART WARS	LA	12918	72231	29 59N	090 15W	0006	01 66 - 12 70		STAR	A	T13060
NEW ORLEANS	MOISANT INL ART WARS	LA	12918	72231	29 59N	090 15W	0006	01 67 - 12 71		STAR	FM	T13574
NEW ORLEANS	MOISANT INL ART WARS	LA	12918	72231	29 59N	090 15W	0001	01 68 - 12 73		STAR	SA	T50827
NEW ORLEANS	MOISANT INL ART WARS	LA	12918	72231	29 59N	090 15W	0006	01 69 - 12 73		STAR	FM	T50308
NEW ORLEANS	MOISANT INL ART WARS	LA	12918	72231	29 59N	090 15W	0006	01 70 - 12 70		STAR	A	T13060
NEW ORLEANS	MOISANT INL ART WARS	LA	12918	72231	29 59N	090 15W	0006	01 74 - 12 74		STAR	FM	T52214.3
NEW ORLEANS	MOISANT INL ART WARS	LA	12918	72231	29 59N	090 15W	0006	01 75 - 12 75		STAR	FM	T52214.3
NEW ORLEANS	MOISANT INL ART WARS	LA	12918	72231	29 59N	090 15W	0006	10 75 - 12 75		STAR	FM	T52231
NEW ORLEANS	MOISANT INL ART WARS	LA	12918	72231	29 59N	090 15W	0006	01 76 - 05 78		STAR	FM	T52231
NEW ORLEANS	MOISANT INL ART WARS	LA	12918	72231	29 59N	090 15W	0001	01 67 - 12 71		STAR	SA	T51018
NEW ORLEANS	MOISANT INL ART WARS	LA	12918	72231	29 59N	090 15W	0001	01 70 - 12 74		STAR	SA	T51804.3
SHREVEPORT	MUNICIPAL ART WARS	LA	13857	72248	32 28N	093 49W	0081	01 60 - 12 64		STAR	A	T13121
SHREVEPORT	MUNICIPAL ART WARS	LA	13857	72248	32 28N	093 49W	0081	01 67 - 12 71		STAR	SA	T14024
SHREVEPORT	MUNICIPAL ART WARS	LA	13857	72248	32 28N	093 49W	0081	01 70 - 12 74		STAR	SA	T51268.3
SHREVEPORT	MUNICIPAL ART WARS	LA	13857	72248	32 28N	093 49W	0081	01 71 - 12 75		STAR	SA	T52256.47H
SHREVEPORT	MUNICIPAL ART WARS	LA	13857	72248	32 28N	093 49W	0081	01 71 - 12 75		STAR	SA	T52256.47H
SHREVEPORT	MUNICIPAL ART WARS	LA	13857	72248	32 28N	093 49W	0081	01 72 - 12 72		STAR	SA	T14338
SHREVEPORT	MUNICIPAL ART WARS	LA	13857	72248	32 28N	093 49W	0081	01 73 - 12 73		STAR	FM	T52445
AUGUSTA	STATE ART CAR	ME	14605		44 19N	069 48W	0108	01 50 - 12 54		STAR	SA	T50831.70
AUGUSTA	STATE ART CAR	ME	14605		44 19N	069 48W	0108	01 50 - 12 54		STAR	MSA	T50304
AUGUSTA	STATE ART CAR	ME	14605		44 19N	069 48W	0108	01 50 - 12 54		STAR	SA	T50482
AUGUSTA	STATE ART CAR	ME	14605		44 19N	069 48W	0108	01 50 - 12 54		STAR	SA	T50831.68
BRUNSWICK	NAS	ME	14611	74392	43 53N	068 56W	0024	01 50 - 12 54		STAR	SA	T13788
CARRIBOU	MUNICIPAL ART WARS	ME	14607	72712	46 52N	068 01W	0181	01 53 - 12 52		STAR	SA	T13788
OLD TOWN	FAR	ME	14622		44 57N	068 40W	0041	01 50 - 12 64		STAR	SA	T13788
PORTLAND	INTERNATIONAL ART WARS	ME	14754	72608	43 39N	070 19W	0024	01 55 - 12 54		STAR	SA	T50849
PORTLAND	INTERNATIONAL ART WARS	ME	14754	72608	43 39N	070 19W	0024	01 50 - 12 54		STAR	SA	T13788
PORTLAND	INTERNATIONAL ART WARS	ME	14754	72608	43 39N	070 19W	0024	10 73 - 08 74		STAR	SA	T13941
PORTLAND	INTERNATIONAL ART WARS	ME	14754	72608	43 39N	070 19W	0024	10 73 - 08 74		STAR	SA	T51268.3
ROCHESTER	PHILLIPS FIELD WAR	MD	13701		39 28N	076 10W	0018	01 59 - 12 57		STAR	FM	T13818
ANDREWS AFB	WASHINGTON DC	MD	13705	72403	38 48N	076 53W	0066	01 58 - 12 70		STAR	FM	T50028
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 50 - 12 54		STAR	SA	T14479.47J
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 50 - 12 54		STAR	A	T14035.47H
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 50 - 12 54		STAR	A	T14479.47I
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 50 - 12 54		STAR	SA	T14479.47L
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 50 - 12 64		STAR	SA	T14479.47K
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 54 - 12 54		STAR	SA	T11878
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 58 - 12 58		STAR	SA	T11878
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 59 - 12 73		STAR	FM	T50651
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 59 - 12 59		STAR	MSA	T13770
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 70 - 12 70		STAR	MSA	T13770
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 71 - 12 71		STAR	MSA	T13770
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 72 - 12 72		STAR	MSA	T14175
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0060	01 73 - 12 73		STAR	SA	T50282
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0047	01 74 - 12 74		STAR	MSA	T15280
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0047	01 74 - 12 74		STAR	FM	T51155
BALTIMORE	FRIENDSHIP INL ART WARS	MD	93721	72408	39 11N	076 40W	0047	01 75 - 12 75		STAR	A	T52268.3
CAMP DETRICH	AF	MD	13749		39 28N	077 27W	0101	01 49 - 12 52		STAR	SA	T50787.3
FORT HEARD	TIPTON AFB	MD	93733		39 35N	076 46W	0043	01 50 - 12 64		STAR	SA	T14479.47I
FORT HEARD	TIPTON AFB	MD	93733		39 35N	076 46W	0043	01 50 - 12 64		STAR	SA	T52371
FORT HEARD	TIPTON AFB	MD	93733		39 35N	076 46W	0043	01 60 - 12 54		STAR	SA	T14479.47L
FORT HEARD	TIPTON AFB	MD	93733		39 35N	076 46W	0043	01 60 - 12 64		STAR	SA	T14479.47K
FORT HEARD	TIPTON AFB	MD	93733		39 35N	076 46W	0043	01 60 - 12 64		STAR	SA	T14479.47J
HAGERSTOWN	MUNICIPAL ART SAME	MD	93708		39 42N	077 43W	0215	01 74 - 12 74		STAR	MSA	T15280.26
PATUXENT RIVER	NAS	MD	13721	72404	38 18N	076 25W	0014	01 53 - 12 72		STAR	FM	T14830
PATUXENT RIVER	NAS	MD	13721	72404	38 18N	076 25W	0014	01 57 - 12 71		STAR	FM	T50220
PATUXENT RIVER	NAS	MD	13721	72404	38 18N	076 25W	0014	01 59 - 12 59		STAR	MSA	T13770
PATUXENT RIVER	NAS	MD	13721	72404	38 18N	076 25W	0014	01 70 - 12 70		STAR	FM	T14156
PATUXENT RIVER	NAS	MD	13721	72404	38 18N	076 25W	0014	01 71 - 12 71		STAR	MSA	T13770
PATUXENT RIVER	NAS	MD	13721	72404	38 18N	076 25W	0014	01 72 - 12 72		STAR	MSA	T14175
SALISBURY	WICOMICO COUNTY ART CAR	MD	93720		38 20N	075 30W	0021	01 49 - 12 58		STAR	FM	T14830
SALISBURY	WICOMICO COUNTY ART CAR	MD	93720		38 20N	075 30W	0021	01 74 - 12 74		STAR	MSA	T15280
SEDFORD	L G HANSCOM FIELD AFB	MA	14702	74490	42 48N	071 17W	0045	01 53 - 12 57		STAR	SA	T01772
BOSTON	LOGAN INL ART WARS	MA	14739	72509	42 32N	071 02W	0009	01 56 - 12 70		STAR	SA	T13333
BOSTON	LOGAN INL ART WARS	MA	14739	72509	42 32N	071 02W	0009	01 57 - 12 71		STAR	SA	T01772

CITY	NAME - TYPE	ST	LEAS #	LEO #	LAT	LONG	ELEV	PERIOD OF RECORD	SUMMARY TYPE	SUM FREQ	TRNS/RQ/REMARKS
BOSTON	LOGAN INT APT WARS	MA	14739	72508	42 22N	071 02W	0000	01 72 - 12 72	STAR	SA	750656
CHICAGO FALLS	WESTOVER AFB	MA	14703	74491	42 12N	072 32W	0075	01 60 - 12 64	STAR	SA	713722
CHICAGO FALLS	WESTOVER AFB	MA	14703	74491	42 12N	072 32W	0075	01 60 - 12 64	STAR	SA	750972
FALMOUTH	STIS AFB	MA	14704		41 38N	070 31W	0042	01 50 - 12 54	STAR	SA	750421
PITTSFIELD	MUNICIPAL APT CAR	MA	14783		42 28N	073 18W	0258	01 48 - 12 58	STAR	SA	714019
SOUTH WELMOUTH	MUNICIPAL APT WARS	MA	14780		42 08N	070 56W	0051	01 70 - 12 74	STAR	SA	752034.3
WORCESTER	MUNICIPAL APT WARS	MA	34746		42 15N	071 52W	0305	01 55 - 12 59	STAR	S	711827
WORCESTER	MUNICIPAL APT WARS	MA	34746		42 15N	071 52W	0310	01 72 - 12 72	STAR	SA	750655
WORCESTER	MUNICIPAL APT WARS	MA	34746		42 15N	071 52W	0310	05 74 - 04 75	STAR	SA	751792
BENTON HARBOR	ROSS FIELD	MI	14871		42 08N	086 26W	0191	01 74 - 12 74	STAR	SA	751046.47H
DETROIT	CITY APT WARS	MI	14822		42 25N	083 01W	0191	01 60 - 12 73	STAR	A	715016
DETROIT	CITY APT WARS	MI	14822		42 25N	083 01W	0191	01 72 - 12 72	STAR	SA	750048
DETROIT	CITY APT WARS	MI	14822		42 25N	083 01W	0191	01 72 - 12 73	STAR	SA	750206
DETROIT	CITY APT WARS	MI	14822		42 25N	083 01W	0191	01 74 - 12 74	STAR	SA	751021
DETROIT	METRO-WAYNE CAP WARS	MI	94847	72537	42 25N	083 01W	0191	01 75 - 12 75	STAR	SA	752135
DETROIT	METRO-WAYNE CAP WARS	MI	94847	72537	42 14N	083 20W	0197	01 71 - 12 71	STAR	SA	750172
DETROIT	METRO-WAYNE CAP WARS	MI	94847	72537	42 14N	083 20W	0197	01 72 - 12 72	STAR	SA	750048
DETROIT	METRO-WAYNE CAP WARS	MI	94847	72537	42 14N	083 20W	0197	01 73 - 12 73	STAR	SA	750206
DETROIT	METRO-WAYNE CAP WARS	MI	94847	72537	42 14N	083 20W	0202	01 74 - 12 74	STAR	MA	752442
DETROIT	METRO-WAYNE CAP WARS	MI	94847	72537	42 14N	083 20W	0202	01 74 - 12 74	STAR	SA	752442
FLINT	BISHOP APT WARS	MI	14826	72637	42 14N	083 20W	0202	01 75 - 12 75	STAR	SA	751021
FLINT	BISHOP APT WARS	MI	14826	72637	42 50N	083 44W	0235	01 60 - 12 64	STAR	MA	752135
FLINT	BISHOP APT WARS	MI	14826	72637	42 50N	083 44W	0235	01 65 - 12 69	STAR	MA	750440
FLINT	BISHOP APT WARS	MI	14826	72637	42 50N	083 44W	0235	01 58 - 12 75	STAR	MA	752408
FLINT	BISHOP APT WARS	MI	14826	72637	42 50N	083 44W	0235	01 72 - 12 72	STAR	SA	751021
FLINT	BISHOP APT WARS	MI	14826	72637	42 50N	083 44W	0235	01 73 - 12 73	STAR	SA	751772
FLINT	BISHOP APT WARS	MI	14826	72637	42 50N	083 44W	0235	01 74 - 12 74	STAR	SA	750512
FLINT	BISHOP APT WARS	MI	14826	72637	42 50N	083 44W	0235	01 75 - 12 74	STAR	SA	751021
FLINT	BISHOP APT WARS	MI	14826	72637	42 50N	083 44W	0235	03 75 - 02 76	STAR	MA	752135
QUINN	KI SAWYER AFB	MI	94836		46 21N	087 24W	0377	01 55 - 12 87	STAR	SA	750228.3
QUINN	KI SAWYER AFB	MI	94836		46 21N	087 24W	0377	01 55 - 12 70	STAR	MA	750922
LANSING	CAPITAL CITY APT WARS	MI	14836	72539	42 47N	084 18W	0266	01 68 - 12 73	STAR	A	715016
MUSKOGON	MUSKOGON COUNTY APT WARS	MI	14840	72638	43 10N	086 14W	0192	01 87 - 12 71	STAR	SA	713800
SAGINAW	TRI-CITY APT CAR	MI	14845		43 32N	084 05W	0203	01 40 - 12 54	STAR	MA	752035.3
SAGINAW	TRI-CITY APT CAR	MI	14845		43 32N	084 05W	0203	01 50 - 12 54	STAR	SA	714236
SAGINAW	TRI-CITY APT CAR	MI	14845		43 32N	084 05W	0204	01 50 - 12 54	STAR	MA	713839
SAGINAW	TRI-CITY APT CAR	MI	14845		43 32N	084 05W	0204	01 74 - 12 74	STAR	MA	715290
TOVERSE CITY	CHERRY CAP CAR	MI	14850		44 44N	085 25W	0192	01 74 - 12 74	STAR	MA	713839
YPSILANTI	WILLOW RUN APT WARS	MI	14853		42 14N	083 32W	0237	10 63 - 09 68	STAR	A	715016
YPSILANTI	WILLOW RUN APT WARS	MI	14853		42 14N	083 32W	0237	10 63 - 09 68	STAR	SA	752125.3
ALEXANDRIA	MUNICIPAL APT CAR	MA	14810		45 52N	095 23W	0435	01 52 - 12 54	STAR	SA	713083
OULUTH	INTERNATIONAL APT WARS	MA	14813	72745	46 50N	092 11W	0434	01 67 - 12 71	STAR	SA	714006
OULUTH	INTERNATIONAL APT WARS	MA	14813	72745	46 50N	092 11W	0434	01 70 - 12 74	STAR	SA	715880.3
OULUTH	INTERNATIONAL APT WARS	MA	14813	72745	46 50N	092 11W	0434	01 70 - 12 70	STAR	SA	712751
MINNEAPOLIS	INTERNATIONAL APT WARS	MA	14822	72658	44 53N	093 13W	0262	01 58 - 12 72	STAR	MA	750087
MINNEAPOLIS	INTERNATIONAL APT WARS	MA	14822	72658	44 53N	093 13W	0262	01 60 - 12 64	STAR	MA	750218
MINNEAPOLIS	INTERNATIONAL APT WARS	MA	14822	72658	44 53N	093 13W	0262	01 55 - 12 74	STAR	MA	752551.3
MINNEAPOLIS	INTERNATIONAL APT WARS	MA	14822	72658	44 53N	093 13W	0262	01 87 - 12 71	STAR	MA	714006
MINNEAPOLIS	INTERNATIONAL APT WARS	MA	14822	72658	44 53N	093 13W	0262	01 70 - 12 70	STAR	SA	712751
ROCHESTER	MUNICIPAL APT WARS	MA	14825	72644	43 55N	092 30W	0402	01 58 - 12 73	STAR	MA	751085
BLOXI	KEESLER AFB	MS	13820		30 24N	088 55W	0000	01 60 - 12 64	STAR	MA	750775
BLOXI	KEESLER AFB	MS	13820		30 24N	088 55W	0000	01 50 - 12 54	STAR	A	750010
COLUMBUS	AFB	MS	13825		33 38N	088 27W	0065	01 58 - 12 74	STAR	SA	750475
COLUMBUS	AFB	MS	13825		33 38N	088 27W	0068	01 56 - 12 70	STAR	SA	750638
GREENVILLE	AFB	MS	13859	72238	33 31N	081 00W	0042	11 59 - 10 60	STAR	SA	714354
JACKSON	THOMPSON HAW WARS	MS	03940	72235	32 19N	090 05W	0110	01 55 - 12 54	STAR	A	752181
JACKSON	THOMPSON HAW WARS	MS	03940	72235	32 19N	090 05W	0110	01 55 - 12 60	STAR	MA	714408
JACKSON	THOMPSON HAW WARS	MS	03940	72235	32 19N	090 05W	0110	01 55 - 12 60	STAR	SA	711873
JACKSON	THOMPSON HAW WARS	MS	03940	72235	32 19N	090 05W	0110	01 58 - 12 70	STAR	SA	712825
JACKSON	THOMPSON HAW WARS	MS	03940	72235	32 19N	090 05W	0110	01 70 - 12 70	STAR	SA	712925
JACKSON	HAWKINS FIELD WARS	MS	13956	72235	32 20N	090 13W	0098	01 60 - 12 54	STAR	MA	714408
JACKSON	HAWKINS FIELD WARS	MS	13956	72235	32 20N	090 13W	0098	01 50 - 12 84	STAR	MA	713267
JACKSON	HAWKINS FIELD WARS	MS	13956	72235	32 20N	090 13W	0098	01 50 - 12 54	STAR	MA	713030
JACKSON	HAWKINS FIELD WARS	MS	13956	72235	32 20N	090 13W	0098	01 58 - 12 70	STAR	SA	751038
MOBILE	BIKE COUNTY CAR	MS	03918		31 15N	089 28W	0141	01 48 - 12 48	STAR	SA	712825
MERIDIAN	KEY FIELD WARS	MS	13865	72234	32 20N	088 45W	0090	01 58 - 12 70	STAR	SA	712825
MERIDIAN	KEY FIELD WARS	MS	13865	72234	32 20N	088 45W	0090	01 70 - 12 70	STAR	SA	712925
COLUMBIA	REGIONAL APT WARS	MO	03945	72445	38 49N	092 13W	0272	01 73 - 12 73	STAR	MA	750300
COLUMBIA	MUNICIPAL APT WARS	MO	03945	72445	38 58N	092 22W	0238	01 54 - 12 66	STAR	MA	713746
KANSAS CITY	MUNICIPAL APT WARS	MO	03947	72446	38 18N	094 33W	0315	01 58 - 12 74	STAR	MA	752323
KANSAS CITY	MUNICIPAL APT WARS	MO	03948	72446	39 07N	094 16W	0241	01 54 - 12 54	STAR	A	750692.3
KANSAS CITY	MUNICIPAL APT WARS	MO	03988	72446	39 07N	094 16W	0228	01 57 - 12 71	STAR	A	713785
KANSAS CITY	MUNICIPAL APT WARS	MO	03988	72446	39 07N	094 16W	0228	01 58 - 09 72	STAR	SA	750635
KIRKSVILLE	MUNICIPAL APT WARS	MO	03988	72446	39 07N	094 16W	0228	01 58 - 12 60	STAR	SA	712081
SAINT LOUIS	CANNON MEMORIAL APT	MO	14938		40 06N	092 13W	0264	01 50 - 12 54	STAR	A	751867
SAINT LOUIS	LAMBERT FIELD WARS	MO	13994	72434	38 45N	090 23W	0172	01 64 - 12 64	STAR	MA	750284
SAINT LOUIS	LAMBERT FIELD WARS	MO	13994	72434	38 45N	090 23W	0172	01 64 - 12 68	STAR	SA	711930.88
SAINT LOUIS	LAMBERT FIELD WARS	MO	13994	72434	38 45N	090 23W	0172	01 55 - 12 69	STAR	SA	712859.2
SAINT LOUIS	LAMBERT FIELD WARS	MO	13994	72434	38 45N	090 23W	0172	01 58 - 12 72	STAR	SA	750123
SAINT LOUIS	LAMBERT FIELD WARS	MO	13994	72434	38 45N	090 23W	0172	01 59 - 12 68	STAR	A	712084
SAINT LOUIS	LAMBERT FIELD WARS	MO	13994	72434	38 45N	090 23W	0172	01 70 - 12 74	STAR	SA	751153.3
SAINT LOUIS	LAMBERT FIELD WARS	MO	13994	72434	38 45N	090 23W	0172	10 70 - 09 71	STAR	A	713157
SAINT LOUIS	LAMBERT FIELD WARS	MO	13994	72434	38 45N	090 23W	0172	12 70 - 02 71	STAR	S	711930
SPRINGFIELD	MUNICIPAL APT WARS	MO	13995	72440	37 14N	093 23W	0388	01 58 - 12 70	STAR	SA	713182
BILLINGS	LOGAN FIELD WARS	MT	24033	72677	45 48N	108 32W	1092	01 57 - 12 71	STAR	SA	714105
BUTTE	SILVER BOW COUNTY APT CAR	MT	24135	72678	45 57N	112 30W	1600	01 56 - 12 50	STAR	SA	713365
CUSTER	CAR	MT	24040		46 07N	107 31W	0878	01 48 - 05 50	STAR	MA	714627
CUT BANK	MUNICIPAL APT CAR	MT	24137		46 08N	112 22W	1174	01 49 - 12 58	STAR	MA	750288

CITY	NAME - TYPE	ST	WGSN #	WGSN #	LAT	LONG	ELEV	PERIOD OF RECORD	SUMMARY TYPE	SUMM FREQ	TABLE/REMARKS
GLASGOW	INTERNATIONAL ART WARS	MT	24028	72768	48 13N	106 37W	2866	01 56 - 12 58	STAR	SA	751080-43
GLASGOW	INTERNATIONAL ART WARS	MT	24028	72768	48 13N	106 37W	2866	01 57 - 12 71	STAR	TA	527
HAYDEN	CITY-COUNTY ART WARS	MT	24013	72770	48 33N	108 48W	9788	01 57 - 12 71	STAR	TA	714627
HELENA	WARS	MT	24144	72772	48 38N	112 00W	1188	01 58 - 12 52	STAR	SA	713835
HELENA	WARS	MT	24144	72772	48 38N	112 00W	1188	01 58 - 10 74	STAR	TA	715236
KALISPELL	GLACIER PARK INL ART WARS	MT	24146	72779	48 18N	114 16W	3008	01 50 - 12 52	STAR	SA	715081
KALISPELL	GLACIER PARK INL ART WARS	MT	24146	72779	48 18N	114 16W	3008	01 53 - 12 72	STAR	SA	714723
LEWISTOWN	MUNICIPAL ART FFA	MT	24038	72780	47 33N	109 27W	1263	01 57 - 12 71	STAR	TA	714627
MILES CITY	MUNICIPAL ART FFA	MT	24037	72780	46 25N	109 52W	3002	01 57 - 12 71	STAR	TA	714135
MISSOULA	JOHNSON-BELL FIELD WARS	MT	24153	72773	46 55N	114 35W	3080	01 57 - 12 71	STAR	TA	714627
LINCOLN	AFB	NE	14804	72551	40 51N	088 45W	3358	01 58 - 12 53	STAR	A	752091
NORTH PLATTE	LEE BIRD FIELD WARS	NE	24023	72562	41 08N	100 41W	3848	01 58 - 12 54	STAR	TA	714312
NORTH PLATTE	LEE BIRD FIELD WARS	NE	24023	72562	41 08N	100 41W	3848	01 58 - 12 73	STAR	SA	715168
NORTH PLATTE	LEE BIRD FIELD WARS	NE	24023	72562	41 08N	100 41W	3848	05 73 - 04 75	STAR	TA	752018.3
OPAWHA	EPPLEY FIELD WARS	NE	14842	72553	41 18N	095 54W	3303	01 54 - 12 54	STAR	A	751933
OPAWHA	EPPLEY FIELD WARS	NE	14842	72553	41 18N	095 54W	3304	01 54 - 12 73	STAR	A	751288
OPAWHA	EPPLEY FIELD WARS	NE	14842	72553	41 18N	095 54W	3303	06 57 - 12 73	STAR	TA	752005
OPAWHA	EPPLEY FIELD WARS	NE	14842	72553	41 18N	095 54W	3298	01 58 - 12 73	STAR	A	701776
OPAWHA	EPPLEY FIELD WARS	NE	14842	72553	41 18N	095 54W	3298	01 73 - 12 73	STAR	A	751020
OPAWHA	OFFUTT AFB	NE	14848	72554	41 07N	085 55W	3314	01 50 - 12 54	STAR	TA	714312
SCOTTSBUFF	MUNICIPAL ART WARS	NE	24028	72568	41 52N	103 36W	1204	01 57 - 12 71	STAR	TA	750683.3
SCOTTSBUFF	MUNICIPAL ART WARS	NE	24028	72568	41 52N	103 36W	1204	01 57 - 12 71	STAR	TA	714842
SCOTTSBUFF	MUNICIPAL ART WARS	NE	24028	72568	41 52N	103 36W	1204	01 58 - 12 72	STAR	SA	750256
ELAO	MUNICIPAL ART FFA	NV	24121	72582	40 50N	115 47W	1547	01 58 - 12 73	STAR	SA	751028
ELY	YELLAND FIELD WARS	NV	23154	72488	38 17N	114 51W	1807	01 57 - 12 71	STAR	SA	713265
LAS VEGAS	NELLIS AFB	NV	23112	72488	38 15N	115 02W	2573	01 58 - 12 57	STAR	TA	715028
LAS VEGAS	MCABARRAN INL ART WARS	NV	23188	72388	38 05N	115 10W	3864	01 58 - 12 73	STAR	SA	750528-470
LAS VEGAS	MCABARRAN INL ART WARS	NV	23188	72388	38 05N	115 10W	3864	01 58 - 12 73	STAR	SA	750528-477
LOVELOCK	DEBART ART FFA	NV	24172	72488	40 04N	118 33W	1180	01 58 - 12 73	STAR	SA	751028
RENO	STEAD AFB	NV	23118	72488	39 40N	118 53W	1531	01 55 - 12 55	STAR	TA	715028
RENO	INTERNATIONAL ART WARS	NV	23185	72488	38 30N	118 47W	1343	01 50 - 12 54	STAR	A	752340
RENO	INTERNATIONAL ART WARS	NV	23185	72488	38 30N	118 47W	1343	01 50 - 12 80	STAR	TA	750878
WINNEMUCCA	MUNICIPAL ART WARS	NV	24126	72583	40 54N	117 48W	1322	01 58 - 12 73	STAR	SA	751028
CONCORD	MUNICIPAL ART WARS	NH	14746	72605	43 12N	071 30W	3104	01 50 - 12 64	STAR	A	715140-102
CONCORD	MUNICIPAL ART WARS	NH	14746	72605	43 12N	071 30W	3104	01 50 - 12 54	STAR	TA	750303
CONCORD	MUNICIPAL ART WARS	NH	14746	72605	43 12N	071 30W	3105	01 70 - 12 70	STAR	SA	712925
PORTSMOUTH	PERSE AFB	NH	04743	72605	43 05N	070 49W	3039	01 58 - 12 58	STAR	SA	712925
ATLANTIC CITY	WARS	NJ	93730	72407	38 27N	074 35W	0020	01 54 - 12 54	STAR	A	752113
ATLANTIC CITY	WARS	NJ	93730	72407	38 27N	074 35W	0020	01 54 - 12 54	STAR	TA	713831
ATLANTIC CITY	WARS	NJ	93730	72407	38 27N	074 35W	0020	01 58 - 12 72	STAR	TA	714622
ATLANTIC CITY	WARS	NJ	93730	72407	38 27N	074 35W	0020	01 70 - 12 74	STAR	A	752025
BEHMAR	ASC	NJ	04738	72407	40 11N	074 04W	0026	01 55 - 12 54	STAR	TA	713381
LARCHMOUNT	NAS	NJ	14780	72408	40 02N	074 19W	0026	01 58 - 12 72	STAR	SA	714630
NEWARK	WARS	NJ	14734	72502	40 42N	074 10W	0009	01 55 - 12 54	STAR	SA	712872
NEWARK	WARS	NJ	14734	72502	40 42N	074 10W	0009	01 50 - 12 54	STAR	SA	714547-47L
NEWARK	WARS	NJ	14734	72502	40 42N	074 10W	0009	01 50 - 12 54	STAR	SA	714547-47I
NEWARK	WARS	NJ	14734	72502	40 42N	074 10W	0009	01 50 - 12 54	STAR	SA	714547-47K
NEWARK	WARS	NJ	14734	72502	40 42N	074 10W	0009	01 50 - 12 54	STAR	SA	714547-47J
NEWARK	WARS	NJ	14734	72502	40 42N	074 10W	0009	01 58 - 12 70	STAR	TA	712910
NEWARK	WARS	NJ	14734	72502	40 42N	074 10W	0009	01 70 - 12 70	STAR	SA	712892
NEWARK	WARS	NJ	14734	72502	40 42N	074 10W	0009	01 71 - 12 71	STAR	SA	750300
TETERBORO	SAMA	NJ	04741	72502	40 51N	074 03W	0022	01 52 - 12 56	STAR	TA	712910
WRIGHTSTOWN	MCUIRE AFB	NJ	14708	72502	40 00N	074 38W	0046	01 55 - 12 70	STAR	SA	715100
ALBUQUERQUE	SUN-KIRTLAND INL ART WARS	NM	23050	72385	35 03N	108 37W	1819	01 50 - 12 54	STAR	TA	714164
ALBUQUERQUE	SUN-KIRTLAND INL ART WARS	NM	23050	72385	35 03N	108 37W	1819	01 75 - 12 75	STAR	TA	752113
FARMINGTON	MUNICIPAL ART FFA	NM	23090	72385	36 49N	108 14W	1877	01 54 - 12 59	STAR	SA	713028
FARMINGTON	MUNICIPAL ART FFA	NM	23090	72385	36 45N	108 14W	1877	05 53 - 04 58	STAR	TA	713160
GALLUP	SENATOR CLARKE FIELD SAMA	NM	23081	72385	35 31N	108 47W	1970	01 73 - 12 75	STAR	SA	752176
DOBBS	LEA COUNTY ART CAA	NM	93034	72385	32 41N	103 12W	1117	01 48 - 12 49	STAR	SA	752339
DOBBS	LEA COUNTY ART CAA	NM	93034	72385	32 41N	103 12W	1117	01 48 - 12 54	STAR	SA	714040
DOBBS	LEA COUNTY ART CAA	NM	93034	72385	32 41N	103 12W	1117	01 53 - 12 54	STAR	SA	752339
LAS CRUCES	WHITE SANDS AF	NM	23038	72385	35 23N	106 20W	1291	01 51 - 12 55	STAR	TA	752346
SANTA FE	CAA	NM	23040	72385	35 37N	108 05W	1925	01 50 - 12 54	STAR	TA	752346
ZUNI	INTERMEDIATE FIELD FSS	NM	93044	72385	35 08N	108 48W	1955	01 57 - 12 71	STAR	TA	714358
ALBANY	MUNICIPAL ART WARS	NY	14735	72518	42 49N	073 48W	3088	01 50 - 12 54	STAR	SA	714613
ALBANY	MUNICIPAL ART WARS	NY	14735	72518	42 49N	073 48W	3080	01 58 - 12 70	STAR	TA	712910
ALBANY	MUNICIPAL ART WARS	NY	14735	72518	42 49N	073 48W	3080	01 57 - 12 71	STAR	SA	714364-115G
ALBANY	MUNICIPAL ART WARS	NY	14735	72518	42 49N	073 48W	3080	01 57 - 12 71	STAR	SA	714364-47G
ALBANY	MUNICIPAL ART WARS	NY	14735	72518	42 49N	073 48W	3080	01 57 - 12 71	STAR	SA	714364-115A
ALBANY	MUNICIPAL ART WARS	NY	14735	72518	42 49N	073 48W	3080	01 57 - 12 71	STAR	SA	714364-115C
ALBANY	MUNICIPAL ART WARS	NY	14735	72518	42 49N	073 48W	3080	01 57 - 12 71	STAR	SA	714364-115M
ALBANY	MUNICIPAL ART WARS	NY	14735	72518	42 49N	073 48W	3080	01 57 - 12 71	STAR	SA	714364-47F
ALBANY	MUNICIPAL ART WARS	NY	14735	72518	42 49N	073 48W	3080	01 57 - 12 71	STAR	SA	714364-115B
ALBANY	MUNICIPAL ART WARS	NY	14735	72518	42 49N	073 48W	3080	01 57 - 12 71	STAR	SA	714364-115E
ALBANY	MUNICIPAL ART WARS	NY	14735	72518	42 49N	073 48W	3080	01 72 - 12 72	STAR	SA	750855
SINGHANTON	SAROGE COUNTY ART WARS	NY	04725	72518	42 13N	075 58W	0405	01 50 - 12 64	STAR	SA	714640
SINGHANTON	SAROGE COUNTY ART WARS	NY	04725	72518	42 13N	075 58W	0403	01 54 - 12 64	STAR	SA	701772
SINGHANTON	SAROGE COUNTY ART WARS	NY	04725	72518	42 13N	075 58W	0403	01 54 - 12 64	STAR	SA	750408
SINGHANTON	TRI-CITIES ART WARS	NY	14738	72518	42 05N	076 08W	3254	01 50 - 12 50	STAR	SA	750408
SUFFALO	GTR SUFFALO INL ART WARS	NY	14733	72528	42 56N	078 44W	3218	01 54 - 12 73	STAR	TA	750358
SUFFALO	GTR SUFFALO INL ART WARS	NY	14733	72528	42 56N	078 44W	3218	01 57 - 12 71	STAR	SA	701772
SUFFALO	GTR SUFFALO INL ART WARS	NY	14733	72528	42 56N	078 44W	3218	01 57 - 12 71	STAR	TA	714462
SUFFALO	GTR SUFFALO INL ART WARS	NY	14733	72528	42 56N	078 44W	3218	01 73 - 12 73	STAR	TA	750847.3
CLINTON	CHEMUNG COUNTY ART CAA	NY	14746	72516	42 10N	076 54W	3289	01 50 - 12 54	STAR	TA	751195.3
GLENS FALLS	LARREN COUNTY ART CAA	NY	14750	72516	43 21N	077 37W	3184	01 50 - 12 54	STAR	TA	751195.3
NEW YORK	LA GUARDIA ART WARS	NY	14732	72503	40 48N	073 52W	3015	01 51 - 12 50	STAR	TA	714022

CITY	NAME - TYPE	ST	WGS 84	WGS 84	LAT	LONG	ELEV	PERIOD OF RECORD	SUMMARY TYPE	SUMM FREQ	TRAB/REMARKS
CHATTANOOGA	LEVELL FIELD WARS	TN	13882	72324	35 32N	085 12W	0210	01 70 - 12 70	STAR	SA	712252
JACKSON	WHEELER	TN	02811		35 28N	088 55W	0129	01 48 - 12 54	STAR	MA	752458
KNOXVILLE	MCGHEE TYSON APT WARS	TN	13891	72325	35 49N	083 50W	0287	01 56 - 12 70	STAR	SA	713054
KNOXVILLE	MCGHEE TYSON APT WARS	TN	13891	72325	35 49N	083 50W	0288	01 56 - 12 70	STAR	SA	750621
MEMPHIS	INTERNATIONAL APT WARS	TN	13893	72324	35 03N	089 50W	0066	01 57 - 12 71	STAR	SA	713470
NASHVILLE	BERRY FIELD MAP WARS	TN	13897	72327	36 07N	086 41W	0177	01 50 - 12 54	STAR	A	714424.47M
NASHVILLE	BERRY FIELD MAP WARS	TN	13897	72327	36 07N	086 41W	0183	01 56 - 12 70	STAR	SA	712881
NASHVILLE	BERRY FIELD MAP WARS	TN	13897	72327	36 07N	086 41W	0183	01 70 - 12 70	STAR	A	712751
NASHVILLE	BERRY FIELD MAP WARS	TN	13897	72327	36 07N	086 41W	0184	01 71 - 12 75	STAR	MA	752420.3
NASHVILLE	BERRY FIELD MAP WARS	TN	13897	72327	36 07N	086 41W	0184	01 73 - 12 73	STAR	MA	750826
ABILENE	MUNICIPAL APT WARS	TX	13862	72268	32 26N	099 41W	0537	01 57 - 12 71	STAR	SA	701772
ABILENE	MUNICIPAL APT WARS	TX	13862	72268	32 26N	099 41W	0537	10 72 - 10 73	STAR	MA	750508
AMARILLO	ENGLISH FLD MAP WARS	TX	23047	72363	35 14N	101 42W	1099	01 55 - 12 54	STAR	SA	750360
AUSTIN	MUELLER MAP WARS	TX	13858	72254	30 18N	097 42W	0189	01 57 - 12 71	STAR	MA	714284
AUSTIN	MUELLER MAP WARS	TX	13858	72254	30 18N	097 42W	0189	01 59 - 12 73	STAR	MA	751101
BEVILLY	CHASE FIELD WARS	TX	12925		28 22N	087 40W	0060	01 55 - 12 59	STAR	SA	750893
BEVILLY	CHASE FIELD WARS	TX	12925		28 22N	087 40W	0060	01 55 - 12 70	STAR	A	713121
CORPUS CHRISTI	NAS	TX	12926		27 41N	087 17W	0006	01 55 - 12 59	STAR	SA	712781
COTULLA	MUNICIPAL APT CAR	TX	12947		28 24N	098 13W	0141	01 50 - 12 54	STAR	SA	750693
DALLAS	LOVE FIELD WARS	TX	13860	72258	32 51N	096 51W	0198	01 50 - 12 64	STAR	SA	713080
DALLAS	LOVE FIELD WARS	TX	13860	72258	32 51N	096 51W	0198	01 57 - 12 71	STAR	MA	714181
DALLAS	LOVE FIELD WARS	TX	13860	72258	32 51N	096 51W	0198	09 72 - 04 73	STAR	A	714960
DALLAS	LOVE FIELD WARS	TX	13860	72258	32 51N	096 51W	0199	09 72 - 12 72	STAR	A	701772
DEL RIO	LAUGHLIN AFB	TX	22001	72261	29 22N	100 47W	0327	01 55 - 12 58	STAR	SA	712781
EL PASO	INTERNATIONAL APT WARS	TX	23044	72270	31 48N	106 24W	1200	01 50 - 12 64	STAR	SA	714622
EL PASO	INTERNATIONAL APT WARS	TX	23044	72270	31 48N	106 24W	1198	01 72 - 12 72	STAR	SA	701772
FORT WORTH	GREATER SW IML APT WARS	TX	03827	72258	32 50N	097 03W	0175	01 57 - 12 71	STAR	MA	752415
FORT WORTH	GREATER SW IML APT WARS	TX	03827	72258	32 50N	097 03W	0175	01 57 - 12 71	STAR	SA	714024
FORT WORTH	GREATER SW IML APT WARS	TX	03827	72258	32 50N	097 03W	0175	09 72 - 04 74	STAR	MA	752415
FORT WORTH	MEACHAM FLD WARS	TX	13881		32 48N	087 21W	0215	01 48 - 12 52	STAR	SA	752393.3
GALVESTON	SCHOLTES FIELD WARS	TX	12923	72242	28 16N	094 51W	0008	01 58 - 12 50	STAR	SA	714432
GALVESTON	SCHOLTES FIELD WARS	TX	12923	72242	28 16N	094 51W	0008	01 58 - 12 52	STAR	A	714356
HOUSTON	ELLINGTON AFB	TX	12905		29 37N	095 10W	0012	01 58 - 12 70	STAR	MA	750955.3
HOUSTON	ELLINGTON AFB	TX	12905		29 37N	095 10W	0012	01 59 - 12 59	STAR	SA	712243
HOUSTON	HOBBY IML APT WARS	TX	12818	72243	29 38N	095 17W	0018	01 54 - 12 68	STAR	SA	713874
HOUSTON	HOBBY IML APT WARS	TX	12818	72243	29 38N	095 17W	0018	01 55 - 12 87	STAR	SA	715425
HOUSTON	INTERNATIONAL APT WARS	TX	12960	72243	29 58N	095 22W	0033	08 59 - 12 71	STAR	MA	714181
HOUSTON	INTERNATIONAL APT WARS	TX	12960	72243	29 58N	095 22W	0033	08 59 - 07 72	STAR	A	714660
HOUSTON	INTERNATIONAL APT WARS	TX	12960	72243	29 58N	095 22W	0033	08 59 - 12 71	STAR	SA	713813
HOUSTON	INTERNATIONAL APT WARS	TX	12960	72243	29 58N	095 22W	0033	09 71 - 12 73	STAR	ITM	750174
HOUSTON	INTERNATIONAL APT WARS	TX	12960	72243	29 58N	095 22W	0033	08 72 - 12 72	STAR	A	701772
HOUSTON	INTERNATIONAL APT WARS	TX	12960	72243	29 58N	095 22W	0033	08 72 - 07 73	STAR	A	714660
LAREDO	AFB	TX	12907	72252	27 32N	098 28W	0154	04 65 - 08 70	STAR	SA	712761
LUFKIN	ANGELINA COUNTY APT FSS	TX	93987		31 14N	094 45W	0087	01 57 - 12 71	STAR	MA	714443
MIDLAND	MID-ODESSA RGL APL WARS	TX	23023	72265	31 56N	102 12W	0875	01 60 - 12 64	STAR	SA	713931
MIDLAND	MID-ODESSA RGL APL WARS	TX	23023	72265	31 56N	102 12W	0875	01 71 - 12 71	STAR	MA	701772
PORT ARTHUR	JEFFERSON COUNTY APT WARS	TX	12917	72241	28 57N	094 01W	0009	01 57 - 12 71	STAR	SA	701772.141
SAN ANGELO	MATHIS FIELD WARS	TX	23034	72263	31 22N	100 30W	0585	01 50 - 12 54	STAR	SA	713931
SAN ANTONIO	INTERNATIONAL APT WARS	TX	12921	72293	29 22N	098 28W	0243	01 50 - 12 54	STAR	SA	713831
TYLER	POUNDERS FIELD CAR	TX	13872		32 22N	089 24W	0173	01 50 - 12 54	STAR	SA	751272
VICTORIA	FOSTER AFB	TX	12812	72256	28 51N	088 55W	0031	01 55 - 12 74	STAR	SA	752254
WACO	MUNICIPAL APT WARS	TX	13864	72256	31 37N	087 13W	0159	01 58 - 12 73	STAR	MA	751101
BOYCE CANYON	CAR	UT	23158		37 42N	112 09W	2317	01 48 - 12 54	STAR	SA	713029
DELTA	MUNICIPAL APT CAR	UT	23162	72478	38 23N	112 31W	1462	01 50 - 12 54	STAR	SA	712781
HARRISVILLE	CAR	UT	23170	72475	38 25N	110 42W	1360	01 49 - 12 54	STAR	SA	713029
HILFORD	MUNICIPAL APT CAR	UT	23178	72475	38 25N	113 01W	1534	07 47 - 12 51	STAR	MA	751121
OGDEN	HILL AFB	UT	24101	72572	41 07N	111 58W	1490	01 55 - 12 50	STAR	SA	712808
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1296	01 48 - 12 48	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1296	01 48 - 12 48	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1296	01 50 - 12 50	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1296	01 51 - 12 51	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1296	01 52 - 12 52	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1296	01 53 - 12 53	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 54 - 12 54	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 55 - 12 55	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 56 - 12 56	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 57 - 12 57	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 58 - 12 58	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 59 - 12 58	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 50 - 12 50	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 51 - 12 51	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 52 - 12 52	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 53 - 12 63	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 54 - 12 54	STAR	A	713858
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 56 - 12 70	STAR	SA	712745
SALT LAKE CITY	INTERNATIONAL APT WARS	UT	24127	72572	40 46N	111 58W	1287	01 70 - 12 72	STAR	SA	701772
SURLINGTON	INTERNATIONAL APT WARS	VT	14742	72617	44 28N	073 09W	0106	01 55 - 12 68	STAR	MA	712179
SURLINGTON	INTERNATIONAL APT WARS	VT	14742	72617	44 28N	073 09W	0104	01 70 - 12 74	STAR	SA	752031.3
SURLINGTON	INTERNATIONAL APT WARS	VT	14742	72617	44 28N	073 09W	0104	01 70 - 12 74	STAR	SA	713370
DANVILLE	MUNICIPAL APT CAR	VA	13728		38 14N	079 20W	0180	01 50 - 12 54	STAR	MA	750970
GREENSBORO	CAR	VA	13732		38 04N	078 09W	0135	01 56 - 12 50	STAR	MA	750970
LYNCHBURG	MUNICIPAL APT WARS	VA	13733	72410	37 20N	079 12W	0296	01 59 - 12 73	STAR	SA	750447
NORFOLK	REGIONAL APT WARS	VA	13737	72308	36 54N	076 12W	0013	01 55 - 12 54	STAR	SA	714000
NORFOLK	REGIONAL APT WARS	VA	13737	72308	36 54N	076 12W	0013	01 73 - 12 73	STAR	SA	711703
NORFOLK	NAS	VA	13750		36 57N	076 17W	0016	12 56 - 12 71	STAR	SA	713590
PULASKI	NEW RIVER APT CAR	VA	13866		37 55N	080 47W	0688	01 50 - 12 54	STAR	SA	751955
QUANTICO	NAS	VA	13773		38 30N	077 18W	0004	01 55 - 12 60	STAR	MA	714427
QUANTICO	NAS	VA	13773		38 30N	077 18W	0004	08 72 - 05 73	STAR	MA	713590

CITY	NAME - TYPE	ST	LEGN	WFO	LAT	LONG	ELEV	PERIOD OF RECORD	SUMMARY TYPE	SUM FREQ	REMARKS
RICHMOND	BYRD FIELD WBAS	VA	13740	72401	37 30N	077 20W	0054	01 54 - 12 70	STAR	SA	750830
RICHMOND	BYRD FIELD WBAS	VA	13740	72401	37 30N	077 20W	0055	01 71 - 12 71	STAR	MA	701772
RICHMOND	BYRD FIELD WBAS	VA	13740	72401	37 30N	077 20W	0055	01 72 - 12 72	STAR	MA	714226
RICHMOND	BYRD FIELD WBAS	VA	13740	72401	37 30N	077 20W	0055	01 74 - 12 74	STAR	A	752083.3
ROANOKE	WOODRUM FIELD WBAS	VA	13741	72411	37 19N	078 58W	0364	01 68 - 12 72	STAR	MA	714656
WALLOPS ISLAND	WAS	VA	33739	72402	37 51N	075 28W	0004	01 57 - 12 72	STAR	MA	714630
WALLOPS ISLAND	WAS	VA	33739	72402	37 51N	075 28W	0004	01 58 - 12 73	STAR	MA	750405.3
BELLINGHAM	MUNICIPAL APT CAR	WA	24217		46 48N	122 32W	0047	01 48 - 12 58	STAR	MA	750851
BELLINGHAM	MUNICIPAL APT CAR	WA	24217		46 48N	122 32W	0048	01 56 - 12 58	STAR	MA	714112
ELLENSBURG	CAR	WA	24218		45 37N	121 09W	0072	01 54 - 12 54	STAR	SA	752008
EVERETT	MUNICIPAL APT CAR	WA	24220		47 02N	120 31W	0227	01 50 - 12 54	STAR	A	714578
EVERETT	DRINE FIELD AFB	WA	24141		47 18N	119 32W	0387	01 50 - 12 54	STAR	A	714578
HOQUIAM	EDWEMAN APT CAR	WA	24203		47 54N	122 17W	0382	01 53 - 12 57	STAR	A	714578
HOQUIAM	LARSON AFB	WA	24125		46 58N	123 56W	0008	01 54 - 12 58	STAR	A	714578
HOQUIAM	WAS	WA	24110		47 11N	119 30W	0381	01 51 - 12 55	STAR	A	714578
PORT ANGELES	WAS	WA	24227	72702	46 58N	122 54W	0066	01 50 - 12 54	STAR	A	714578
SEATTLE	SEA-TAC INTL APT WBAS	WA	24228	74201	46 08N	122 24W	0005	01 48 - 12 53	STAR	MA	714411
SEATTLE	SEA-TAC INTL APT WBAS	WA	24233	72703	47 27N	122 18W	0137	01 48 - 12 53	STAR	MA	714411
SEATTLE	BOEING FIELD WBAS	WA	24233	72703	47 27N	122 18W	0137	01 57 - 12 71	STAR	MA	711170
SPOKANE	GEIGER FIELD INTL APT WBAS	WA	24234		47 32N	122 18W	0010	01 50 - 12 64	STAR	SA	714578
TACOMA	MCCORD AFB	WA	24157	72785	47 38N	117 32W	0721	01 57 - 12 70	STAR	SA	713385
TOLEDO	WILCOX APT CAR	WA	24267	74206	46 28N	122 28W	0088	01 50 - 12 54	STAR	A	714578
WALLA WALLA	CITY-COUNTY APT CAR	WA	24241		46 21N	118 17W	0383	01 50 - 12 54	STAR	A	714578
WIDDEY ISLAND	WAS	WA	24160		46 21N	122 40W	0010	01 57 - 12 71	STAR	MA	714578
YAKIMA	MUNICIPAL APT WBAS	WA	24240	72781	46 34N	120 32W	0324	01 50 - 12 54	STAR	A	714578
CHARLESTON	KANAWHA APT WBAS	WV	13888	72414	38 22N	081 35W	0301	01 58 - 12 73	STAR	MA	750556.3
HUNTINGTON	TRI-STATE APT WBAS	WV	03860	72425	38 22N	082 33W	0258	01 70 - 12 74	STAR	SA	715675.3
HUNTINGTON	TRI-STATE APT WBAS	WV	03860	72425	38 22N	082 33W	0258	01 75 - 12 75	STAR	SA	752400.3
HUNTINGTON	TRI-STATE APT WBAS	WV	03860	72425	38 22N	082 33W	0258	01 50 - 12 54	STAR	MA	750833
HUNTINGTON	TRI-STATE APT WBAS	WV	03860	72425	38 22N	082 33W	0258	01 50 - 12 54	STAR	MA	750866
MARTINSBURG	MUNICIPAL APT CAR	WV	93818	72425	38 25N	082 30W	0179	01 50 - 12 54	STAR	SA	713898
HOBBSBORO	MUNICIPAL APT CAR	WV	13734		38 24N	077 58W	0186	01 50 - 12 54	STAR	MA	750833
ROCKWELL	MUNICIPAL APT CAR	WV	13736		38 38N	079 55W	0380	01 50 - 12 54	STAR	MA	750866
ROCKWELL	WAS	WV	13887		38 18N	081 34W	0205	01 50 - 12 54	STAR	SA	713824
EAU CLAIRE	MUNICIPAL APT FSS	WI	14881		44 52N	081 28W	0273	01 58 - 12 73	STAR	SA	750848
GREEN BAY	AUSTIN STRAUDEL APT WBAS	WI	14888	72645	44 28N	088 08W	0212	01 54 - 12 73	STAR	SA	715137
GREEN BAY	AUSTIN STRAUDEL APT WBAS	WI	14888	72645	44 28N	088 08W	0212	01 57 - 12 71	STAR	SA	714008
GREEN BAY	AUSTIN STRAUDEL APT WBAS	WI	14888	72645	44 28N	088 08W	0212	01 54 - 12 73	STAR	SA	750848
LA CROSSE	MUNICIPAL APT WBAS	WI	14888	72645	44 28N	088 08W	0212	01 73 - 12 73	STAR	SA	715137
LA CROSSE	MUNICIPAL APT WBAS	WI	14820	72643	43 52N	091 15W	0201	01 57 - 12 73	STAR	SA	701772
MADISON	TRUAX FIELD WBAS	WI	14820	72643	43 52N	091 15W	0201	01 57 - 12 73	STAR	SA	714006
MADISON	TRUAX FIELD WBAS	WI	14837	72641	43 08N	089 20W	0265	01 54 - 12 73	STAR	SA	715137
MADISON	TRUAX FIELD WBAS	WI	14837	72641	43 08N	089 20W	0265	01 57 - 12 71	STAR	SA	713398
MADISON	TRUAX FIELD WBAS	WI	14837	72641	43 08N	089 20W	0265	01 71 - 12 71	STAR	SA	701772
MILWAUKEE	MITCHELL FIELD WBAS	WI	14839	72640	42 57N	087 54W	0215	01 50 - 12 73	STAR	SA	715137
MILWAUKEE	MITCHELL FIELD WBAS	WI	14839	72640	42 57N	087 54W	0215	01 50 - 12 54	STAR	MA	750250
MILWAUKEE	MITCHELL FIELD WBAS	WI	14839	72640	42 57N	087 54W	0215	01 54 - 12 64	STAR	SA	750685
MILWAUKEE	MITCHELL FIELD WBAS	WI	14839	72640	42 57N	087 54W	0215	01 54 - 12 73	STAR	SA	715137
MILWAUKEE	MITCHELL FIELD WBAS	WI	14839	72640	42 57N	087 54W	0215	01 56 - 12 70	STAR	SA	713174
MILWAUKEE	MITCHELL FIELD WBAS	WI	14839	72640	42 57N	087 54W	0211	01 57 - 12 71	STAR	SA	714006
MILWAUKEE	MITCHELL FIELD WBAS	WI	14839	72640	42 57N	087 54W	0211	01 58 - 12 72	STAR	MA	714482
MILWAUKEE	MITCHELL FIELD WBAS	WI	14839	72640	42 57N	087 54W	0209	01 70 - 07 70	STAR	A	711873
MILWAUKEE	MITCHELL FIELD WBAS	WI	14839	72640	42 57N	087 54W	0205	07 73 - 12 73	STAR	SA	715137
MILWAUKEE	MITCHELL FIELD WBAS	WI	14839	72640	42 57N	087 54W	0205	07 73 - 06 74	STAR	SA	750873
MILWAUKEE	MITCHELL FIELD WBAS	WI	14839	72640	42 57N	087 54W	0205	01 74 - 12 74	STAR	A	752042
MILWAUKEE	L J TIMPHEMAN APT CAR	WI	94888		43 07N	088 02W	0227	01 58 - 12 72	STAR	MA	714537
CASPER	AIR TERMINAL WBAS	WY	24088	72568	42 55N	108 28W	1622	01 66 - 12 75	STAR	SA	752227.3
CASPER	AIR TERMINAL WBAS	WY	24088	72568	42 55N	108 28W	1622	01 57 - 12 71	STAR	MA	714235
CHEYENNE	MUNICIPAL APT WBAS	WY	24018	72564	41 08N	104 49W	1871	01 50 - 12 54	STAR	MA	750663.3
CHEYENNE	MUNICIPAL APT WBAS	WY	24018	72564	41 08N	104 49W	1871	01 57 - 12 71	STAR	MA	750313
CHEYENNE	MUNICIPAL APT WBAS	WY	24018	72564	41 08N	104 49W	1871	01 67 - 12 71	STAR	MA	750663.3
CHEYENNE	MUNICIPAL APT WBAS	WY	24018	72564	41 08N	104 49W	1871	01 74 - 12 74	STAR	MA	714318
LANDER	HUNT APT WBAS	WY	24021	72576	42 40N	108 44W	1588	01 70 - 12 74	STAR	A	751847.3
ROCK SPRINGS	MUNICIPAL APT WBAS	WY	24028	72563	41 18N	104 57W	1305	01 50 - 07 52	STAR	MA	751818.3
ROCK SPRINGS	MUNICIPAL APT WBAS	WY	24027	72574	41 38N	108 04W	2056	01 60 - 12 54	STAR	SA	714283
ROCK SPRINGS	MUNICIPAL APT WBAS	WY	24027	72574	41 38N	108 04W	2056	01 67 - 12 71	STAR	SA	701772
SHERIDAN	SHERIDAN CAP WBAS	WY	24028	72666	41 48N	105 58W	1202	01 49 - 12 53	STAR	SA	752211.3
SHERIDAN	SHERIDAN CAP WBAS	WY	24028	72666	41 48N	105 58W	1202	01 49 - 12 53	STAR	SA	714135

TECHNICAL REPORT DATA
(Please read Instructions on the reverse before completing)

1. REPORT NO. EPA-450/4-87-009			2.			3. RECIPIENT'S ACCESSION NO.					
4. TITLE AND SUBTITLE NETWORK DESIGN AND OPTIMUM SITE EXPOSURE CRITERIA FOR PARTICULATE MATTER						5. REPORT DATE May 1987					
						6. PERFORMING ORGANIZATION CODE 81-01-044-1					
7. AUTHOR(S) R. C. Koch and H. E. Rector						8. PERFORMING ORGANIZATION REPORT NO. GEOMET Report No. ESF-1185					
9. PERFORMING ORGANIZATION NAME AND ADDRESS GEOMET Technologies, Inc. 1801 Research Boulevard Rockville, Maryland 20858						10. PROGRAM ELEMENT NO.					
						11. CONTRACT/GRANT NO. 68-02-3584					
12. SPONSORING AGENCY NAME AND ADDRESS U.S. Environmental Protection Agency Research Triangle Park, North Carolina 27711						13. TYPE OF REPORT AND PERIOD COVERED Final					
						14. SPONSORING AGENCY CODE					
15. SUPPLEMENTARY NOTES											
16. ABSTRACT This report presents procedures and criteria for selecting appropriate locations for particulate matter (PM ₁₀) monitoring stations. Background on sources of particulate matter, monitoring objectives, spatial relationships and various meteorological considerations used in site selection are provided.											
17. KEY WORDS AND DOCUMENT ANALYSIS											
a. DESCRIPTORS			b. IDENTIFIERS/OPEN ENDED TERMS			c. COSATI Field/Group					
particulate matter site exposure criteria site selection monitoring objectives air pollution											
18. DISTRIBUTION STATEMENT RELEASE TO PUBLIC						19. SECURITY CLASS (This Report) UNCLASSIFIED			21. NO. OF PAGES 132		
						20. SECURITY CLASS (This page) UNCLASSIFIED			22. PRICE		