

Department of the Interior  
U.S. Geological Survey

**LANDSAT DATA CONTINUITY MISSION (LDCM)  
LEVEL 1 (L1)  
DATA FORMAT CONTROL BOOK (DFCB)**

**Version 6.0**

**August 2012**



**LANDSAT DATA CONTINUITY MISSION (LDCM)  
LEVEL 1 (L1)  
DATA FORMAT CONTROL BOOK (DFCB)**

**August 2012**

EROS  
Sioux Falls, South Dakota

## Document History

---

Document Number	Document Version	Publication Date	Change Number
LDCM-DFCB-004	Version 1.0	February 2010	CCR# 118
LDCM-DFCB-004	Version 1.1	April 2010	CCR# 214
LDCM-DFCB-004	Version 2.0	April 2011	CCR# 370
LDCM-DFCB-004	Version 3.0	September 2011	DCR# 527
LDCM-DFCB-004	Version 4.0	February 2012	DCR #718
LDCM-DFCB-004	Version 5.0	May2012	DCR #850
LDCM-DFCB-004	Version 6.0	August 2012	DCR #1016

# Contents

---

<b>Document History .....</b>	<b>iii</b>
<b>Contents.....</b>	<b>iv</b>
<b>List of Tables .....</b>	<b>v</b>
<b>Section 1 Introduction.....</b>	<b>1</b>
1.1 Background.....	1
1.2 Purpose and Scope .....	1
1.3 Configuration Management.....	1
1.4 DFCB Overview .....	2
1.5 L1Gt / L1T Output Files Overview .....	2
1.5.1 Final Product Packaging .....	3
1.5.2 Naming Convention .....	4
1.5.3 Example File Names.....	5
<b>Section 2 Data Format Definition .....</b>	<b>6</b>
2.1 GeoTIFF.....	6
2.1.1 L1Gt / L1T Image File .....	6
2.1.2 Quality Band (QB) File .....	8
2.1.3 Checksum File .....	9
2.1.4 L1G Metadata File .....	9
<b>References.....</b>	<b>21</b>

## List of Tables

---

Table 1-1. Band Reference Table .....	3
Table 1-2. File Components .....	3
Table 1-3. File Naming Convention .....	4
Table 1-4. Compressed Product File Naming Convention .....	4
Table 2-1. GeoTIFF Keys Used to Define UTM Projection.....	7
Table 2-2. GeoTIFF Keys Used to Define Polar Stereographic Projection.....	8
Table 2-3. QBBit Description.....	9
Table 2-4. L1Gt / L1T Metadata File.....	20

## Section 1 Introduction

---

The Landsat Data Continuity Mission (LDCM) is a joint mission formulated by the National Aeronautics and Space Administration (NASA) and the U.S. Geological Survey (USGS). LDCM is a remote sensing satellite mission providing coverage of the Earth's land surfaces. This Mission continues the 30-plus years of global data collection and distribution provided by the Landsat series of satellites.

### 1.1 Background

LDCM is a component of the Landsat Program conducted jointly by NASA and the USGS. The goal of LDCM is to continue to collect, archive, and distribute multispectral imagery that affords global, synoptic, and repetitive coverage of the Earth's land surfaces at a scale where natural and human-induced changes can be detected, differentiated, characterized, and monitored over time. This LDCM goal keeps with the Landsat programmatic goals stated in the United States Code (USC) Title 15, Chapter 82 "Land Remote Sensing Policy" (derived from the Land Remote Sensing Policy Act of 1992). This policy requires that the Landsat Program provide data into the future that are sufficiently consistent with previous Landsat data to allow the detection and quantitative characterization of changes in or on the land surface of the globe. The LDCM was conceived as a follow-on mission to the highly successful Landsat series of missions that have provided satellite coverage of the Earth's continental surfaces since 1972. The data from these missions constitute the longest continuous record of the Earth's surface as seen from space.

The LDCM is intended to ensure that Landsat-like data will be provided to the USGS National Satellite Land Remote Sensing Data Archive (NSLRSDA) for at least five years.

### 1.2 Purpose and Scope

This document establishes the data format for the LDCM Level 1 product. It defines the content and layout for the product, which consists of one of the following:

- The Level 1 Systematic Terrain Corrected (L1Gt) product created using Digital Elevation Models (DEMs) and ephemeris.
- The Level 1 Terrain (Corrected) (L1T) precision corrected product created using ground control points, DEMs, and ephemeris.

### 1.3 Configuration Management

This Data Format Control Book (DFCB) is under LDCM configuration control. Any proposed change to this document requires LDCM Configuration Control Board (CCB) approval according to LDCM-POL-002 Landsat Data Continuity Mission (LDCM) Development Configuration Control Board (CCB) Process Document (see References).

## 1.4 DFCB Overview

This document contains detailed information about the LDCM L1Gt / L1T output data file format and packaging. The output files defined in this DFCB are based on the previously established Geographical Tagged Image File Format (GeoTIFF).

This document does not guarantee the availability or accessibility of products, nor does it imply who may receive each product type. See the U.S. Geological Survey's Product Distribution Policy for more information.

The following product-type definitions provide an understanding of the nomenclature used in this document and a reference for the relationships between product types:

- Level 0 (L0) Data Product – L0 data products are image data with all data transmission and formatting artifacts removed. These products are time provided, spatial, and band-sequentially ordered multispectral digital image data. See LDCM-DFCB-002 Landsat Data Continuity Mission (LDCM) Level 0 Reformatted (L0R) Data Format Control Book (DFCB) for more information.
- Level 1 Radiometric (L1R) – L1R data products consist of radiometrically corrected image data derived from L0 data scaled to at-aperture spectral radiance or reflectance. The L1R is not defined in this DFCB.
- Level 1 Systematic (L1G) – L1G data products consist of L1R data products with systematic geometric corrections applied and resampled for registration to a cartographic projection, referenced to the World Geodetic System 1984 (WGS84), G873, or current version.
- Level 1 Gt (L1Gt) – L1Gt data products consist of L1R data products with systematic geometric and terrain corrections applied and resampled for registration to a cartographic projection, referenced to the WGS84, G873, or current version. L1Gt data products assume the use of onboard positional information or definitive ephemeris, as well as the use of controlled elevation data to correct for parallax errors.
- Level 1 Terrain (L1T) – L1T data products consist of L1R data products with systematic geometric corrections applied, using Ground Control Points (GCPs) or onboard positional information to resample the image data for registration to a cartographic projection, referenced to the WGS84, G873, or current version. The data are also terrain corrected for relief displacement.

## 1.5 L1Gt / L1T Output Files Overview

Standard L1T products, which are Digital Number (DN) products in 16-bit integer format, can be converted to Top of Atmosphere (TOA) reflectance (Bands 1–9) or radiance (Bands 1–11) using scaling factors provided in the product metadata. Refer to LDCM-ADEF-001 Landsat Data Continuity Mission (LDCM) Calibration and Validation (Cal/Val) Algorithm Description Document (ADD) for a description of the radiance and reflectance calculations, and rescaling procedures used during processing. Refer to LDCM-DFCB-005 Landsat Data Continuity Mission (LDCM) Calibration Parameter File (CPF) Data Format Control Book (DFCB) for definitions of the reflectance conversion and the rescaling values used to process the Level 1 products. The Calibration Parameter File

(CPF) used to process a specific scene can be accessed through the LDCM Project Web site (<http://landsat.usgs.gov/>).

The L1Gt / L1T image data are radiometrically and geometrically corrected and are available in GeoTIFF. Table 1-1 shows the band identification, while Table 1-2 lists the L1Gt / LT product components.

<b>Band Reference Number</b>	<b>Band Description</b>	<b>Band Center (nm)</b>
1	Coastal Aerosol (Operational Land Imager (OLI))	433
2	Blue (OLI)	482
3	Green (OLI)	562
4	Red (OLI)	655
5	Near-Infrared (NIR) (OLI)	865
6	Short Wavelength Infrared (SWIR) 1 (OLI)	1610
7	SWIR 2 (OLI)	2200
8	Panchromatic (OLI)	590
9	Cirrus (OLI)	1375
10	Thermal Infrared Sensor (TIRS) 1	10800
11	TIRS 2	12000

**Table 1-1. Band Reference Table**

<b>L1G Product Components</b>
L1Gt / L1T image file (one for each band)
Quality Band (QB) file
Checksum file
L1Gt / L1T metadata file

**Table 1-2. File Components**

### 1.5.1 Final Product Packaging

The final output product is a tar.gz file. The files are written to a tar file format and then compressed with the gzip application. The tar file does not contain any subdirectory information. Therefore, uncompressing (untarring) the file dumps all of the files directly into the current directory.



## 1.5.2 Naming Convention

Table 1-3 and Table 1-4 contain the file names associated with the Level 1 products.

Ls8pprrrYYYYDDDGGGVV\_FT.ext

Identifier	Description
L	Landsat
s	Sensor of: O = OLI, T = TIRS, C = Combined TIRS and OLI Indicates which sensor collected data for this product
8	Landsat mission number
ppp	Satellite orbit location in reference to the Worldwide Reference System-2 (WRS-2) path of the product
rrr	Satellite orbit location in reference to the WRS-2 row of the product
YYYY	Acquisition year of the image
DDD	Acquisition day of year
GGG	Ground station ID
VV	Version
_FT	File type, where FT equals one of the following: image band file number (B1–B11), MTL (metadata file), BQA (quality band file), MD5 (checksum file)
.ext	File extension, where .TIF equals GeoTIFF file extension, and .txt equals text extension

**Table 1-3. File Naming Convention**

Ls8pprrrYYYYDDDGGGVV.FT.ext

Identifier	Description
L	Landsat
s	Sensor of: O = OLI, T = TIRS, C = Combined TIRS and OLI Indicates which sensor collected data for this product
8	Landsat mission number
ppp	Satellite orbit location in reference to the WRS-2 path of the product
rrr	Satellite orbit location in reference to the WRS-2 row of the product
YYYY	Acquisition year of the image
DDD	Acquisition day of year
GGG	Ground station ID
VV	Version
.FT	File type, where FT equals tar (tarred file)
.ext	File extension, where .gz equals zipped (compressed) extension

**Table 1-4. Compressed Product File Naming Convention**

### **1.5.3 Example File Names**

#### **1.5.3.1 Image Files**

LC82220052014265LGN00\_B1.TIF  
LC82220052014265LGN00\_B2.TIF  
LC82220052014265LGN00\_B3.TIF  
LC82220052014265LGN00\_B4.TIF  
LC82220052014265LGN00\_B5.TIF  
LC82220052014265LGN00\_B6.TIF  
LC82220052014265LGN00\_B7.TIF  
LC82220052014265LGN00\_B8.TIF  
LC82220052014265LGN00\_B9.TIF  
LC82220052014265LGN00\_B10.TIF  
LC82220052014265LGN00\_B11.TIF

#### **1.5.3.2 Quality Band**

LC82220052014265LGN00\_BQA.TIF

#### **1.5.3.3 Metadata**

LC82220052014265LGN00\_MTL.txt

#### **1.5.3.4 Compressed**

LC82220052014265LGN00.tar.gz

#### **1.5.3.5 Checksum**

LC82220052014265LGN00\_MD5.txt

## Section 2 Data Format Definition

---

This section describes the storage format for the data.

### 2.1 GeoTIFF

GeoTIFF defines a set of Tagged Image File Format (TIFF) tags, which describe cartographic and geodetic information associated with geographic TIFF imagery. GeoTIFF is a means for tying a raster image to a known model space or map projection and for describing those projections. A metadata format provides geographic information to associate with the image data. However, the TIFF file structure allows both the metadata and the image data to encode into the same file.

#### 2.1.1 L1Gt / L1T Image File

The description of an image in GeoTIFF requires tags and keys; the image files contain these tags and keys, which are read by GeoTIFF readers.

Each image band in the L1G product is in a separate file. Each band comprises a grayscale GeoTIFF file, which is in uncompressed 16-bit unsigned integers.

##### 2.1.1.1 GeoTIFF Tags

GeoTIFF tags convey information about the image. The tags describe the image using information the GeoTIFF reader needs to control the appearance of the image on the user's screen. The TIFF tags are embedded in the same file as the TIFF image. The GeoTIFF tags provide information on the image projection and corner points, which define the geographic location and extent of the image.

A complete description of the raster data requires geo-referencing of the data, which is accomplished using tags. The Level 1 production system uses the transformation raster, model space tie points, and scaling parameters. ModelTiepointTag and ModelPixelScaleTag are used for this purpose.

##### 2.1.1.1.1 GeoTIFF ModelTiepointTag

The GeoTIFF ModelTiepointTag stores the raster-to-model tiepoint pairs.

###### 2.1.1.1.1.1 Description

The raster-to-model tiepoint pairs are stored in the following order: ModelTiepointTag = (... , I, J, K, X, Y, Z...), where (I, J, K) is the point at location (I, J) in raster space with pixel-value K, and (X, Y, Z) is a vector in model space. The ModelTiepointTag requires that K and Z are set to zero. See the GeoTIFF Specification document (see References) for more information.

The raster image is geo-referenced by specifying its location, size, and orientation in the model coordinate space. Because the relationship between the raster space and the model space often are exact, the affine transformation relationship can be defined using

one set of tiepoints and the ModelPixelScaleTag, which gives the vertical and horizontal raster grid cell size.

**2.1.1.1.1.2 Parameters**

Tag = 33922  
 Type = DOUBLE  
 N = 6\*K, K = number of tiepoints

**2.1.1.1.2 GeoTIFF ModelPixelScaleTag Tag**

The GeoTIFF ModelPixelScaleTag tag specifies the size of the raster pixel spacing in the model space units when the raster space is embedded in the model space coordinate system without rotation.

**2.1.1.1.2.1 Description**

The size of raster pixel spacing in the model space units consists of three values. These values are ModelPixelScaleTag = (ScaleX, ScaleY, ScaleZ), where ScaleX and ScaleY give the horizontal and vertical spacing of raster pixels, and ScaleZ maps the pixel value of a DEM into the correct Z-scale.

A single tiepoint in the ModelTiepointTag, together with the ModelPixelScaleTag, determines the relationship between raster and model space.

**2.1.1.1.2.2 Parameters**

Tag = 33550  
 Type = DOUBLE  
 N = 3

**2.1.1.2 GeoTIFF Keys**

In addition to tags, the description of a projection in GeoTIFF requires the use of keys. Table 2-1 lists the keys necessary to define the projections supported by the L1G production systems, along with their possible values.

Valid Keys	Possible Values	Meaning
GTMModelTypeGeoKey	1	ModelTypeProjected (Projection Coordinate System)
GTRasterTypeGeoKey	2	RasterPixelPoint (the coordinate is at the center of the pixel)
GTCitationGeoKey	(ASCII, 17)	American Standard Code for Information Interchange (ASCII) reference to public documentation
GeogLinearUnitsGeoKey	9001	Linear_Meter
GeogAngularUnitsGeoKey	9102	Angular_Degree
ProjectedCSTypeGeoKey	20000–32760	European Petroleum Survey Group (EPSG) Projection System Codes
	32767	User-defined

**Table 2-1. GeoTIFF Keys Used to Define UTM Projection**

Valid Keys	Possible Values	Meaning
ProjCoordTransGeoKey	15	CT_PolarStereographic
GTModelTypeGeoKey	1	ModelTypeProjected (Projection Coordinate System)
GTRasterTypeGeoKey	2	RasterPixellsPoint (the coordinate is at the center of the pixel)
GTCitationGeoKey	(ASCII, 17)	ASCII reference to public documentation
GeographicTypeGeoKey	4326	GCS_WGS_84
GeogLinearUnitsGeoKey	9001	Linear_Meter
GeogAngularUnitsGeoKey	9102	Angular_Degree
ProjectedCSTypeGeoKey	20000–32760	EPSG Projection System Codes (see the EPSG Geodetic Parameter Registry for values)
	32767	User-defined
ProjectionGeoKey	10000–19999	EPSG / Petrotechnical Open Software Corporation (POSC) Projection Codes (see the EPSG Geodetic Parameter Registry for values)
	32767	User-defined
ProjLinearUnitsGeoKey	9001	Linear_Meter
ProjStraightVertPoleLongGeoKey	0.0000000	Value in units of GeogAngularUnits
ProjNatOriginLatGeoKey	-71.0000000	Value in units of GeogAngularUnits
ProjFalseNorthingGeoKey	0.0000000	Value entered in units of ProjLinearUnits
ProjFalseEastingGeoKey	0.0000000	Value entered in units of ProjLinearUnits

**Table 2-2. GeoTIFF Keys Used to Define Polar Stereographic Projection**

### 2.1.2 Quality Band (QB) File

The QB file contains quality statistics gathered from the image data and cloud mask information for the scene. The QB file is a 16-bit image with the same dimensions as the L1Gt or L1T scene. Bits are allocated for some artifacts that are distinguishable at the L1G stage of processing. Bit 0 is the least significant. Several land surface classification types exist and a range of confidence levels are provided for each classification type.

The two-bit confidence levels are as follows:

- 00 No confidence level set (used for fill or for a class not reported)
- 01 Low confidence
- 10 Mid confidence
- 11 High confidence

A QB value of 1 (00 01 hex) is reserved for fill data. When processing a non-fill pixel, reaching this QB value should not be possible. High-confidence clouds (values 11 in bits 14 and 15) should have a value of C000 hex, or 49152.

Bit	Flag Description	Values
0	Designated Fill	0 for image data 1 for fill data
1	Dropped Frame (Reserved)	0 for image data 1 for dropped frame
2	Terrain Occlusion	0 for normal data 1 for terrain occlusion
3	Reserved	Reserved for a future 1-bit class artifact designation
4–5	Water confidence	00 = None or Unset 01 = 0–35% confidence the pixel is water 10 = 36–64% confidence the pixel is water 11 = 65–100% confidence the pixel is water
6–7	Reserved	Reserved for a future 2-bit class artifact designation
8–9	Vegetation confidence (Reserved)	Same as water confidence
10–11	Snow/Ice confidence	Same as water confidence
12–13	Cirrus confidence	Same as water confidence
14–15	Cloud confidence	Same as water confidence

**Table 2-3. QBBit Description**

### 2.1.3 Checksum File

A checksum file is created for every product. A checksum file is generated on the final .tar.gz file. The checksum file contains a listing of Message-Digital Algorithm 5 (MD5) checksums for all files, except for itself. The file is in plain text format and contains the system's md5sum output. For example, a collection with a scene ID of LC82220052014265LGN00 has a checksum file named LC82220052014265LGN00\_MD5.txt.

### 2.1.4 L1G Metadata File

The L1G metadata file is created during product generation and contains information specific to the product ordered. Table 2-4 lists the full contents of the L1G metadata file. The metadata file is text in the Object Description Language (ODL) format.

Parameter Name	Value, Format, and Range	Parameter Description / Remarks
GROUP	= L1_METADATA_FILE	The beginning of the first-level ODL group. It indicates the start of the L1G metadata file level group.
GROUP	= METADATA_FILE_INFO	The beginning of the metadata file information group.
ORIGIN	= "Image courtesy of the U.S. Geological Survey"	Origin of the product.
REQUEST_ID	= "NNNNNNNNNNNNNN_UUUUU"	Product Request Id. NNNNNNNNNNNNNN_UUUUU, where NNNNNNNNNNNNNN = 13-digit TRAM order number and UUUUU = 5-digit TRAM unit number.
LANDSAT_SCENE_ID	= "Ls8pprrrYYYYDDGGVV"	The unique Landsat scene identifier.
FILE_DATE	= YYYY-MM-DDTHH:MM:SSZ	The date when the metadata file for the L1G product set was created. The date is based on Universal Time Coordinated (UTC) (also known as Greenwich Mean Time (GMT)).
STATION_ID	= "XXX"	The ground station that received the data. See LS-IC-04 Landsat Ground Station (GS) Identifiers for all possible station IDs (e.g., "LGN" = Landsat Ground Network) (see References).
PROCESSING_SOFTWARE_VERSION	= "IAS_X.Y.Z" = "LPGS_X.Y.Z"	The processing software version that created the product. The version consists of a subsystem name followed by an underscore then the software version, where X is the major release number, Y is the minor release number, and Z is the patch (or engineering) release number. X, Y, and Z are all numeric values.
END_GROUP	= METADATA_FILE_INFO	The end of the metadata information group.
GROUP	= PRODUCT_METADATA	The beginning of the product metadata group.
DATA_TYPE	= "L1T" = "L1GT"	The identifier to inform the user of the product type.
ELEVATION_SOURCE	= "N" = "GLS2000" = "RAMP" = "GTOPO30"	Indicates the source (if any) of the DEM used in the correction process. N indicates no corrections applied.
OUTPUT_FORMAT	= "GEOTIFF"	The output format of the image.
SPACECRAFT_ID	= "LANDSAT_8"	Spacecraft from which the data were captured.
SENSOR_ID	= "OLI_TIRS" = "OLI" = "TIRS"	Sensor(s) used to capture this scene.
WRS_PATH	= 1-251	Orbital WRS-2 defined nominal Landsat satellite track (path)
WRS_ROW	= 1-248	Orbital WRS-2 defined nominal Landsat row number for this scene.
NADIR_OFFNADIR	= "NADIR" = "OFFNADIR"	Nadir or Off-Nadir condition of the scene.
TARGET_WRS_PATH	= 1-233	Nearest WRS-2 path to the line-of-sight scene center of the image.
TARGET_WRS_ROW	= 1-248, 880-889, 990-999	Nearest WRS-2 row to the line-of-sight scene center of the image. Rows 880-889 and 990-999 are reserved for the polar regions where it is undefined in the WRS-2.
DATE_ACQUIRED	= YYYY-MM-DD	The date the image was acquired.

Parameter Name	Value, Format, and Range	Parameter Description / Remarks
SCENE_CENTER_TIME	= HH:MI:SS.SSSSSSZ	Scene center time of the date the image was acquired. HH = Hour (00-23), MI = Minute, SS.SSSSSS = Fractional seconds, Z = constant (indicates "Zulu" time (same as GMT)).
CORNER_UL_LAT_PRODUCT	= -90.00000 through +90.00000	The latitude value for the upper-left corner of the product, measured at the center of the pixel. Positive (+) value indicates north latitude; negative (-) value indicates south latitude. Units are in degrees.
CORNER_UL_LON_PRODUCT	= -180.00000 through +180.00000	The longitude value for the upper-left corner of the product, measured at the center of the pixel. Positive (+) value indicates east longitude; negative (-) value indicates west longitude. Units are in degrees.
CORNER_UR_LAT_PRODUCT	= -90.00000 through +90.00000	The latitude value for the upper-right corner of the product. Measured at the center of the pixel. Units are in degrees.
CORNER_UR_LON_PRODUCT	= -180.00000 through +180.00000	The longitude value for the upper-right corner of the product, measured at the center of the pixel. Units are in degrees.
CORNER_LL_LAT_PRODUCT	= -90.00000 through +90.00000	The latitude value for the lower-left corner of the product, measured at the center of the pixel. Units are in degrees.
CORNER_LL_LON_PRODUCT	= -180.00000 through +180.00000	The longitude value for the lower-left corner of the product, measured at the center of the pixel. Units are in degrees.
CORNER_LR_LAT_PRODUCT	= -90.00000 through +90.00000	The latitude value for the lower-right corner of the product, measured at the center of the pixel. Units are in degrees.
CORNER_LR_LON_PRODUCT	= -180.00000 through +180.00000	The longitude value for the lower-right corner of the product, measured at the center of the pixel. Units are in degrees.
CORNER_UL_PROJECTION_X_PRODUCT	= -132000000.000 through 132000000.000	The upper-left corner map projection X coordinate, measured at the center of the pixel. Units are in meters.
CORNER_UL_PROJECTION_Y_PRODUCT	= -132000000.000 through 132000000.000	The upper-left corner map projection Y coordinate, measured at the center of the pixel. Units are in meters.
CORNER_UR_PROJECTION_X_PRODUCT	= -132000000.000 through 132000000.000	The upper-right corner map projection X coordinate, measured at the center of the pixel. Units are in meters.
CORNER_UR_PROJECTION_Y_PRODUCT	= -132000000.000 through 132000000.000	The upper-right corner map projection Y coordinate, measured at the center of the pixel. Units are in meters.
CORNER_LL_PROJECTION_X_PRODUCT	= -132000000.000 through 132000000.000	The lower-left corner map projection X coordinate, measured at the center of the pixel. Units are in meters.
CORNER_LL_PROJECTION_Y_PRODUCT	= -132000000.000 through 132000000.000	The lower-left corner map projection Y coordinate, measured at the center of the pixel. Units are in meters.
CORNER_LR_PROJECTION_X_PRODUCT	= -132000000.000 through 132000000.000	The lower-right corner map projection X coordinate, measured at the center of the pixel. Units are in meters.
CORNER_LR_PROJECTION_Y_PRODUCT	= -132000000.000 through 132000000.000	The lower-right corner map projection Y coordinate, measured at the center of the pixel. Units are in meters.
PANCHROMATIC_LINES	= 0-99999	The number of product lines for the panchromatic band (Band 8). This parameter is only present if the panchromatic band is present in the product.



Parameter Name	Value, Format, and Range	Parameter Description / Remarks
PANCHROMATIC_SAMPLES	= 0–99999	The number of product samples for the panchromatic band (Band 8). This parameter is only present if the panchromatic band is in the product.
REFLECTIVE_LINES	= 0–99999	The number of product lines for the reflective bands (Bands 1–7, and Band 9). This parameter is only present if reflective bands are in the product.
REFLECTIVE_SAMPLES	= 0–99999	The number of product samples for the reflective bands (Bands 1–7, and Band 9). This parameter is only present if reflective bands are in the product.
THERMAL_LINES	= 0–99999	The number of product lines for the thermal bands (Bands 10–11). This parameter is only present if thermal bands are in the product.
THERMAL_SAMPLES	= 0–99999	The number of product samples for the thermal bands (Bands 10–11). This parameter is only present if thermal bands are in the product.
FILE_NAME_BAND_1	= “Ls8pprrrYYYYDDDGGGVV_B1.TIF”	The file name for Band 1. This parameter is only present if the band is included in the product.
FILE_NAME_BAND_2	= “Ls8pprrrYYYYDDDGGGVV_B2.TIF”	The file name for Band 2. This parameter is only present if the band is included in the product.
FILE_NAME_BAND_3	= “Ls8pprrrYYYYDDDGGGVV_B3.TIF”	The file name for Band 3. This parameter is only present if the band is included in the product.
FILE_NAME_BAND_4	= “Ls8pprrrYYYYDDDGGGVV_B4.TIF”	The file name for Band 4. This parameter is only present if the band is included in the product.
FILE_NAME_BAND_5	= “Ls8pprrrYYYYDDDGGGVV_B5.TIF”	The file name for Band 5. This parameter is only present if the band is included in the product.
FILE_NAME_BAND_6	= “Ls8pprrrYYYYDDDGGGVV_B6.TIF”	The file name for Band 6. This parameter is only present if the band is included in the product.
FILE_NAME_BAND_7	= “Ls8pprrrYYYYDDDGGGVV_B7.TIF”	The file name for Band 7. This parameter is only present if the band is included in the product.
FILE_NAME_BAND_8	= “Ls8pprrrYYYYDDDGGGVV_B8.TIF”	The file name for Band 8. This parameter is only present if the band is included in the product.
FILE_NAME_BAND_9	= “Ls8pprrrYYYYDDDGGGVV_B9.TIF”	The file name for Band 9. This parameter is only present if the band is included in the product.
FILE_NAME_BAND_10	= “Ls8pprrrYYYYDDDGGGVV_B10.TIF”	The file name for Band 10. This parameter is only present if the band is included in the product.
FILE_NAME_BAND_11	= “Ls8pprrrYYYYDDDGGGVV_B11.TIF”	The file name for Band 11. This parameter is only present if the band is included in the product.
FILE_NAME_BAND_QUALITY	= “Ls8pprrrYYYYDDDGGGVV_BQA.TIF”	The file name for the quality band. This parameter is only present if the band is included in the product.
METADATA_FILE_NAME	= “Ls8pprrrYYYYDDDGGGVV_MTL.txt”	The file name for L1G metadata.
BPF_NAME_OLI	= “LO8BPFYYYY <sub>1</sub> MM <sub>1</sub> DD <sub>1</sub> hh <sub>1</sub> mm <sub>1</sub> ss <sub>1</sub> _YY <sub>2</sub> MM <sub>2</sub> DD <sub>2</sub> hh <sub>2</sub> mm <sub>2</sub> ss <sub>2</sub> .nn”	The file name for the Bias Parameter File (BPF) used to generate the product, if applicable. This only applies to products that contain OLI bands.
BPF_NAME_TIRS	= “LT8BPFYYYY <sub>1</sub> MM <sub>1</sub> DD <sub>1</sub> hh <sub>1</sub> mm <sub>1</sub> ss <sub>1</sub> _YY <sub>2</sub> MM <sub>2</sub> DD <sub>2</sub> hh <sub>2</sub> mm <sub>2</sub> ss <sub>2</sub> .nn”	The file name for the Bias Parameter File (BPF) used to generate the product, if applicable. This only applies to products that contain TIRS bands.

Parameter Name	Value, Format, and Range	Parameter Description / Remarks
CPF_NAME	= "L8CPFyyyy <sub>1</sub> mm <sub>1</sub> dd <sub>1</sub> _yyy <sub>2</sub> mm <sub>2</sub> dd <sub>2</sub> .nn"	The file name for the Calibration Parameter File (CPF) used to generate the product.
RLUT_FILE_NAME	= "L8RLUTyyyymm <sub>1</sub> dd <sub>1</sub> _yyy <sub>2</sub> mm <sub>2</sub> dd <sub>2</sub> Vnn.h5"	The file name for the Response Linearization Lookup Table (RLUT) used to generate the product, if applicable.
END_GROUP	= PRODUCT_METADATA	The end of the product metadata group.
GROUP	= IMAGE_ATTRIBUTES	The beginning of the image attributes group.
CLOUD_COVER	= 0.00–100.00, -1	The overall cloud coverage (percent) of the WRS-2 scene. -1 indicates that the score was not calculated.
IMAGE_QUALITY_OLI	= 0–9	The composite image quality for the OLI bands. Values: 9 = Best. 1 = Worst. 0 = Image quality not calculated. This parameter is only present if OLI bands are present in the product.
IMAGE_QUALITY_TIRS	= 0–9	The composite image quality for the TIRS bands. Values: 9 = Best. 1 = Worst. 0 = Image quality not calculated. This parameter is only present if TIRS bands are present in the product.
ROLL_ANGLE	= -15.00 through +15.00	The amount of spacecraft roll angle at the scene center. The roll value is given in the Yaw Steering Frame (YSF) reference, whose x-axis is aligned with the instantaneous ground track velocity vector. Rolls about this x-axis go by the right-hand rule: a positive roll results in the instruments pointing to the left of the ground track, while a negative roll results in a look to the right.
SUN_AZIMUTH	= -180.00000000 through 180.00000000	The Sun azimuth angle in degrees for the image center location at the image center acquisition time. A positive value indicates angles to the east or clockwise from the north. A negative value (-) indicates angles to the west or counterclockwise from the north.
SUN_ELEVATION	= -90.00000000 through 90.00000000	The Sun elevation angle in degrees for the image center location at the image center acquisition time. A positive value indicates a daytime scene. A negative value (-) indicates a nighttime scene. Note: For reflectance calculation the sun zenith angle is needed, which is 90 - sun elevation angle.
EARTH_SUN_DISTANCE	= N.NNNNNNN	Measurement of the earth to sun distance at the particular day and time of imagery acquisition. Astronomical unit (AU) of measurement.
GROUND_CONTROL_POINTS_MODEL	= 1-999	Number of ground control points used in the precision correction process. This parameter is only present if the DATA_TYPE is L1T.
GEOMETRIC_RMSE_MODEL	= N.NNN	Combined Root Mean Squared Error (RMSE) of the geometric residuals (meters) in both across-track and along-track directions measured on the GCPs used in geometric precision correction. This parameter is only present if the DATA_TYPE is L1T.

Parameter Name	Value, Format, and Range	Parameter Description / Remarks
GEOMETRIC_RMSE_MODEL_Y	= N.NNN	The post-fit RMSE for the along-track direction. Units are in meters equal to or greater than zero, with no upper limit, and three decimal places. This parameter is only present if the DATA_TYPE is L1T.
GEOMETRIC_RMSE_MODEL_X	= N.NNN	The post-fit RMSE for the along-track direction. Units are in meters equal to or greater than zero, with no upper limit, and three decimal places. This parameter is only present if the DATA_TYPE is L1T.
GROUND_CONTROL_POINTS_VERIFY	=1-9999	Number of ground control points used in the verification of the terrain corrected product. This parameter is only present if it was calculated.
GEOMETRIC_RMSE_VERIFY	=0.000-9999.999	RMSE of the geometric residuals (meters) measured on the terrain-corrected product independently using GLS2000. This parameter is only present if it was calculated.
END_GROUP	= IMAGE_ATTRIBUTES	The end of the image attributes group.
GROUP	= MIN_MAX_RADIANCE	
RADIANCE_MAXIMUM_BAND_1	= NNN.NNNNN	Maximum achievable spectral radiance value for Band 1. This parameter is only present if this band is included in the product.
RADIANCE_MINIMUM_BAND_1	= NNN.NNNNN	Minimum achievable spectral radiance value for Band 1. This parameter is only present if this band is included in the product.
RADIANCE_MAXIMUM_BAND_2	= NNN.NNNNN	Maximum achievable spectral radiance value for Band 2. This parameter is only present if this band is included in the product.
RADIANCE_MINIMUM_BAND_2	= NNN.NNNNN	Minimum achievable spectral radiance value for Band 2. This parameter is only present if this band is included in the product.
RADIANCE_MAXIMUM_BAND_3	= NNN.NNNNN	Maximum achievable spectral radiance value for Band 3. This parameter is only present if this band is included in the product.
RADIANCE_MINIMUM_BAND_3	= NNN.NNNNN	Minimum achievable spectral radiance value for Band 3. This parameter is only present if this band is included in the product.
RADIANCE_MAXIMUM_BAND_4	= NNN.NNNNN	Maximum achievable spectral radiance value for Band 4. This parameter is only present if this band is included in the product.
RADIANCE_MINIMUM_BAND_4	= NNN.NNNNN	Minimum achievable spectral radiance value for Band 4. This parameter is only present if this band is included in the product.
RADIANCE_MAXIMUM_BAND_5	= NNN.NNNNN	Maximum achievable spectral radiance value for Band 5. This parameter is only present if this band is included in the product.
RADIANCE_MINIMUM_BAND_5	= NNN.NNNNN	Minimum achievable spectral radiance value for Band 5. This parameter is only present if this band is included in the product.
RADIANCE_MAXIMUM_BAND_6	= NNN.NNNNN	Maximum achievable spectral radiance value for Band 6. This parameter is only present if this band is included in the product.

Parameter Name	Value, Format, and Range	Parameter Description / Remarks
RADIANCE_MINIMUM_BAND_6	= NNN.NNNNN	Minimum achievable spectral radiance value for Band 6. This parameter is only present if this band is included in the product.
RADIANCE_MAXIMUM_BAND_7	= NNN.NNNNN	Maximum achievable spectral radiance value for Band 7. This parameter is only present if this band is included in the product.
RADIANCE_MINIMUM_BAND_7	= NNN.NNNNN	Minimum achievable spectral radiance value for Band 7. This parameter is only present if this band is included in the product.
RADIANCE_MAXIMUM_BAND_8	= NNN.NNNNN	Maximum achievable spectral radiance value for Band 8. This parameter is only present if this band is included in the product.
RADIANCE_MINIMUM_BAND_8	= NNN.NNNNN	Minimum achievable spectral radiance value for Band 8. This parameter is only present if this band is included in the product.
RADIANCE_MAXIMUM_BAND_9	= NNN.NNNNN	Maximum achievable spectral radiance value for Band 9. This parameter is only present if this band is included in the product.
RADIANCE_MINIMUM_BAND_9	= NNN.NNNNN	Minimum achievable spectral radiance value for Band 9. This parameter is only present if this band is included in the product.
RADIANCE_MAXIMUM_BAND_10	= NNN.NNNNN	Maximum achievable spectral radiance value for Band 10. This parameter is only present if this band is included in the product.
RADIANCE_MINIMUM_BAND_10	= NNN.NNNNN	Minimum achievable spectral radiance value for Band 10. This parameter is only present if this band is included in the product.
RADIANCE_MAXIMUM_BAND_11	= NNN.NNNNN	Maximum achievable spectral radiance value for Band 11. This parameter is only present if this band is included in the product.
RADIANCE_MINIMUM_BAND_11	= NNN.NNNNN	Minimum achievable spectral radiance value for Band 11. This parameter is only present if this band is included in the product.
END_GROUP	= MIN_MAX_RADIANCE	
GROUP	= MIN_MAX_REFLECTANCE	Minimum and maximum reflectance values for the OLI bands. This group will only be present if there are OLI bands present in the product.
REFLECTANCE_MAXIMUM_BAND_1	= N.NNNNNN	Maximum achievable reflectance value for Band 1. This parameter is only present if this band is included in the product.
REFLECTANCE_MINIMUM_BAND_1	= N.NNNNNN	Minimum achievable reflectance value for Band 1. This parameter is only present if this band is included in the product.
REFLECTANCE_MAXIMUM_BAND_2	= N.NNNNNN	Maximum achievable reflectance value for Band 2. This parameter is only present if this band is included in the product.
REFLECTANCE_MINIMUM_BAND_2	= N.NNNNNN	Minimum achievable reflectance value for Band 2. This parameter is only present if this band is included in the product.
REFLECTANCE_MAXIMUM_BAND_3	= N.NNNNNN	Maximum achievable reflectance value for Band 3. This parameter is only present if this band is included in the product.

Parameter Name	Value, Format, and Range	Parameter Description / Remarks
REFLECTANCE_MINIMUM_BAND_3	= N.NNNNNN	Minimum achievable reflectance value for Band 3. This parameter is only present if this band is included in the product.
REFLECTANCE_MAXIMUM_BAND_4	= N.NNNNNN	Maximum achievable reflectance value for Band 4. This parameter is only present if this band is included in the product.
REFLECTANCE_MINIMUM_BAND_4	= N.NNNNNN	Minimum achievable reflectance value for Band 4. This parameter is only present if this band is included in the product.
REFLECTANCE_MAXIMUM_BAND_5	= N.NNNNNN	Maximum achievable reflectance value for Band 5. This parameter is only present if this band is included in the product.
REFLECTANCE_MINIMUM_BAND_5	= N.NNNNNN	Minimum achievable reflectance value for Band 5. This parameter is not present if this band is not included in the product.
REFLECTANCE_MAXIMUM_BAND_6	= N.NNNNNN	Maximum achievable reflectance value for Band 6. This parameter is only present if this band is included in the product.
REFLECTANCE_MINIMUM_BAND_6	= N.NNNNNN	Minimum achievable reflectance value for Band 6. This parameter is only present if this band is included in the product.
REFLECTANCE_MAXIMUM_BAND_7	= N.NNNNNN	Maximum achievable reflectance value for Band 7. This parameter is only present if this band is included in the product.
REFLECTANCE_MINIMUM_BAND_7	= N.NNNNNN	Minimum achievable reflectance value for Band 7. This parameter is only present if this band is included in the product.
REFLECTANCE_MAXIMUM_BAND_8	= N.NNNNNN	Maximum achievable reflectance value for Band 8. This parameter is only present if this band is included in the product.
REFLECTANCE_MINIMUM_BAND_8	= N.NNNNNN	Minimum achievable reflectance value for Band 8. This parameter is only present if this band is included in the product.
REFLECTANCE_MAXIMUM_BAND_9	= N.NNNNNN	Maximum achievable reflectance value for Band 9. This parameter is only present if this band is included in the product.
REFLECTANCE_MINIMUM_BAND_9	= N.NNNNNN	Minimum achievable reflectance value for Band 9. This parameter is only present if this band is included in the product.
END_GROUP	= MIN_MAX_REFLECTANCE	
GROUP	= MIN_MAX_PIXEL_VALUE	
QUANTIZE_CAL_MAX_BAND_1	= 1-65535	Maximum possible pixel value for Band 1. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MIN_BAND_1	= 0-1	Minimum possible pixel value for Band 1. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MAX_BAND_2	= 1-65535	Maximum possible pixel value for Band 2. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MIN_BAND_2	= 0-1	Minimum possible pixel value for Band 2. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MAX_BAND_3	= 1-65535	Maximum possible pixel value for Band 3. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MIN_BAND_3	= 0-1	Minimum possible pixel value for Band 3. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MAX_BAND_4	= 1-65535	Maximum possible pixel value for Band 4. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MIN_BAND_4	= 0-1	Minimum possible pixel value for Band 4. This parameter is only present if this band is included in the product.

Parameter Name	Value, Format, and Range	Parameter Description / Remarks
QUANTIZE_CAL_MAX_BAND_5	= 1-65535	Maximum possible pixel value for Band 5. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MIN_BAND_5	= 0-1	Minimum possible pixel value for Band 5. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MAX_BAND_6	= 1-65535	Maximum possible pixel value for Band 6. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MIN_BAND_6	= 0-1	Minimum possible pixel value for Band 6. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MAX_BAND_7	= 1-65535	Maximum possible pixel value for Band 7. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MIN_BAND_7	= 0-1	Minimum possible pixel value for Band 7. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MAX_BAND_8	= 1-65535	Maximum possible pixel value for Band 8. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MIN_BAND_8	= 0-1	Minimum possible pixel value for Band 8. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MAX_BAND_9	= 1-65535	Maximum possible pixel value for Band 9. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MIN_BAND_9	= 0-1	Minimum possible pixel value for Band 9. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MAX_BAND_10	= 1-65535	Maximum possible pixel value for Band 10. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MIN_BAND_10	= 0-1	Minimum possible pixel value for Band 10. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MAX_BAND_11	= 1-65535	Maximum possible pixel value for Band 11. This parameter is only present if this band is included in the product.
QUANTIZE_CAL_MIN_BAND_11	= 0-1	Minimum possible pixel value for Band 11. This parameter is only present if this band is included in the product.
END_GROUP	= MIN_MAX_PIXEL_VALUE	
GROUP	= RADIOMETRIC_RESCALING	The beginning of the radiometric rescaling group. The parameter for a band is only included if that band is present in the product.
RADIANCE_MULT_BAND_1	= N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Radiance units for Band 1 ( $W/(m^2 \text{ sr } \mu m)/DN$ ).
RADIANCE_MULT_BAND_2	= N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Radiance units for Band 2 ( $W/(m^2 \text{ sr } \mu m)/DN$ ).
RADIANCE_MULT_BAND_3	= N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Radiance units for Band 3 ( $W/(m^2 \text{ sr } \mu m)/DN$ ).
RADIANCE_MULT_BAND_4	= N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Radiance units for Band 4 ( $W/(m^2 \text{ sr } \mu m)/DN$ ).
RADIANCE_MULT_BAND_5	= N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Radiance units for Band 5 ( $W/(m^2 \text{ sr } \mu m)/DN$ ).
RADIANCE_MULT_BAND_6	= N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Radiance units for Band 6 ( $W/(m^2 \text{ sr } \mu m)/DN$ ).

Parameter Name	Value, Format, and Range	Parameter Description / Remarks
RADIANCE_MULT_BAND_7	= N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Radiance units for Band 7 (W/(m <sup>2</sup> sr um)/DN).
RADIANCE_MULT_BAND_8	= N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Radiance units for Band 8 (W/(m <sup>2</sup> sr um)/DN).
RADIANCE_MULT_BAND_9	= N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Radiance units for Band 9 (W/(m <sup>2</sup> sr um)/DN).
RADIANCE_MULT_BAND_10	= N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Radiance units for Band 10 (W/(m <sup>2</sup> sr um)/DN).
RADIANCE_MULT_BAND_11	= N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Radiance units for Band 11 (W/(m <sup>2</sup> sr um)/DN).
RADIANCE_ADD_BAND_1	= NN.NNNNN	The additive rescaling factor used to convert calibrated DN to Radiance units for Band 1 (W/(m <sup>2</sup> sr um)).
RADIANCE_ADD_BAND_2	= NN.NNNNN	The additive rescaling factor used to convert calibrated DN to Radiance units for Band 2 (W/(m <sup>2</sup> sr um)).
RADIANCE_ADD_BAND_3	= NN.NNNNN	The additive rescaling factor used to convert calibrated DN to Radiance units for Band 3 (W/(m <sup>2</sup> sr um)).
RADIANCE_ADD_BAND_4	= NN.NNNNN	The additive rescaling factor used to convert calibrated DN to Radiance units for Band 4 (W/(m <sup>2</sup> sr um)).
RADIANCE_ADD_BAND_5	= NN.NNNNN	The additive rescaling factor used to convert calibrated DN to Radiance units for Band 5 (W/(m <sup>2</sup> sr um)).
RADIANCE_ADD_BAND_6	= NN.NNNNN	The additive rescaling factor used to convert calibrated DN to Radiance units for Band 6 (W/(m <sup>2</sup> sr um)).
RADIANCE_ADD_BAND_7	= NN.NNNNN	The additive rescaling factor used to convert calibrated DN to Radiance units for Band 7 (W/(m <sup>2</sup> sr um)).
RADIANCE_ADD_BAND_8	= NN.NNNNN	The additive rescaling factor used to convert calibrated DN to Radiance units for Band 8 (W/(m <sup>2</sup> sr um)).
RADIANCE_ADD_BAND_9	= NN.NNNNN	The additive rescaling factor used to convert calibrated DN to Radiance units for Band 9 (W/(m <sup>2</sup> sr um)).
RADIANCE_ADD_BAND_10	=NN.NNNNN	The additive rescaling factor used to convert calibrated DN to Radiance units for Band 10 (W/(m <sup>2</sup> sr um)).
RADIANCE_ADD_BAND_11	=NN.NNNNN	The additive rescaling factor used to convert calibrated DN to Radiance units for Band 11 (W/(m <sup>2</sup> sr um)).
REFLECTANCE_MULT_BAND_1	=N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Reflectance for Band 1 (DN <sup>-1</sup> ).
REFLECTANCE_MULT_BAND_2	=N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Reflectance for Band 2 (DN <sup>-1</sup> ).
REFLECTANCE_MULT_BAND_3	=N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Reflectance for Band 3 (DN <sup>-1</sup> ).
REFLECTANCE_MULT_BAND_4	=N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Reflectance for Band 4 (DN <sup>-1</sup> ).
REFLECTANCE_MULT_BAND_5	=N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Reflectance for Band 5 (DN <sup>-1</sup> ).

Parameter Name	Value, Format, and Range	Parameter Description / Remarks
REFLECTANCE_MULT_BAND_6	=N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Reflectance for Band 6 (DN <sup>-1</sup> ).
REFLECTANCE_MULT_BAND_7	=N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Reflectance for Band 7 (DN <sup>-1</sup> ).
REFLECTANCE_MULT_BAND_8	=N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Reflectance for Band 8 (DN <sup>-1</sup> ).
REFLECTANCE_MULT_BAND_9	=N.NNNNeNN	The multiplicative rescaling factor used to convert calibrated DN to Reflectance for Band 9 (DN <sup>-1</sup> ).
REFLECTANCE_ADD_BAND_1	=N.NNNNNN	The additive rescaling factor used to convert calibrated DN to Reflectance for Band 1.
REFLECTANCE_ADD_BAND_2	=N.NNNNNN	The additive rescaling factor used to convert calibrated DN to Reflectance for Band 2.
REFLECTANCE_ADD_BAND_3	=N.NNNNNN	The additive rescaling factor used to convert calibrated DN to Reflectance for Band 3.
REFLECTANCE_ADD_BAND_4	=N.NNNNNN	The additive rescaling factor used to convert calibrated DN to Reflectance for Band 4.
REFLECTANCE_ADD_BAND_5	=N.NNNNNN	The additive rescaling factor used to convert calibrated DN to Reflectance for Band 5.
REFLECTANCE_ADD_BAND_6	=N.NNNNNN	The additive rescaling factor used to convert calibrated DN to Reflectance for Band 6.
REFLECTANCE_ADD_BAND_7	=N.NNNNNN	The additive rescaling factor used to convert calibrated DN to Reflectance for Band 7.
REFLECTANCE_ADD_BAND_8	=N.NNNNNN	The additive rescaling factor used to convert calibrated DN to Reflectance for Band 8.
REFLECTANCE_ADD_BAND_9	=N.NNNNNN	The additive rescaling factor used to convert calibrated DN to Reflectance for Band 9.
END_GROUP	= RADIOMETRIC_RESCALING	The end of the radiometric rescaling group.
GROUP	= TIRS_THERMAL_CONSTANTS	The beginning of the TIRS thermal constants group. This group is included only with products that include TIRS data. Note: Temperature in degrees Kelvin = K2/(ln(K1/Radiance + 1)).
K1_CONSTANT_BAND_10	= N.NN	K1 coefficient for Band 10 radiance to temperature conversion.
K1_CONSTANT_BAND_11	= N.NN	K1 coefficient for Band 11 radiance to temperature conversion.
K2_CONSTANT_BAND_10	= N.NN	K2 coefficient for Band 10 radiance to temperature conversion.
K2_CONSTANT_BAND_11	= N.NN	K2 coefficient for Band 11 radiance to temperature conversion.
END_GROUP	= TIRS_THERMAL_CONSTANTS	The end of TIRS thermal constants group.
GROUP	= PROJECTION_PARAMETERS	The beginning of the projection parameters group.
MAP_PROJECTION	= "UTM" = "PS"	The map projection used in creating the image. Universal Transverse Mercator (UTM) or Polar Stereographic (PS).
DATUM	= "WGS84"	The datum used in creating the image.
ELLIPSOID	= "WGS84"	The ellipsoid used in creating the image.
UTM_ZONE	= 1 to 60	The value used to indicate the zone number. This parameter is only included for the UTM projection.



Parameter Name	Value, Format, and Range	Parameter Description / Remarks
VERTICAL_LON_FROM_POLE	= 0.00000	The vertical longitude from the pole. This parameter is only included for the polar stereographic projection.
TRUE_SCALE_LAT	= -71.00000 = 71.00000	The latitude of true scale. A value of -71 is used for scenes over Antarctica and 71 is used for off-nadir scenes at the North Pole. This parameter is only included for the polar stereographic projection.
FALSE_EASTING	= 0	False easting in meters. This parameter is only included for the polar stereographic projection.
FALSE_NORTHING	= 0	False northing in meters. This parameter is only included for the polar stereographic projection.
GRID_CELL_SIZE_PANCHROMATIC	= 15.00	The grid cell size in meters used in creating the image for the panchromatic band, if part of the product. This parameter will only be included if the panchromatic band is included in the product.
GRID_CELL_SIZE_REFLECTIVE	= 30.00	The grid cell size in meters used in creating the image for Visible and Near Infrared (VNIR)/ Short-Wave Infrared (SWIR) bands, if part of the product. This parameter will only be included if the reflective bands are included in the product.
GRID_CELL_SIZE_THERMAL	= 30.00	The grid cell size in meters used in creating the image for the thermal bands, if part of the product. This parameter will only be included if the thermal bands are included in the product.
ORIENTATION	= "NORTH_UP" = "NOMINAL"	The orientation used in creating the image.
RESAMPLING_OPTION	= "CUBIC_CONVOLUTION"	The resampling option used in creating the image. Cubic Convolution (CC).
END_GROUP	= PROJECTION_PARAMETERS	The end of the projection parameters group.
END_GROUP	= L1_METADATA_FILE	The end of the Level 1 metadata file level group.
END		Required standalone parameter signifying the file end.

**Table 2-4. L1Gt / L1T Metadata File**

## References

---

Please see [http://landsat.usgs.gov/tools\\_acronyms\\_ALL.php](http://landsat.usgs.gov/tools_acronyms_ALL.php) for a list of acronyms.

EPSG Geodetic Parameter Registry. Version 7.4. <<http://www.epsg-registry.org>>.

GeoTIFF Specification Version 1.8.2. December 28, 2000.  
<<http://www.remotesensing.org/geotiff/spec/geotiffhome.html>>.

Landsat Remote Sensing Strategy. PDD NSTC-3.

Public Law 102-555. Land Remote Sensing Policy Act of 1992.

U.S. Code Title 15, Chapter 82. Land Remote Sensing Policy.

USGS/EROS. LS-IC-04. Landsat Ground Station (GS) Identifiers.

USGS/EROS. LDCM-ADEF-001. Landsat Data Continuity Mission (LDCM) Calibration and Validation (Cal/Val) Algorithm Description Document (ADD).

USGS/EROS. LDCM-DFCB-005. Landsat Data Continuity Mission (LDCM) Calibration Parameter File (CPF) Data Format Control Book (DFCB).

USGS/EROS. LDCM-DFCB-006. Landsat Data Continuity Mission (LDCM) Bias Parameter File (BPF) Data Format Control Book (DFCB).

USGS/EROS. LDCM-POL-002. Landsat Data Continuity Mission (LDCM) Development Configuration Control Board (CCB) Process Document.